


FlexNet Operations

User Guide



Legal Information

Book Name: FlexNet Operations User Guide (UAT)
Part Number: FNO-2024.05UAT-UGO
Product Release Date: May 2024

Copyright Notice

Copyright © 2024 Flexera Software

This publication contains proprietary and confidential information and creative works owned by Flexera Software and its licensors, if any. Any use, copying, publication, distribution, display, modification, or transmission of such publication in whole or in part in any form or by any means without the prior express written permission of Flexera Software is strictly prohibited. Except where expressly provided by Flexera Software in writing, possession of this publication shall not be construed to confer any license or rights under any Flexera Software intellectual property rights, whether by estoppel, implication, or otherwise.

All copies of the technology and related information, if allowed by Flexera Software, must display this notice of copyright and ownership in full.

FlexNet Operations incorporates software developed by others and redistributed according to license agreements. Copyright notices and licenses for these external libraries are provided in a supplementary document that accompanies this one.

Intellectual Property

For a list of trademarks and patents that are owned by Flexera Software, see <https://www.reverera.com/legal/intellectual-property.html>. All other brand and product names mentioned in Flexera Software products, product documentation, and marketing materials are the trademarks and registered trademarks of their respective owners.

Restricted Rights Legend

The Software is commercial computer software. If the user or licensee of the Software is an agency, department, or other entity of the United States Government, the use, duplication, reproduction, release, modification, disclosure, or transfer of the Software, or any related documentation of any kind, including technical data and manuals, is restricted by a license agreement or by the terms of this Agreement in accordance with Federal Acquisition Regulation 12.212 for civilian purposes and Defense Federal Acquisition Regulation Supplement 227.7202 for military purposes. The Software was developed fully at private expense. All other use is prohibited.

Contents

- 1 FlexNet Operations User Guide 31**
 - Introduction to FlexNet Operations 32**
 - FlexNet Operations Home Page 34**
 - FlexNet Operations Environments 34**
 - User Acceptance Testing (UAT) 35
 - Production (PROD) 35
 - About Download Management and FlexNet Electronic Software Delivery 36**
 - About FlexNet Usage Management 38**
 - Product Support Resources 38**
 - Contact Us 39**

- 2 Packaging Products 43**
 - About Packaging Products 44**
 - About Trial Products 47
 - About Download Management: FlexNet Electronic Software Delivery Components 48
 - Working with Features 49**
 - About Features 49
 - Viewing Features 49
 - Creating a Feature 50
 - Using Feature Count Aggregation 55**
 - Reviewing Features 56
 - Working with Feature Bundles 56**
 - About Feature Bundles 57
 - Viewing Feature Bundles 57
 - Creating a Feature Bundle 58
 - Reviewing Feature Bundles 59
 - Deploying a Feature Bundle 59
 - Working with Products 60**

- About Products 61
- Viewing Products..... 62
- Creating a Product..... 63
 - FlexNet Publisher Versions for Cross-Version Signature Support..... 69
- Adding Features or Feature Bundles to a Product..... 70
- Linking License Models to a Product..... 71
- Mapping a Product to a Part Number..... 72
- Relating Products to Other Products..... 73
- Mapping a Product to a Product Line..... 75
- Reviewing Products..... 76
- Deploying a Product..... 76
- Reviewing New Product Hierarchy..... 76
- Working with Suites..... 76**
 - Viewing Suites..... 77
 - Creating a Suite..... 77
 - Adding Products to a Suite..... 81
 - Linking License Models to a Suite..... 82
 - Mapping a Suite to a Part Number..... 83
 - Relating Suites to Other Products..... 84
 - Deploying a Suite..... 85
- Working with Maintenances..... 86**
 - Creating a Maintenance..... 86
 - Mapping a Maintenance to a Part Number..... 88
 - Relating Maintenance to Other Products..... 88
- Managing Part Numbers..... 89**
 - Adding Part Numbers..... 90
 - Deleting Part Numbers..... 91
 - Mapping Part Numbers..... 91
 - Importing Part Numbers..... 91
- Managing Product Lines..... 91**
 - Enabling Product Lines..... 92
 - Adding Product Lines and Product Line Attributes..... 94
 - Deleting Product Lines or Product Line Attributes..... 94
- Working with Updates..... 95**
 - About Updates..... 95
 - Updates and Security..... 96
 - Viewing Updates..... 96
 - Creating or Modifying an Update..... 97
 - Update Overview..... 98
 - Update Release From..... 99
 - Update Release To..... 100
 - Update Languages..... 101
- Managing Download Packages..... 102**
 - About Download Packages..... 103
 - About Download Package Attributes..... 105

About Download Package Restrictions	107
About Physical Distribution and Order Media Requests	109
About Export Compliance	109
Creating a Download Package	113
Searching for a Download Package	116
Viewing Download Package Information	117
Viewing this Download Package	118
Viewing Where a Download Package Is Used	118
Viewing Download Package Restrictions	118
Viewing Emails Related to a Download Package	119
Viewing Download Package Transactions	119
Viewing Download Packages of a Product	120
Editing Download Package Information	120
Editing a Download Package	121
Editing a Download Package File List	122
Reidentifying a Download Package	122
Restricting a Download Package	123
Creating an Email Notification for a Download Package	125
Copying Download Packages	126
Copying a Download Package with Files	127
Copying a Download Package without Files	128
Managing Download Package Associations	128
About Download Package Associations	129
Associating a Download Package to a Product	129
Disassociating a Download Package from a Product	131
Associating a Download Package to Files	132
Disassociating a Download Package from Files	132
Managing Containerized Applications	133
About Containerized Applications	134
Working with the Revenera Registry	134
About the Revenera Registry	134
Accessing the Revenera Registry	135
About Projects in the Revenera Registry	137
About Users in the Revenera Registry	137
About Entitlement and Security Checks in the Revenera Registry	138
Distributing Containerized Applications	138
Preparing a Download Package in FlexNet Operations	139
Uploading Containerized Applications	143
Downloading Containerized Applications	144
Viewing Containerized Applications	145
Identifying Syntax for “pull” Command	146
Identifying Syntax for “helm repo add” Command	146
Managing Download Files	147
About Files and File Images	148
About File Attributes	151
About Aliases	154

- About File Restrictions 154
- Adding Files 155
- Searching for Files 156
- Viewing File Information 158
 - Viewing this File 158
 - Viewing Where a File Is Used 159
 - Viewing File Restrictions 159
 - Viewing Emails Related to a File 159
 - Viewing File Transactions 160
 - Viewing File Downloads 160
- Editing File Information 161
 - Editing a File 161
 - Aliasing a File 163
 - Uploading a File Image 164
 - Deleting a File Image 165
 - Reidentifying a File 165
 - Restricting a File 166
 - Creating an Email Notification for a File 166
- Managing File Associations 168
 - About File Associations 169
 - Associating a File to Download Packages 170
 - Using Associate Where to Copy Associations from Another File 171
 - Disassociating a File from a Download Package 172
- Managing License Agreements 172**
 - About Agreements 173
 - Listing Agreements 173
 - Creating an Agreement 174
 - Viewing an Agreement’s Transactions 174
 - Editing an Agreement 175
- Managing Producers 175**
 - About Producers 176
 - Listing Producers 176
 - Creating a Producer 177
 - Viewing a Producer’s Transactions 177
 - Editing a Producer 177
 - Reidentifying a Producer 178
 - Deactivating a Producer 178
 - Reactivating a Producer 179
- 3 Entitling Customers and Activating Licenses 181**
 - Entitling Customers to Licenses 181**
 - Entitlement Terms 182
 - What is an Entitlement? 183
 - What is an Entitlement Line Item? 183
 - What is a Bulk Entitlement? 184
 - What is an Upgrade? 184

What is a Test Upgrade?	185
What is an Upsell?	185
What is a Test Upsell?	186
What is a Renewal?	186
What is a Test Renewal?	186
What is a Merge?	186
What is a Transfer?	187
Viewing Entitlements	187
Creating an Entitlement	189
Configuring an Entitlement Line Item	191
Configuring a Maintenance Line Item	193
Changing the State of a Line Item	194
Deleting an Entitlement Line Item	194
Creating a Bulk Entitlement	195
Configuring a Bulk Entitlement	196
Loading Web Register Keys	198
Adding a Web Register Key	199
Deleting a Web Register Key	199
Specifying User-Supplied Web Register Keys	200
Bulk Operations: Upgrade, Upsell, or Renew a Product	200
Verifying the Status of a Bulk Operation	204
Emailing Bulk Operation Notifications	204
Merging Entitlements	205
Transferring Entitlements	206
Transfer Entitlements Wizard	207
Viewing Fulfillment History	207
Viewing Custom Attributes	208
Activating Licenses	209
Activation Terms	209
What is a License?	210
What is Activation?	210
What is the Activatable Line Item Type?	210
What is an Activation ID?	210
What is Batch Activation?	211
What is License Consolidation?	211
Viewing Entitlements to Activate	212
Emailing an Entitlement Line Item	214
Activating a License	214
Activate Licenses Wizard	215
Trusted Activate Wizard	217
Specifying Host IDs	218
Configuring Hosts in the Trusted Activate Wizard	220
Special Host ID Types	220
Configuring Counts	225
Configuring Counts for Trusted Activation	227
Reviewing Activations and Generating Licenses	228

Transferring Entitlement Line Items	229
Transfer Entitlement Line Item Wizard	229
Emailing a License	230
Manual Activations	230
Viewing a Manual Activation Response	231
Short Code Activations	231
Viewing a Short Code Activation Response	232
4 Supporting Licenses	233
Support Licenses Terminology	234
What is a Fulfillment?	234
What is a License Return?	234
What is a License Repair?	234
What is a License Rehost?	235
What is an Emergency License?	235
What is a Stop Gap License?	235
What is Support Type?	236
Viewing Fulfillment Records	236
Returning a License	238
Repairing a License	239
Rehosting a License	240
Generating an Emergency License	240
Correcting a Publisher Error in a License	241
Upgrade, Upsell, or Renew a Fulfillment	242
Using the SUPERSEDE and SUPERSEDE_SIGN Keywords	246
<i>Considerations When Using SUPERSEDE or SUPERSEDE_SIGN.</i>	246
<i>Example of Using SUPERSEDE</i>	248
<i>Example of Using SUPERSEDE_SIGN.</i>	250
<i>Configuring the SUPERSEDE or SUPERSEDE_SIGN Keyword.</i>	253
Generating a Stop Gap License	253
Consolidating Licenses	254
Consolidated Licenses Page	255
Rehosting a Consolidated License	256
Batch Rehosting	256
Transferring Licenses	256
Manual Return	257
Viewing a Manual Return	257
Manual Repair	258
Viewing a Manual Repair	258
Short Code Return	259
Viewing a Short Code Return	260
Short Code Repair	260
Viewing a Short Code Repair	261
Supporting Hosts	261
Transferring Hosts	262
Supporting Embedded Licenses	262

Return Material Authorizations (RMAs)	263
Upgrades, Renewals, and Upsells.	263
Transfers	265
Temporary (Emergency and Stop-Gap) Licenses	266
Supporting Offline Device Activation	267
Offline Activation: Generating a License	267
Offline Activation: Downloading a Pre-Installed License	268
Offline Activation: Downloading an Additional License	268
5 Managing Devices	271
About Device Management	273
About Standalone Devices, Servers, and Served Devices	274
About Device Ownership	274
About Device Attributes.	278
About Server Attributes	280
About Device Status.	282
About Overriding the Expiration Date of an Entitlement	282
About the Device–Device User Association	283
Listing Devices	284
Filtering the Devices List	285
Previewing Licenses on a Device	285
Searching for Devices.	286
Viewing Devices	287
Viewing this Device	288
Viewing a Server’s Binding-Break Status	289
Viewing a Server’s Served Devices	289
Viewing Device History	289
Viewing Device Requests	290
Viewing a Vendor Dictionary for a Device	290
Downloading a License File for a Device	290
Viewing a License File for a Device.	291
Downloading a Response for a Device Request.	291
Viewing a Response for a Device Request	292
Viewing Standalone Device Updates	292
Creating Devices	293
Editing Devices	295
Editing Device Attributes.	296
Adding a Pre-installed Product to a Device	297
Assigning an Account to a Device.	298
Associating a Device with a Device User	298
Returning a Device.	299
Moving a Device.	300
Making a Device Obsolete	301
Working with Licenses on a Device.	302
Mapping an Entitlement	302

Mapping Entitlements by Activation IDs	303
Removing Licenses	304
Supporting Devices	305
Generating a License File	306
Generating a Capability Response	306
Uploading a Capability Request from the Device Page	306
Offline Device Management	307
Uploading a Capability Request from the Offline Device Management Page	307
Uploading Synchronization History	308
6 Managing Usage	309
About Usage Management	310
Usage Management Concepts	310
About Usage Models	311
About Usage Reports	313
Usage Gauges	313
Usage Tables	314
Usage Timelines and Comparisons	314
Viewing Usage Reports	315
Listing Usage Models	316
Uploading Usage Data	317
7 Managing Accounts and Users	319
Managing Users	320
About Users	321
FlexNet Operations Default Users	322
Managing Your Profile	322
Editing Your User Profile	323
Changing Your FlexNet Password	324
If You Forget Your FlexNet Password	324
Finding Your Container Registry Secret	325
Browsing Users	325
Creating a User	326
Editing a User	328
Linking Product Lines to User Accounts	330
Deleting a User	330
Deactivating and Reactivating a User	331
Working with Roles and Permissions	332
Assigning a Role to a User	333
Browsing Roles	333
Browsing Users with a Role	334
Adding a Role	334
Editing a Role	335
Deleting a Role	336
Deactivating and Reactivating a Role	336

- FlexNet Operations Permissions 336
 - Alert Management 337
 - System Administration 338
 - Operations Feature Bundles 338
 - Operations License Models 339
 - Operations Entitlements (Producer Portal) 340
 - Accounts (End-User Portal) 341
 - Trusted Storage Licensing (End-User Portal) 343
 - Operations Web Services 343
 - Operations Export Import 344
 - User Management 344
 - Account Management 345
 - Operations Features 345
 - Operations Products, Suites, and Maintenance 346
 - Operations Part Numbers (Producer Portal) 348
 - Operations License Management (Producer Portal) 348
 - Operations Policies 349
 - Operations Trusted Storage Licensing (Producer Portal) 350
 - Reporting 351
 - Child Account (End-User Portal) 351
 - License Technologies 352
 - FlexNet Embedded 353
 - FlexNet Embedded (End-User Portal) 353
 - Customer Growth 354
 - Usage 354
 - Updates 354
- FlexNet Operations Permission Dependencies 354
- FlexNet Operations Roles 359
 - Producer User Roles 360
 - End-User Customer Roles 373
- Managing Accounts 377**
 - About Accounts 377
 - Default Accounts 378
 - Account Types 379
 - Partners and Distribution Tiers 380
 - Browsing Accounts or Sub-Accounts 380
 - Creating a New Account 381
 - Editing an Account or Sub-Account 383
 - Deleting an Account 384
- Account Health 385**
 - Customer Growth Dashboard 386
 - Alert List 387
 - Listing Account Alerts 387
 - Filtering Accounts Alerts 387
 - Accounts 388
 - Listing Accounts 389

- Filtering the Account List 390
- Account Health Overview 390
- Account Product Health 391
- Account Renewal Health 392
- Account Alerts 394

- 8 Analyzing Usage and Entitlement Data (Early Access) 397**
- Understanding Data Freshness 398**
- Setting Up Conditional Notifications Based on Data Changes 399**
- Types of Conditional Notifications 400
- Components for Conditional Notifications 400
- Metrics 401
 - Metrics Overview 401
 - Building a Metric 404
- Triggers 404
 - Scheduling 405
 - New Data 405
 - Update Data 405
- Conditions 406
 - Adding Conditions 406
 - Types of Conditions 406
 - Using Conditions 407
- Send Actions 407
 - Send to Webhook 407
 - Send Email 408
 - Data Action: Submit Data 409
- Viewing Conditional Notifications 410
- Creating Conditional Notifications 410
 - Creating a Conditional Notification 411
 - Configuring a Conditional Notification 411
 - Activating a Conditional Notification 412
- Editing a Conditional Notification 413
- Deleting Conditional Notifications 413
- Conditional Notification Activity Log 413
- Example Walkthroughs for Conditional Notifications 414
 - Use Case: Send Notification When an Account Is Created in a Specific Region (Field Value) 414
 - Creating the Notification of Type “Field Value” 414
 - Defining the Conditions for the Field to Compare 415
 - Use Case: Send Notification when Number of Feature Requests Exceeds Threshold (Aggregate Values) 417
 - Creating the Notification of Type “Aggregate Value” 417
 - Defining the Conditions for the Metric to Compare 418
 - Scheduling the Notification With Threshold 420
- Using Analytics Reports to Explore Customer Data 422**
- Data Flow for Data Analytics 422
- Analytics Dashboard 423
 - Actions in the Analytics Dashboard 424

- Tiles in the Analytics Dashboard 426
- Charts in the Analytics Dashboard 426
 - Renewal: Active Accounts by Business Region* 427
 - Fulfillment: Total vs Available Quantity Per Product* 440
 - Top Products by Standalone Devices* 440
 - Top Feature Requests by Served Devices* 441
- Reports 442
 - Renewals Report 443
 - Attributes for Renewals Report* 444
 - Sample of Renewals Report* 445
 - Fulfillment Report 445
 - Attributes for Fulfillment Report* 445
 - Sample of Fulfillment Report* 447
 - Accounts Created Report 447
 - Entitlement Line Items Created Report 449
 - High-Water Mark Report 452
 - Charts in the High-Water Mark Report* 452
 - Attributes for High-Water Mark Report* 452
 - Sample of High-Water Mark Report* 453
 - Dropdown Filters in the High-Water Mark Report* 454
 - Drilldown in High-Water Mark Report* 454
- Downloading Data 455
- Sorting Data in Tables 456
- Drilldown Action in Charts 457
- Subscribing to Dashboards 457
 - Configuring Subscriptions 458
 - Managing Subscriptions 459
- Filtering Data 460**
 - Filter Hierarchy 460
 - Filter Logic 461
 - Layers 461
 - Columns 461
 - Values 462
 - Filter Panel 463
 - Condensed vs Expanded View 465
 - Including and Excluding Deleted Data in Dashboards 465
 - Viewing Filters Directly from Reports 466
 - Adding a Filter 466
 - Editing or Deleting a Filter 467
 - Defining a Filter 468
 - Using Tokens in Filters 471
 - Filtering Based On Relative Dates 472
 - “Dates” Versus “Date Names” 473
- Formulas 473**
 - Creating Formulas 474
 - The Formula Builder Interface 474

Data Engine Syntax Mode	475
Creating a Formula Using Data Engine Syntax Mode.....	476
Examples for Formulas Using Data Engine Syntax Mode	476
Data Engine Syntax	479
Functions Supported in Data Engine Syntax	480
Standardized Syntax Mode	482
Creating a Formula Using Standardized Syntax Mode.....	482
Testing a Formula in Standardized Syntax	483
Standardized Syntax Reference	483
Supported Functions in Standardized Syntax.....	485
Adding a Nested Formula	487
Editing, Duplicating, and Deleting Formulas	487
Bucketing Data	488
Creating Buckets	488
Managing Bucketed Columns.....	490
Tokens	490
Types of Tokens	491
Tokens Suggestion Box.....	491
Token Management.....	491
System Tokens	492
9 Branding the End-User Portal	495
About the Standard Branding Approach.....	495
About the Advanced Branding Approach	496
Overview of Producer-Configurable Branding Options	496
Branding-Specific Settings	497
Sample CSS, Header, and Footer Files	502
Sample Custom CSS File	502
Sample Header File	505
Sample Footer File	506
General Navigation Settings	506
Changing End-User Portal Settings.....	507
End-User Portal Page Structure	508
10 Getting Started with FlexNet Embedded Licensing	515
Introduction.....	516
Exercise Prerequisites.....	516
The License Lifecycle: FlexNet Embedded	516
FlexNet Embedded Licensing Key Concepts	517
Next Steps	519
FlexNet Embedded Licensing: Advanced Topics	519
Setup	520
Setup: Key Concepts	520
Setup: Exercises.....	521
Adding a Publisher and a Publisher Identity.....	521

Deploy the Embedded Counted License Model	522
Adding Product Features	522
Adding a Product	523
Deploying a Product	525
Entitling a Customer Account to a Product	525
Setup: Next Steps	527
Setup: Advanced Topics	527
Devices	527
Devices: Key Concepts	527
Devices: Exercises	529
Creating a Device	529
Mapping an Additional Product Entitlement to a Device	532
Claiming a Device and Mapping an Additional Product Entitlement	533
Activating a Device's Pre-Installed and Additional Product Licenses	534
Devices: Next Steps	536
Devices: Advanced Topics	536
License Servers	539
License Servers: Key Concepts	540
License Server: Exercises	541
Creating a FlexNet Embedded License Server	541
Mapping Additional Product Entitlements to a License Server	541
License Server: Advanced Topics	543
11 Getting Started with FlexNet Publisher Trusted Storage-Based Licensing	547
Introduction	547
Exercise Prerequisites	548
The License Lifecycle: FlexNet Publisher Trusted Storage-Based Licensing	548
FlexNet Publisher Licensing Toolkit	549
Configuring Your Machine for Trusted Storage	550
Next Steps	553
Trusted Storage License Activation	553
Trusted Storage License Activation Key Concepts	553
Trusted Storage License Models	553
Generating Trusted Storage Licenses	554
Activation Utilities	554
Online Activation	556
Trusted Storage License Activation Exercises	558
Client-Side Online Activation	559
Server-Side Online Activation	561
Local Online Activation	563
Trusted Storage License Activation Next Steps	565
Trusted Storage License Activation Advanced Topics	565
Trusted Storage License Support	565
Trusted Storage Key Concepts	566
Trusted Storage Exercises	567

Client-Side Online Return	567
Trusted Storage Advanced Topics	568
12 Getting Started with FlexNet Publisher License File-Based Licensing	571
Introduction	571
The License Lifecycle: FlexNet Publisher License File-Based Licensing	572
Certificate License Activation	573
Certificate License Activation Key Concepts	573
Certificate License Activation Exercises	574
Generating a Certificate License	574
Reviewing Fulfillment History after Activation	576
Certificate License Activation Next Steps	576
Certificate License Activation Advanced Topics	576
Certificate License Support	577
Certificate License Support Key Concepts	577
Certificate License Support Exercises	577
Returning a Certificate License	577
Reviewing Fulfillment History after a Return	578
Certificate License Support Advanced Topics	579
13 Getting Started with Non-FlexNet Licensing Technologies	581
Introduction	581
Non-FlexNet License Technologies	582
The License Lifecycle: Non-FlexNet Licensing Technologies	583
Exercise Prerequisites	583
External SOAP Service Technology	584
External SOAP Service Technology: Key Concepts	584
External SOAP Service Technology: License Technology Set-Up	585
External SOAP Service Technology: Setting Up and Deploying the License Technology	585
External SOAP Service Technology: Setting Up and Deploying the License Model	586
External SOAP Service Technology: Creating and Deploying the Product	587
External SOAP Service Technology: License Activation	588
External SOAP Service Technology: Entitling the Customer to the Product	588
External SOAP Service Technology: Activating the License	589
External SOAP Service Technology: License Support	591
External SOAP Service Technology: Repairing the License	592
External SOAP Service Technology: Returning the License	592
Manual Technology	593
Manual Technology: Key Concepts	593
Manual Technology: License Technology Set-Up	593
Manual Technology: Setting Up and Deploying the License Technology	594
Manual Technology: Setting Up and Deploying the License Model	595
Manual Technology: Creating and Deploying the Product	595
Manual Technology: License Activation	596
Manual Technology: Entitling the Customer to the Product	597

Manual Technology: Activating the License	598
Manual Technology: License Support	599
Manual Technology: Repairing the License	599
Manual Technology: Returning the License	600
Hands-Free Technology	601
Non-FlexNet Licensing Technologies: Advanced Topics	601
License Activation	602
License Support	602
14 Getting Started with Cloud Licensing Service	605
FlexNet Cloud Licensing Service Concepts	606
FlexNet Embedded Licensing	606
License Servers	606
Auto-Provisioning	606
Features	607
Capability Requests and Responses	607
Publishers and Publisher Identities	608
FlexNet Cloud Licensing Service Exercises	608
Prerequisites	609
Preparing FlexNet Operations	610
Cloud Licensing Service: Creating License Models	610
Cloud Licensing Service: Creating Features	613
Cloud Licensing Service: Creating Products	614
Cloud Licensing Service: Creating an Account and a User	617
Cloud Licensing Service: Entitling the Account	618
Cloud Licensing Service: Viewing the Auto-Provisioned License Server	620
Cloud Licensing Service: Obtaining the License Server URL	621
Cloud Licensing Service: Running a Served Client Example	621
15 Getting Started with Entitlement Management	623
Introduction	624
Exercise Prerequisites	624
The License Lifecycle: Entitlement Management	624
Account and User Creation	625
Account and User Creation Key Concepts	625
Account and User Creation Exercise Scenario	626
Account and User Creation Exercises	626
Creating a Producer User	626
Creating a Customer Account	626
Creating a Customer End User	627
Account and User Creation Next Steps	628
Account and User Creation Advanced Topics	628
Product Creation	628
Product Creation Key Concepts	629
Product Creation Exercises	630

- Deploying a License Technology and Model 630
- Creating a Product Line 631
- Creating a Product 632
- Linking a License Model to a Product 632
- Mapping a Product to a Product Line 633
- Deploying a Product 633
- Product Creation Next Steps 634
- Product Creation Advanced Topics 634
- Entitlement Creation 635**
- Entitlement Creation Key Concepts 635
- Entitlement Creation Exercises 639
 - Creating and Configuring an Entitlement 639
 - Deploying an Entitlement 640
 - Reviewing an Entitlement on the End-User Portal 641
- Entitlement Creation Next Steps 641
- Entitlement Creation Advanced Topics 642
- 16 Getting Started with Electronic Software Delivery 645**
- Introduction 646**
- Prerequisites 646
- The License Lifecycle: Electronic Software Delivery 646
- The Electronic Software Delivery Module 647
- About Electronic Software Delivery 649**
- Download Packages 649
- Download Files 649
- Containerized Applications 650
 - About the Revenera Registry 650
 - Accessing the Revenera Registry 651
 - About Projects in the Revenera Registry 652
 - Important Information for Open Registry Users 652
- License Agreements 652
- Producers and Product Lines 652
- Electronic Software Delivery Setup for Distributing Files 653**
- Before You Begin 654
- Creating a Producer 655
- Creating Download Packages 656
- Associating Download Packages with a Product 658
- Creating Download Files 659
- Associating Download Files with Download Packages 662
- Viewing and Downloading Files from the End-User Portal 663
- Electronic Software Delivery: Advanced Topics 666
- Electronic Software Delivery Setup for Containerized Applications 668**
- Prerequisites 668
- Creating a Download Package with Containerized Applications Support 669
- Associating the Download Package with a Product 671

Pushing Containerized Applications to the Registry	672
Viewing Containerized Applications in the End-User Portal	673
Pulling Docker Images and Helm Charts from the Registry	675
Logging in to the Revenera Registry	675
Downloading Docker Images	676
Downloading Helm Charts	676
17 Getting Started with Usage Management	677
FlexNet Usage Management Concepts	678
Usage Management	678
Metered Licensing	678
Products	679
Features	679
Capability Requests and Responses	679
License Servers	680
Local License Servers	680
Cloud Licensing Service Instances	680
Auto-Provisioning	680
Usage Dashboard	681
Usage Gauges	682
Usage Tables	682
Usage Timelines	682
FlexNet Usage Management Exercises	683
Prerequisites	684
Preparing FlexNet Operations	684
Usage Management: Creating License Models	685
Usage Management: Creating Features	688
Usage Management: Creating a Product Line	689
Usage Management: Creating Products	690
Usage Management: Creating an Account and User	692
Usage Management: Entitling the Account	693
Usage Management: Viewing the Auto-Provisioned License Server	695
Usage Management: Obtaining the License Server URL	696
Usage Management: Running a Usage-Capture Client Example	697
Usage Management: Viewing Usage Information	697
Usage Management: Next Steps	698
Advanced FlexNet Usage Management Activities	699
Manually Creating a License Server	699
Uploading Historical Usage	701
Reconciliation Summaries	701
Obtaining Raw Usage Data	701
Usage Data via SOAP	702
18 Getting Started with Updates and Insights	703
The License Lifecycle: Updates and Insights	704

- About Updates and Insights** **705**
 - The Updates and Insights Module 705
 - Prerequisites for Automated Updates 706
 - Update Key Concepts 707
 - Notification Server 707
 - Anonymous Devices 708
- Requesting Update Information** **708**
 - Flow of Requests 708
 - REST APIs for Requesting Update Information 710
 - Device Registration** **710**
 - Register a Device* 711
 - Poll for Device Registration Status* 711
 - Status Log** **712**
 - Log the Status of the Update Process* 712
 - Poll for Completion of Status Change* 713
 - Updates** **714**
 - Find Available Updates* 714
 - Poll for Response to the Request for Updates* 716
 - Request Manifest File* 717
 - Poll for Response to the Request for Manifest File* 717
- Logging Device Events** **719**
 - Events REST API 720
 - Log the Event of the Update Process** **720**
 - Poll for Response to the Request for Event Logging** **721**
 - Viewing Logged Events 722
- Authorizing Update Requests** **723**
 - Update Authorization Key REST API 724
- Securing Update Responses** **725**
 - Update Signing Key REST API 725
 - Signed Updates REST API 726
 - Find Available Signed Updates** **726**
 - Poll for Response to the Request for Signed Updates** **727**
 - Request Manifest File** **729**
 - Poll for Response to the Request for Manifest File** **729**
- Updates and Insights Exercises** **731**
 - Prerequisites 731
 - Preparing FlexNet Operations 732
 - Creating a Download Package** **733**
 - Associating a Download Package with a Product** **734**
 - Creating Download Files** **736**
 - Associating Download Files with a Download Package** **738**
 - Creating an Update 739
 - Updates and Insights Next Steps 743
 - Requesting Updates and Manifests** **743**
 - Requesting Updates* 744
 - Polling for Updates* 744

Requesting the Manifest 745

Polling for Manifest 745

Requesting Signed Updates and Manifests 746

Obtaining the Public Key 746

Requesting Signed Updates 747

Polling for Signed Updates 748

Requesting the Signed Manifest 749

Polling for Signed Manifest 749

Authorizing Requests for Updates and Manifests 750

Verifying the Update 751

19 Getting Started with FlexNet Customer Growth 753

Introduction 754

 The License Lifecycle: FlexNet Customer Growth 754

 The FlexNet Customer Growth Module 755

 Exercise Prerequisites 756

FlexNet Customer Growth Concepts 756

 The Customer Growth Dashboard 757

About the Dashboard Charts 758

Key Performance Indicator (KPI) Scores 759

About the Dashboard Account List 761

Watched and Unwatched Accounts 761

Alerts 762

 Account Health Pages 762

Accounts Health Page 762

Account Detail Pages 763

 Renewals 765

Renewal Jobs 766

Renewal Reminder Email Messages 767

Expiring Entitlements Page 768

More About the Expiring Lines Shown on the Expiring Entitlements Page 768

More About How Expiring Lines Are Selected for the Renewal Reminder Email Message 770

 Next Steps 771

Visualizing Customer Health 771

 Viewing the Customer Growth Dashboard 772

 Toggling Between All Accounts and the Watchlist 772

 Viewing the Accounts Health Page 773

 Filtering the Accounts Health List 773

 Searching the Accounts Health List 773

 Watching and Unwatching Accounts 774

 Viewing Account Details 774

 Working with the Products Tab on the Account Details Page 775

 Working with the Renewals Tab on the Account Details Page 776

 Next Steps 778

Notifying End Users about Expiring Entitlements 778

 Preparing Entitlement Line Items for Renewal Exercises 778

- Activating the Renewal Email Templates 781
- Setting Up the Job 782
- Viewing the Expiring Entitlements Page and Receiving Renewal Notifications 782
- Next Steps 785
- Notifying End Users About Expired Entitlements 785**
- Preparing Entitlement Line Items for Renewal Exercises 786
- Activating the Renewal Email Templates 789
- Setting Up the Job 790
- Viewing the Expiring Entitlements Page and Receiving Renewal Notifications 790
- Next Steps 792

20 Getting Started with Advanced Organization Management 793

- Introduction 793**
- Prerequisites 794
- The License Lifecycle: Advanced Organization Management 794
- Performing Searches in the FlexNet Operations Producer Portal User Interface 795
- Managing Accounts 798**
- Accounts Key Concepts 798
- About Accounts 799
- Management Tasks 800
- Browsing Accounts and Sub-Accounts* 801
- Creating, Editing, or Deleting an Account* 801
- Account Management Exercises 801
- Browsing Accounts 802
- Creating a Customer Account and User 802
- Creating a Customer Sub-Account 804
- Creating a Producer Sub-Account 804
- Editing an Account 805
- Deleting an Account 805
- Account Management Next Steps 806
- Account Management Advanced Topics 806
- Managing Users 807**
- Users Key Concepts 807
- About Users 807
- Users and Accounts* 808
- Default Users* 810
- Your User Profile and Password* 810
- Browsing Users* 811
- Creating, Editing, or Deleting a User* 811
- Resetting a User Password* 811
- Deactivating and Reactivating a User* 811
- About Roles and Permissions 812
- Permissions* 812
- Roles* 813
- Browsing Roles* 813
- Assigning a Role to a User* 813

<i>Browsing Users with a Role</i>	813
User Management Exercises	814
Browsing Users	814
Creating a User	815
Editing a User	816
Resetting a User's Password	816
Changing a User's Account	816
Deactivating or Reactivating a User	817
Deleting a User	817
Browsing Roles	818
Browsing Users with a Role	818
Assigning or Removing a User's Role	819
User Management Next Steps	819
User Management Advanced Topics	820
Managing Channel Partners	820
Channel Partner Key Concepts	820
Partners and Distribution Tiers	820
Architecture Overview	821
<i>Built-In Tiers</i>	822
<i>Custom Tiers</i>	823
Designing Channel Partner Tiers	823
Creating a Partner Account	825
Channel Partner Next Steps	826
Channel Partner Advanced Topics	826
21 Configuring FlexNet Operations	829
Using the System Menu	829
Performing System Configuration	831
Configuring the FlexNet Platform Server	832
Configuring the Producer Portal User Interface	837
Configuring Validators	838
Configuring System Settings	840
Configuring Trusted Activation Settings	863
Configuring Public Services Settings	865
Configuring End-User Portal Settings	866
Activating and Licensing FlexNet Operations	883
Importing a Configuration	883
Exporting a Configuration	883
Configuring Embedded Devices Settings	884
Secure Token Single Sign-On	891
Configuring Secure Token Single Sign-On	892
Synchronizing SSO Application User Data	892
Generating a Token	894
Constructing a URL	894
Viewing Transaction Histories	895

Managing Custom Content **897**

- About Custom Content 897
- About Product Trial Registration Support 905
 - Trial Registration Process 905
 - Sending End Users to a Trial Registration Page 905
 - Showing a Custom Registration-Success Page (Optional) 906
 - Customizing Trial Registration Content 906
 - “Trial Registration” Section 906
 - “Product Selection” Section 907
 - “Additional Information” Section 907
 - Defining Custom Attributes 907
 - Defining Custom User Attributes 908
 - Defining Custom Account Attributes 908
 - Defining Custom License Attributes 908
- Listing Custom Content 912
- Creating Custom Content 913
- Editing Custom Content 914
- Localizing Custom Content 915

22 Performing Administrative Tasks **917**

Using the Event Notification Service REST API **918**

- Events Triggering Event Notifications 920
- Accessing the Event Notification Service REST API 921
 - Base URL 922
 - Permissions 922
 - Authentication 922
- Configuring Event Notifications 924
 - Using the Event Notification Service REST API Endpoints 924
 - Configuration Parameters for Event Notifications 925
- Payload to Webhook Endpoints 927
- Monitoring the Event Notification Service Status 929

Administering Alerts **929**

- Browsing Alerts 930
- Dismissing (Removing) an Alert 930
- Configuring Alert Behavior 931
 - Creating a Customized Schedule 932
- Setting Alert Subscriptions 935
- FlexNet Operations Alert Types 936
 - More About the Product Version Upgrade Job 942
 - More About the Expiring Entitlements Job 945
 - More About the Expired Entitlements Job 947

Administering Custom Attributes **949**

- About Custom Attributes 950
- Managing Custom Attributes 954
 - Custom Attribute Settings 954
 - Adding Custom Attributes 956

Listing Custom Attributes	956
Editing Custom Attributes	957
Deleting Custom Attributes	959
Managing Custom Host Attributes	959
Custom Host Attribute Settings	960
Adding Custom Host Attributes	961
Listing Custom Host Attributes	961
Deleting Custom Host Attributes	962
Managing Custom License Attributes	963
Custom License Generator Attribute Settings	964
Custom License Model Attribute Settings	965
Adding Custom License Attributes	966
Listing Custom License Attributes	968
Editing Custom License Attributes	969
Deleting Custom License Attributes	969
Importing and Exporting Entities	970
Import/Export Package Structure	970
XML Metafile Structure	971
Importing and Exporting Entities Overview	972
System Configuration	973
Exporting Entities	974
Importing Entities	976
Using Data Import Templates	978
Time Zone Settings	980
Import/Export Job Status	983
Administering License Technologies	984
Managing License Technologies	985
Creating a License Technology	986
Using External Services with License Technologies	991
External Service Operations	991
Creating an External Service	992
Managing License Generator Configurations	994
Creating a License Generator Configuration	995
Creating a FlexNet Publisher Licensing Toolkit License Generator (VCG) Configuration	996
Managing License Model or License Generator Custom Attributes	999
Creating a License Generator Configuration Custom Attribute	999
Creating a Custom License Model Custom Attribute	1001
Managing Custom Host Attributes	1003
Creating a Custom Host Attribute	1003
Administering License Models	1006
About License Models	1007
License Model Types	1007
Certificate License Models	1008
Trusted License Models	1009
Embedded License Models	1010
Custom License Models	1011

License Model Attribute Specification Time	1011
About Overdraft Support	1012
About the License Expiration Grace Period	1016
Predefined Substitution Variables for License Strings	1017
Custom Attributes in License Strings	1019
Managing License Models	1020
Creating a License Model	1021
Copying a License Model	1038
Deleting a License Model	1038
Deploying a License Model	1039
Printing a License Model	1039
Exporting License Models	1039
Employing a Predefined Substitution Variable	1040
Setting Up Custom License Model Attributes	1041
Setting License Model Policies	1041
Working with Time Zones	1046
Administering Device and License Server Setup	1048
About Device and License Server Setup	1049
About Device Series and Device Models	1049
About Server Host Types	1051
Device Series Attributes	1051
Device Model Attributes	1052
Server Host Type Attributes	1053
About Publishers and Publisher Identities	1054
Managing Publisher Identities	1054
Creating a Publisher	1054
Creating a Publisher Identity	1055
Downloading Identity Files	1056
Managing Device Series	1057
Listing Device Series	1057
Viewing a Device Series	1057
Adding a Device Series	1058
Editing a Device Series	1058
Managing Device Models	1059
Searching Device Models	1059
Viewing a Device Model	1060
Creating a Device Model	1060
Editing a Device Model	1062
Managing Server Host Types	1063
Listing Server Host Types	1063
Viewing a Server Host Type	1063
Creating a Server Host Type	1064
Editing a Server Host Type	1066
Viewing Request History	1066
Monitoring the FlexNet Embedded Back Office	1067
Working with Transaction Keys	1068

About Transaction Keys	1068
Managing Transaction Keys	1070
Creating a Transaction Key	1070
Configuring Anchoring	1072
Working with Application Specification Records (ASRs)	1073
About Activation Specification Records (ASRs)	1073
Local Trials	1074
Managing Local Trial ASRs	1074
Creating a Local Trial ASR	1075
Emailing a Local Trial ASR	1077
Short Code ASRs	1078
About Short Code Activations	1078
Managing Short Code ASRs	1079
Creating a Short Code ASR	1079
Linking a Short Code ASR with a Bulk Entitlement	1082
Viewing Short Code Summary	1084
Emailing a Short Code ASR	1085
View and Manage Trusted Activation Requests	1085
Managing Email and Email Templates	1086
Managing Email	1088
Verifying Email Addresses and Domains (AWS Only)	1088
Creating a Download Package Notification	1089
Creating a File Notification	1091
List Sent Emails	1094
View Sent Emails	1095
Resend Email	1096
Managing Email Templates	1096
About Email Templates	1097
Listing Email Templates	1111
Adding Email Templates	1112
Viewing Email Templates	1113
Editing an Email Template	1114
Prevent Blocking of Email Sent by FlexNet Operations	1116
Authorizing FlexNet Operations to Send Email on Behalf of the Your Email Server	1117
Configuring the Email Template	1118
23 Reporter Quick Reference	1121
Accessing the Reporter	1121
Using Help	1122
Terminology Used in this Guide	1122
Data Refresh Intervals	1123
24 Managing Web Intelligence Reports	1125
Folder and Document Organization	1126
Accessing Recent Documents and Messages	1126

Navigating Folders and Documents	1126
Default Folders in the “My Documents” Drawer	1127
Default Folders in the “Folders” Drawer.....	1127
Document Organization and Actions	1128
Creating a Folder	1128
Deleting a Folder	1129
Running a Standard Report	1129
Creating a Web Intelligence Report	1130
Steps to Create a Web Intelligence Report.....	1130
Building a Query.....	1133
Controlling the Retrieval of Duplicates.....	1134
Opening a Report in Reading or Design Mode	1135
Modifying the Report	1137
Modifying Report Elements.....	1137
Inserting Cells	1137
Inserting Charts	1138
Converting a Report to Tables or Charts.....	1139
Modifying Charts	1140
Viewing a Query Summary.....	1141
Formatting the Report	1142
Data Access: Providing a Customized Variable	1143
Analysis: Providing Filters and Input Controls	1145
Adding Filters.....	1145
Creating Input Control	1147
Page Setup: Adding Multiple Reports to a Document	1150
Viewing the History of Reports	1150
Refreshing Reports	1151
Exporting Reports in Different Formats and Purpose	1154
Scheduling Reports	1156
Scheduling a Report	1157
Events Options for a Scheduled Report	1159
Destination Options for a Scheduled Report	1160
Delivery Rules for Scheduled Documents.....	1167
Deleting a Report's Schedule	1167
Pausing a Report's Schedule	1168
Recycle Bin Accordion.....	1169
Enabling Reports from Legacy Reporter.....	1169
25 Reporter Standard Reports	1171
Before You Begin.....	1171
Standard Reports	1172
ACT-Accounts Created in Last X Days.....	1173
ENT-Entitlement Lines Created in Last X Days.....	1174
ENT-Entitlement Lines Expiring in X Days.....	1176
ENT-Maintenance Expiring in Next X Days	1177

FUL-Fulfillments Created in Last X Days 1179

FUL-Fulfillments with Returns/Rehosts/Reinstallations 1184

PRD-Product Created in Last X Days 1186

1

FlexNet Operations User Guide

FlexNet Operations is a Web-based application that supports the integration of software license delivery into the business operations of software publishers and device manufacturers. This section provides a high-level overview of FlexNet Operations, a brief discussion of its environments, and previews the concepts and information covered in other sections of the online help.

The remainder of the user guide is organized into the following sections.

Table 1-1 ▪ FlexNet Operations User Guide

Section	Description
Using FlexNet Operations	<p>Discusses the tasks associated with using FlexNet Operations to manage the licensing of software products and devices.</p> <ul style="list-style-type: none">● Packaging Products● Entitling Customers and Activating Licenses● Supporting Licenses● Managing Devices● Managing Usage● Managing Accounts and Users● Analyzing Usage and Entitlement Data (Early Access)● Branding the End-User Portal

Table 1-1 ▪ FlexNet Operations User Guide

Section	Description
Getting Started	<p>This section explains fundamental concepts, and provides exercises to help you get started using the basic features of FlexNet Operations.</p> <ul style="list-style-type: none">● Getting Started with FlexNet Embedded Licensing● Getting Started with FlexNet Publisher Trusted Storage-Based Licensing● Getting Started with FlexNet Publisher License File-Based Licensing● Getting Started with Non-FlexNet Licensing Technologies● Getting Started with Cloud Licensing Service● Getting Started with Entitlement Management● Getting Started with Electronic Software Delivery● Getting Started with Updates and Insights● Getting Started with Usage Management● Getting Started with FlexNet Customer Growth● Getting Started with Advanced Organization Management
Administrator Reference	<p>This section identifies FlexNet Operations administration processes—such as managing system configuration, setting up event notifications for analysis purposes, license technologies, device and license server setup, and email templates—and describes how to perform those administration tasks.</p> <ul style="list-style-type: none">● Configuring FlexNet Operations● Performing Administrative Tasks
Reporting	<p>This section explains how to get started using FlexNet Reporter, and describes the standard reports.</p> <ul style="list-style-type: none">● Reporter Quick Reference● Reporter Standard Reports

Introduction to FlexNet Operations

FlexNet Operations is a Web-based application that supports the integration of software license delivery into the business operations of software publishers and device manufacturers. It allows vendors to automate the stages of the software license lifecycle, which is illustrated in the following figure:



Figure 1-1: Software License Lifecycle Stages

The following table describes the stages of the software license lifecycle.

Table 1-2 ▪ Stages of the Software License Lifecycle

Stage	Description
Create Products	Create product definitions that are used to generate licenses.
Order/Entitle	Define an account's rights to obtain licenses for your products.
Deliver/Install	Deliver the application software to the customer and install that software.
Activate	Deliver licenses to the customer.
Return/Rehost	Manage license transfers from one user or system to another.
Maintain/Update	Deliver software updates to the customer.
Upsell/Renew	Renew the customer's licenses, or sell the customer additional product functionality.

FlexNet Operations Home Page

The home page for FlexNet Operations displays the following information:

Table 1-3 ▪ FlexNet Operations Home Page

Widget	Description
Alerts	A list of the most recent alert activity. Click See All to go to the Alerts page to see all the alerts.
Announcements	A list of any announcements regarding the FlexNet Operations portal.
QuickSearch	Enables quick access to searches for Entitlements, Licenses, Devices, Customer Users, Customer Accounts and Products. Once you have selected a search type, use the drop down boxes and text box to further define your search criteria.
Account Health	Provides an at-a-glance view of over all Account Health, Renewal Risk and Consumption Health for all accounts. For details on the features of the Account Health information, see Account Health . Click Health Dashboard to go to the Health Dashboard page.

FlexNet Operations Environments

FlexNet Operations has two environments:

- [User Acceptance Testing \(UAT\)](#)
- [Production \(PROD\)](#)

About Your Site ID

The URLs for the entry points into the FlexNet Operations systems use a site ID, which is supplied by Revenera. This ID is usually your organization's **DNS name**, but can also be the **Tenant ID** that was assigned to your organization when FlexNet Operations was first implemented, and would have the format **flexNNNN**.

For example, the URL for the FlexNet Operations Producer Portal for the company ABCD with the tenant ID of 1234 might appear as follows:

Method	Site ID in URL
Using the DNS name	https:// ABCD -fno.flexnetoperations.com/flexnet/operations
Using the Tenant ID	https:// flex1234 -fno.flexnetoperations.com/flexnet/operations

User Acceptance Testing (UAT)

The UAT environment is a place to perform configuration, integration development, testing, and training. The following URLs are entry points into the FlexNet Operations system.

Table 1-4 ▪ FlexNet Operations UAT Environment URLs

Use	URL
Producer Portal (you)	https://<siteID>-fno-uat.flexnetoperations.com/flexnet/operations
End User Portal (end customers and channel partners)	https://<siteID>-uat.flexnetoperations.com/flexnet/operationsportal
FlexNet Embedded Activation Endpoint	https://<siteID>-uat.compliance.flexnetoperations.com/deviceservices
Cloud Licensing Service Module Endpoint	https://<siteID>-uat.compliance.flexnetoperations.com/instances/<CLS instance ID>/request
Download Packaging Service	https://<siteID>-fno-uat.flexnetoperations.com/flexnet/services/v2/DownloadPackagingService
Electronic Software Delivery FTP Site	uploaduat.flexnetoperations.com
Notification Server	https://<siteID>-ns-uat.flexnetoperations.com/



Note ▪ For more information on <siteID>, see [About Your Site ID](#).

Production (PROD)

The Production instance is for customer entitlement management and licenses, usage, and delivery activities. The following URLs are entry points into the FlexNet Operations system.

Table 1-5 ▪ FlexNet Operations Production Environment URLs

Use	URL
Producer Portal (you)	https://<siteID>-fno.flexnetoperations.com/flexnet/operations
End User Portal (end customers and channel partners)	https://<siteID>.flexnetoperations.com/flexnet/operationsportal
FlexNet Embedded Activation Endpoint	https://<siteID>.compliance.flexnetoperations.com/deviceservices

Table 1-5 ▪ FlexNet Operations Production Environment URLs

Use	URL
Cloud Licensing Service Module Endpoint	https://<siteID>.compliance.flexnetoperations.com/instances/<CLS instance ID>/request
Download Packaging Service	https://<siteID>-fno.flexnetoperations.com/flexnet/services/v2/DownloadPackagingService
Electronic Software Delivery FTP Site	upload.flexnetoperations.com
Notification Server	https://<siteID>-ns.flexnetoperations.com/



Note ▪ For more information on <siteID>, see [About Your Site ID](#).

About Download Management and FlexNet Electronic Software Delivery

FlexNet Electronic Software Delivery (requires the Software Delivery module) adds electronic download support to FlexNet Operations. Producers who use FlexNet Operations with FlexNet Electronic Software Delivery define their downloads as part of the product packaging process. The downloads they specify are available to entitled end users in the End-User Portal.

Downloads are specified as download packages. A download package describes a group of files or containerized applications (Docker images and Helm charts) or both and relates that group with a product, a producer, and, optionally, a license agreement.




Figure 1-2: Download packages

A product can have many download packages, and download packages can be associated with one or more products. Download packages collect files or containerized applications into groups that might comprise a software release, a component, or any other grouping that fits your account's needs.

For producers who use FlexNet Operations with FlexNet Electronic Software Delivery, the Producer Portal includes features for managing download packages, files, agreements, and producers. The Products menu includes links for creating and managing these items. Also, product lines, which are otherwise optional, are required for producers who use FlexNet Electronic Software Delivery.

Containerized applications are managed and stored in a separate registry that is either hosted by Revenera or by the software producer.

For more information about download management, see the following sections in [Packaging Products](#):

- [Managing Download Packages](#)
- [Managing Containerized Applications](#)
- [Managing Download Files](#)
- [Managing License Agreements](#)
- [Managing Producers](#)



Tip - Export compliance prevents the delivery of files to residents of certain countries, in keeping with U.S. restrictions on the sale of regulated technologies to these countries. The user-configurable export compliance settings are managed at the download package level. For more information about export compliance, see [About Export Compliance](#).

See Also

[Getting Started with Electronic Software Delivery](#)
[Managing Product Lines](#)
[Packaging Products](#)
[Configuring End-User Portal Settings](#)

About FlexNet Usage Management

FlexNet Usage Management adds usage management support to FlexNet Operations. In conjunction with FlexNet Embedded licensing, FlexNet Usage management includes the ability to set up usage-enabled license models, products, license servers and view usage history reports in the FlexNet Operations Producer Portal.

FlexNet Operations and FlexNet Usage Management help application producers maximize software revenues and eliminate revenue leakage through new support of increasingly popular usage-based trust but verify, pay-for-use, and pay-for-coverage models. FlexNet Usage Management provides application producers the flexibility to implement any software licensing model across the entire spectrum—from strict enforcement to usage-based, trust but verify.

In FlexNet Operations, usage management functionality is integrated with license models, features, products, and other components, and supported on FlexNet Embedded hosts, devices, and license servers. In the Producer Portal, usage reports are available from the Usage menu. (See [Managing Usage](#).) In the End-User Portal, users in customer accounts can view usage reports for their account.

See Also

[Getting Started with Usage Management](#)
[Packaging Products](#)
[Managing Devices](#)
[Administering License Models](#)
[About Usage Management](#)

Product Support Resources

The following resources are available to assist you with using this product:

- [Reverera Product Documentation](#)
- [Reverera Community](#)
- [Reverera Learning Center](#)
- [Reverera Support](#)

Reverera Product Documentation

You can find documentation for all Reverera products on the [Reverera Product Documentation](#) site:

<https://docs.revenera.com>

Revenera Community

On the [Revenera Community](https://community.revenera.com) site, you can quickly find answers to your questions by searching content from other customers, product experts, and thought leaders. You can also post questions on discussion forums for experts to answer. For each of Revenera’s product solutions, you can access forums, blog posts, and knowledge base articles.

<https://community.revenera.com>

Revenera Learning Center

The Revenera Learning Center offers free, self-guided, online videos to help you quickly get the most out of your Revenera products. You can find a complete list of these training videos in the Learning Center.

<https://learning.revenera.com>

Revenera Support

For customers who have purchased a maintenance contract for their product(s), you can submit a support case or check the status of an existing case by first logging into the [Revenera Community](https://community.revenera.com) and then making selections on the **Get Support** menu, including **Open New Case** and other options.




Figure 1-3: Get Support Menu of Revenera Community

Contact Us

Revenera is headquartered in Itasca, Illinois, and has offices worldwide. To contact us or to learn more about our products, visit our website at:

<http://www.revenera.com>

You can also follow us on social media:

- [Twitter](#)
- [Facebook](#)
- [LinkedIn](#)
- [YouTube](#)
- [Instagram](#)

Part 1

Using FlexNet Operations

This part of the FlexNet Operations User Guide includes the following sections:

- [Packaging Products](#)
- [Entitling Customers and Activating Licenses](#)
- [Supporting Licenses](#)
- [Managing Devices](#)
- [Managing Usage](#)
- [Managing Accounts and Users](#)
- [Analyzing Usage and Entitlement Data \(Early Access\)](#)
- [Branding the End-User Portal](#)

Packaging Products

Packaging products is the process of creating product definitions that are used to generate licenses.

Products are built up from features and feature bundles and linked to one or more license models to define how they can be used. Products can also be assembled into groups of products called suites.

During the product packaging process, you create features, feature bundles, products, and suites, and when doing so specify upgrade, upsell, and other relationships between those products and suites to capture your overall product hierarchy within FlexNet Operations.



Note - *Maintenances are special types of products. Maintenance products define maintenance or support plans that can be tied to regular products.*

See the following sections for details about the tasks involved with the product packaging process:

Table 2-1 -

Topic	Description
About Packaging Products	Discusses general product packaging concepts. This section also includes subtopics dedicated to trial product and download management concepts. <ul style="list-style-type: none"> About Trial Products About Download Management: FlexNet Electronic Software Delivery Components
Working with Features	Includes information about viewing, adding, and managing features.
Working with Feature Bundles	Describes creating and managing feature bundles.
Working with Products	Discusses product creation and management.
Working with Suites	Explains how to build and manage a group of products.

Table 2-1 •

Topic	Description
Working with Maintenances	Discusses the use of maintenance products.
Managing Part Numbers	Discusses the optional use of part numbers to tie your products to your accounting system.
Managing Product Lines	Discusses the optional use of product lines to help organize your products into groups.
Working with Updates	Provides a singular delivery and update interface for software and devices.
Managing Download Packages	Discusses how download packages are used, how they interact with products and files, and how they are rendered to End-User Portal users.
Managing Containerized Applications	Explains how to manage and distribute containerized applications.
Managing Download Files	Addresses adding and uploading of files, associating files with download packages, and other file management concepts and tasks.
Managing License Agreements	Covers the creation and maintenance of licensing agreements and how they are related to download packages.
Managing Producers	Explains how to add producers in the Producer Portal and how producers are related to download packages.

See Also

[Administering License Technologies](#)
[Administering License Models](#)

About Packaging Products

In FlexNet Operations, you define your products as a collection of features that can be licensed and ordered as a set. This process of defining your products is referred to as product packaging. The product packaging process is highly flexible and many of the steps are particular to the licensing technology and models you support. Please first read the getting-started section specific to your licensing technology and follow the exercises there before packaging your products.

Discussion of the product packaging process is divided into the following groups:

- [Product Packaging Concepts](#)
- [Example Product Definition](#)
- [Product Packaging Overview](#)
- [Before You Begin](#)

- [Product Packaging Wizard](#)

For a discussion of trial products and how to make products available on the End-User Portal's **Trial Registration** page, see the subtopic, [About Trial Products](#).

For a discussion of download package and download file concepts, see the subtopic, [About Download Management: FlexNet Electronic Software Delivery Components](#).

Product Packaging Concepts

In FlexNet Operations, a *product* represents a unit that can be ordered and licensed. The product hierarchy is designed to enable modularity and re-use, and to minimize duplication:

- A *feature* represents a licensable capability defined in a software application, and is the basic building block for a product. An example of a feature would be the Add function in a calculator, or the Print function in a word processing program.
- A *feature bundle* is an aggregation of features. Feature bundles are primarily of interest to Product Managers because they facilitate modularity and easy re-use of features across products. In FlexNet Operations, you map features to feature bundles, and then to products.
- A *product* is packaged from individual features or feature bundles and is associated with one or more [license models](#). One or more part numbers can be assigned to a product.
- A *suite* is packaged from individual products that are functionally complementary, and is associated with one or more [license models](#). One or more part numbers can be assigned to a suite.
- A *maintenance* represents the rights to get updates and upgrades to a product. A maintenance can be related to one or more products. One or more part numbers can be assigned to a maintenance product.

To help keep the number of product definitions as low as possible, values of many product attributes can be set at one of several times in the license lifecycle.



Note - Producers who use FlexNet Operations and FlexNet Electronic Software Delivery (requires the Software Delivery module) can also create download package, files, and agreements. For more information, see [About Download Management and FlexNet Electronic Software Delivery](#).

Example Product Definition

Consider an application called Sample App 3000. Its features might include, for example:

- Print
- Convert
- Save

The features of your program correspond to features expressed in your license rights as defined by product management. One common practice is to prefix feature names with the product name, as in:

- SampleApp.print
- SampleApp.convert
- SampleApp.save

Another common practice is to define a feature that represents the entire application, checking out this feature when the application initializes, and checking it back in when the application exits. Such a feature might be called `SampleApp.primary`.

Product Packaging Overview

Once you have created and deployed your license technology and license models, you can begin defining your products. Packaging a product is the process of creating a product definition that is used to create entitlements and to generate licenses. The product packaging process includes

- Creating one or more transaction keys (if you use any trusted license models)
- Creating a product line (required for producers who use FlexNet Operations for software delivery)
- Creating the hierarchy of features, feature bundles, products, and suites
- Creating maintenance products
- Associating license models (and transaction keys) with products and suites
- Associating part numbers with products and suites (optional)
- Relating products to other products, suites, or maintenance (optional)
- Associating product lines with products and suites (optional)

Also, in the interface, an optional, four-step product packaging wizard can lead you through creating features, features bundles, products, and suites. (See [Product Packaging Wizard](#).) License models and optionally, part numbers and product lines, are associated with a product in the flow of the wizard, but they must be created outside the steps of the wizard. Creating maintenance products also occurs outside the steps of the wizard.

Before You Begin

Before you start the product packaging process, it is important that you deploy your license technology and at least one license model.

It is also valuable to carefully consider the best way to define and combine your features and products and the best way to license your products.

Please read the FlexNet Operations getting started section particular to your license technology before you package your products.

Product Packaging Wizard

The product packaging wizard is a four-step flow that walks users through pages for

1. Adding features
2. Adding feature bundles
3. Adding products
4. Adding suites

Each step in the product packaging wizard includes a number of sub-steps that are contained in an entity-specific sub-wizard. Even so, the product packaging wizard includes most, but not all, product packaging activities. Some license technology-specific or optional activities are not part of the wizard, but the pages for those activities can be accessed directly from the **Products** menu. For example, when the product lines feature is

enabled, you can map your product to a product line as part of the product sub-wizard; creating the product lines, though, must be done separately by clicking **Products > Product Lines** and then following the instructions in [Managing Product Lines](#).

The steps and all the tasks each step contains are shown at the bottom of the **Package Products** page.



Tip ▪ To open the **Package Products** page, click **Products > Products**.

Move from one step to the other using the **Next** button at the bottom of each page.

See Also

[About Trial Products](#)

[About Download Management: FlexNet Electronic Software Delivery Components](#)

About Trial Products

Producers can provide free trial registrations for their products. Trial registration allows your customers to acquire temporary license rights to designated products by providing their email address and, optionally, other contact information in the End-User Portal.

How Does It Work?

To support free trials, producers create a custom content page to be a destination where trial users can find your trial products and opt-in to try out those products. This trial registration page shows a list of products that have been made available for trials and requests (at minimum) an email address from the trial user. (Other contact information can also be gathered but is not required, by FlexNet Operations, for the trial registration process.)

After a user selects a trial product, supplies the required contact information, and clicks **Complete**, the End-User Portal sends them an email message with their End-User Portal login information and entitles them to a trial of the selected product. (The trial period is determined by the product's license model.)

Steps for Supporting Trial Registrations

Supporting trial registrations requires planning and preparation. Producers who want to support trial registrations must perform the following steps to make their products available to trial users:

- Create and deploy the products and license models you want to offer for trial registrations. These can be existing products and license models, but the trial period is based on the expiration in the license model.
- Map part numbers—with **Available for Trial**—to these product/license model combinations.
- Create custom content for the **Trial Registration** page using the **TrialRegistration** template. This custom content is customizable and brand-able. When published, it shows the trial products and contact information input controls. See [About Product Trial Registration Support](#) for details about creating the **Trial Registration** page.
- Optionally create a trial registration-specific variation of the Welcome Email for End Users email template. The Trial Registration custom content page identifies the template variation to use. Without alterations, trial users receive a message based on the default Welcome Email for End Users template.
- Link prospective trial customers to your **Trial Registration** page using the Custom Content ID value of your trial registration page.

See Also

[Managing Part Numbers](#)
[Managing Custom Content](#)
[Managing Email Templates](#)

About Download Management: FlexNet Electronic Software Delivery Components

Producers who use FlexNet Operations and FlexNet Electronic Software Delivery may also create download packages and add files for their users and channel partners to download from the End-User Portal. When packaging products, these producers also create the following:

- Download packages
- Download files
- License agreements
- Producers
- Product lines

The **Products** menu includes links for creating and managing these items.

FlexNet Electronic Software Delivery also supports the distribution of containerized applications (Docker images and Helm charts). These applications are stored in a separate registry (either hosted by Revenera or hosted by the software producer).



Tip - Some attributes of these electronic software delivery components are localizable in the Producer Portal. Localizable attributes are easy to identify because they show a **Show Languages** button. When editing a download package or file, click **Show Languages** to show the fields in which you provide localized values.

For more information about download management, see [About Download Management and FlexNet Electronic Software Delivery](#).

For more about software-delivery management tasks, see [Managing Download Packages](#), [Managing Containerized Applications](#), [Managing Download Files](#), [Managing License Agreements](#), and [Managing Producers](#).

See Also

[Packaging Products](#)
[Working with Features](#)
[Working with Products](#)

Working with Features

This section explains what a feature is and what role it plays in the product packaging and licensing process. The following topics are included:

Table 2-2 •

Topic	Description
About Features	Discusses what features are and how they are used in FlexNet Operations.
Viewing Features	Provides basic information about viewing, creating, deleting, printing, and changing the state of a feature.
Creating a Feature	Covers the feature creation process in greater detail.
Reviewing Features	Describes how to review a feature.

See Also

- [Packaging Products](#)
- [About Packaging Products](#)
- [Working with Feature Bundles](#)

About Features

A *feature* represents a licensable capability defined in a software application, and is the basic building block for a product. A feature could represent any of the following:

- a product consisting of one or more components
- a specific version of a product
- a part of a product
- one or more pieces of data (restricted through the access routines)

An example of a feature would be the Add function in a calculator, or the Print function in a word processing program.

See Also

- [Viewing Features](#)
- [Creating a Feature](#)
- [Reviewing Features](#)

Viewing Features

Features can be viewed on the **Feature** page.




Task *To open the Feature page*

- Click **Products > Features**.

The **Feature** page automatically displays recently accessed feature bundles, if applicable. To view all features, select **Features** from the **Search For** choice list, and click the **Simple Search** button. You can also search for feature based on specific criteria. The table below describes some of the actions you can perform from the **Feature** page.

Table 2-3 ▪ View Features Capabilities

Capability	Description
Add a new feature from scratch	To add a new feature, click Add New Feature . (See Creating a Feature .)
Make a new feature from a copy of an existing feature	To copy a feature, select exactly one feature and click the Copy button. Then, follow the guidelines in Creating a Feature .
Delete a feature	To delete a feature, select one or more features and click the Delete button.  Note ▪ <i>Deployed features and features used in device series cannot be deleted.</i>
Change the state of a feature	To change the state of one or more features, select the features, click the Change State choice list, and select a state. Features can be in one of the following states: draft or deployed. A feature is created and can be edited in the draft state. When a feature bundle or product is deployed, all the features it contains are also deployed.
Print a feature	To print a feature, select one or more features and click the Print button.

See Also

[About Features](#)
[Importing and Exporting Entities](#)

Creating a Feature

You can create a new feature in the Producer Portal from the **Feature** page of the **Package Products** pages.



Tip ▪ *Save time by starting with a copy of an existing feature. Select the feature you want to copy, click **Copy**, type a new feature name, make any other necessary changes, and save the new feature. This approach can save time and reduce the chance for errors.*



Task **To create a feature**

1. Click **Products > Features**. This link opens the **Feature** page.
2. Click **Add New Feature**.
3. Provide values for the following fields:

Table 2-4 • Feature Creation Fields

Field	Description
Feature Name	<p>Name to uniquely identify the feature. The name can contain 30 characters or less when using FlexNet Licensing technology, or 64 characters or less for other licensing technologies. The name cannot contain spaces. The characters can be ASCII characters, numbers, periods, underscores, or hyphens.</p> <div style="border: 1px solid #ccc; padding: 2px; width: fit-content; margin: 10px auto;"> </div> <hr/> <p>Important • For FlexNet Publisher, the supported character set is restricted to lowercase alphabet (a-z), uppercase alphabet (A-Z), digits (0-9), and underscore (_). Other than for legacy applications still in production, the hyphen (-) is no longer supported.</p>
Version Format Type	<p>Select a Fixed or Date-Based version format.</p> <p>See Creating a FlexNet Publisher Licensing Toolkit License Generator (VCG) Configuration for more information about this property.</p>
Version	<p>If a Fixed version format is selected, enter the latest (highest-numbered) version of this feature that is supported by a generated license certificate. For FlexNet Licensing technology, the version consists of numbers and at most one decimal point, with a ten character maximum, for example, 1 or 1.5. For custom license technologies, this is a string with a maximum length of 64 characters.</p>
Description	<p>Describe the characteristics of this feature that make it unique.</p>
Units	<p>For FlexNet Usage Management users, Units specifies the units to be used for usage reporting. For example, if your usage-capture clients are capturing usage of data, you may want to label the reported counts as bytes or kilobytes or gigabytes.</p> <p>Units and Scale (below) work together to describe what the metered feature is counting.</p>

Table 2-4 • Feature Creation Fields



Field	Description
Scale	<p>For FlexNet Usage Management users, Scale is the feature scale. It represents how much is a unit for usage reporting purposes. For example, if your usage-capture clients are capturing usage of data in bytes but you want to report usage in kilobytes, enter 1024 for Scale.</p> <p>Units (above) and Scale work together to describe what the metered feature is counting.</p>
State	<p>A feature can be in one of two states—Draft or Deployed.</p> <ul style="list-style-type: none">● Draft: A feature is created as a draft that can be modified or deleted. Both draft and deployed features can be added to a feature bundle or a product in a draft state.● Deployed: A deployed cannot be modified or deleted. If a feature bundle or product is deployed, all the draft features it contains are also deployed. After a feature is deployed to use in production, it cannot be deleted or modified. <p>New features start out in a Draft state. A feature’s state cannot be changed on the Create a Feature page. To change a feature’s state after it has been created, use the Change State control on the Feature page (Products > Features).</p>
Aggregation Type	<p>Feature counts can be aggregated by SUM or MAX. Select one of the following values:</p> <ul style="list-style-type: none">● NONE—Feature counts are not aggregated and the default behavior is retained.● SUM—Feature counts are aggregated based on the sum of all counts.● MAX—Captures the highest feature count. <p>For more information, see Using Feature Count Aggregation.</p>  <p>Note • The Aggregation Type field is available only if the configuration option Enable feature count aggregation (under System > Configure > FlexNet Operations > Embedded Device Settings) is selected.</p>
Feature Overrides	<p>The configuration option Allow feature override changes to be published to a License Server (under System > Configure > FlexNet Operations > Embedded Device Settings) controls whether changes to feature overrides are reflected on the relevant instance of the FlexNet Cloud Licensing Service. See Embedded Device Settings.</p>

Table 2-4 • Feature Creation Fields

Field	Description
Vendor String	Used to override for specifically this feature, a vendor string defined in a license model. In addition to accepting an explicitly specified string, this field can accept, enclosed in curly braces, one of several predefined substitution variables or the name of a custom attribute. Use of this field is controlled by the FlexNet Operations license, and a user must be assigned a role that includes the Set Feature Override permission.
Notice	Used to override for this feature, a notice string defined in a license model. In addition to accepting an explicitly specified string, this field can accept, enclosed in curly braces, one of several predefined substitution variables or the name of a custom attribute. Use of this field is controlled by the FlexNet Operations license, and a user must be assigned a role that includes the Set Feature Override permission.
Serial Number	Used to override for this feature, a serial number defined in a license model. In addition to accepting an explicitly specified string, this field can accept, enclosed in curly braces, one of several predefined substitution variables or the name of a custom attribute. Use of this field is controlled by the FlexNet Operations license, and a user must be assigned a role that includes the Set Feature Override permission.
Counted	<p>Determines whether a feature is counted. Choose from</p> <ul style="list-style-type: none"> ● Yes ● No ● Do Not Override <p>Choosing a value, other than Do Not Override, overrides the value set in the license model.</p>
Reusable	<p>Determines whether this feature is reusable (only applies to metered features). Choose from</p> <ul style="list-style-type: none"> ● Yes ● No ● Do Not Override <p>Choosing a value, other than Do Not Override, overrides the value set in the license model.</p>

Table 2-4 • Feature Creation Fields

Field	Description
Client Uniqueness	<p>This property allows you to specify which combination of unique identifiers defines a group. This capability allows multiple members of same group can check out this feature and the checkout count is incremented by 1 only. This property must be used with counted licenses only.</p> <p>For example, if you set this to Group Mask = User, the user can check the feature out as many times as they are required to and they only increment the checkout count by 1. The first time the user checks out the feature, the checkout count is incremented by 1, but subsequent checkouts of that feature on different machines do not affect the checkout count.</p> <p>As another example, if you set this Group Mask = Host, then when the first user checks out a feature from Machine A, the checkout count is incremented by 1. Subsequent checkouts by different users from that same machine do not affect the checkout count.</p> <p>This configuration overrides the value set for the FlexNet license model. Choices include:</p> <ul style="list-style-type: none">● Do Not Override (default): Do not override the configuration defined for the associated license model.● Group Mask (User, Host, Display, Vendor Defined): Define the combination of criteria that create a unique group.● None: Each checkout request is uniquely counted. <p>These fields are only valid for FLEX licenses. See also Creating a License Model.</p> <hr/> <p> Note • For users of the FlexNet Publisher Licensing Toolkit, consult the documentation on the DUP_GROUP keyword.</p>



Note • If necessary, click the **Reset** button to reset all the feature fields.

4. Complete the feature creation process by clicking either **Save**, **Next**, or **Add New Feature**.
 - Click **Save** to save the feature.
 - Click **Next** to save the feature and show the **Feature Bundles** page.
 - Click **Add New Feature** to save the feature and start to create another feature.



Tip • After a feature has been saved, the history of its state changes can be viewed by clicking the **View History** button.

See Also

- [Copying a License Model](#)
- [Managing Custom License Attributes](#)

Using Feature Count Aggregation

FlexNet Operations can aggregate feature counts to support various business models.

The aggregation types SUM and MAX are supported:

- **SUM**—The sum of all feature counts captured over the aggregation interval.
- **MAX**—The largest feature count captured over the aggregation interval.

Prerequisites

The configuration option **Enable feature count aggregation** must be selected (under **System > Configure > FlexNet Operations > Embedded Device Settings**), and features to be aggregated must have an aggregation type set (see the previous topic, [Creating a Feature](#)).

FlexNet Operations aggregates feature counts only if the following conditions are met:

- All license model attributes are identical
- All of the following entities have identical values:
 - Name
 - Version
 - Vendor String
 - Notice
 - Serial Number
 - Expiration Date
 - Issuer
 - Version Date

Feature Count Aggregation Example

Assume that a producer offers the following product packages:

Product Package	Features
Premium	<ul style="list-style-type: none"> ● FeatureA with a count of 1,000 ● FeatureB with a count of 1,000
Volume	<ul style="list-style-type: none"> ● FeatureA with a count of 200,000 ● FeatureB with a count of 5,000

Customers can purchase the **Premium** package and later add a **Volume** package. The resulting feature counts differ depending on the selected aggregation type:

Feature	Aggregation Type	Feature Count
FeatureA	SUM	201,000 (1,000 + 200,000)
	MAX	200,000
FeatureB	SUM	6,000 (1,000 + 5,000)
	MAX	5,000

Reviewing Features

After you create features, you can review the features that have been recently created and perform the same operations on them as you can when [viewing features](#).

Working with Feature Bundles

Feature bundles are intended to simplify the packaging process. For example, suppose you provide multiple applications, and every application contains common library, help, and graphics features. Instead of manually adding all three features to each of your products, you can create a feature bundle (perhaps giving it the name `sampleapp.common`) containing the three features, and then add the feature bundle to each product.

Table 2-5 •

Topic	Description
About Feature Bundles	Describes feature bundles and their purpose.
Viewing Feature Bundles	Briefly discusses how to view, create, delete, print, and change the state of a feature bundle.
Creating a Feature Bundle	Covers the feature bundle creation process in detail.
Reviewing Feature Bundles	Describes the review step in the feature bundle creation process.
Deploying a Feature Bundle	Describes how to deploy a feature bundle.

See Also

[Working with Features](#)
[About Features](#)
[Working with Products](#)

About Feature Bundles

A *feature bundle* is a collection of features. Feature bundles are primarily of interest to product managers because they facilitate modularity and easy reuse of features across products. In FlexNet Operations, you map features to feature bundles, and then to products.

See Also

- [About Features](#)
- [Working with Feature Bundles](#)

Viewing Feature Bundles

Feature bundles can be viewed on the **Feature Bundle** page.




Task *To open the Feature Bundle page*

- Click **Products > Feature Bundles**.

The **Feature Bundle** page automatically displays recently accessed feature bundles. To view all feature bundles, select **Feature Bundles** from the **Search For** choice list, and click the **Simple Search** button. You can also search for feature bundles based on specific criteria. The table below describes some of the actions you can perform from the **Feature Bundles** page.

Table 2-6 - Viewing Feature Bundles Capabilities

Capability	Description
Add a new feature bundle from scratch	To add a new feature bundle, click Add New Feature Bundle . (See Creating a Feature Bundle .)
Make a new feature bundle from a copy of an existing feature bundle	To copy a feature bundle, select exactly one feature bundle and click the Copy button. Then, follow the guidelines in Creating a Feature Bundle .
Delete a feature bundle	To delete a feature bundle, select one or more feature bundles and click the Delete button.
	
	Note - <i>Deployed feature bundles cannot be deleted.</i>
Change the state of a feature bundle	Feature bundles can be in one of the following states: draft or deployed.
Print a feature bundle	To print a feature bundle, select one or more feature bundles and click the Print button.

See Also

- [Deploying a Feature Bundle](#)
- [Importing and Exporting Entities](#)

Creating a Feature Bundle

You can create a new feature bundle in the Producer Portal from the **Feature Bundle** page of the **Package Products** pages.



Tip - Save time by starting with a copy of an existing feature bundle. Select the feature bundle you want to copy, click **Copy**, type a new feature bundle name, make any other necessary changes, and save the new feature bundle. This approach can save time and reduce the chance for errors.



Task To create a feature bundle

1. Click **Products > Feature Bundles**. This link opens the **Feature Bundle** page.
2. Click **Add New Feature Bundle**.
3. Provide values for the following fields:

Table 2-7 - Feature Bundle Values

Value	Description
Feature Bundle Name	Name to uniquely identify the feature bundle. The name can contain spaces.
Description	Describe the characteristics of this feature bundle that make it unique.
State	A feature bundle can be in one of two states: <ul style="list-style-type: none">● Draft: A feature bundle is created as a draft that can be modified or deleted; draft feature bundles can contain draft or deployed features. A draft or deployed feature bundle can be added to a product in the draft state.● Deployed: If a product is deployed, all the draft features and feature bundles it contains are also deployed. After a feature bundle is deployed to use in production, it cannot be deleted or modified.

4. To add features to the feature bundle, click the **Add Features** button. A pop-up window appears in which you can search for and select one or more of the **Available Features**. Note that the list of features may be large enough to appear on multiple pages in the pop-up window.
 - a. Select the features you want to add.
 - b. Click the right arrow to move those features to the **Selected Features** list.
 - c. When the **Selected Features** list is complete, click the **Add** button to add the features to the feature bundle.



Note - To remove one or more features from the list of features in the feature bundle, select the features and click the **Remove Features** button.

5. On the **Create a Feature Bundle** page, if necessary, modify the **Quantity** to change the count of the feature in the feature bundle.

For example, say the count of a Feature A is 3 in feature bundle FB1. When one unit of FB1 is added to a product, a license generated for the product contains 3 counts of Feature A.

6. Complete the feature bundle by clicking **Save**, **Next**, or **Add New Feature Bundle**.
 - Click **Save** to save the feature bundle.
 - Click **Next** to save the feature bundle and show the **Products** page.
 - Click **Add New Feature Bundle** to save the feature bundle and start to create another feature bundle.



Note - If necessary, click the **Reset** button to reset all the feature bundle fields.



Tip - After a feature bundle has been saved, you can view the history of its state changes by clicking the **View History** button.

Reviewing Feature Bundles

After you create feature bundles, you can review the feature bundles that have been recently created and perform the same operations on them as you can when [viewing feature bundles](#).

Deploying a Feature Bundle

Feature bundles can be deployed from the **Feature Bundle** page (**Products > Feature Bundles**).

A feature bundle is created in the Draft state. Feature bundles in the Draft state can be edited. Once a feature bundle is deployed, it can no longer be altered. When a feature bundle is deployed, all the features it contains are also deployed. Likewise, when a product is deployed, all the features and features bundles it contains are also deployed.



Task

To deploy one or more feature bundles

1. On the **Feature Bundle** page, select the feature bundles to deploy.
2. Click **Change State > Deploy**, and confirm your choice by clicking **OK**. The **Deploy Feature Bundles** page displays the list of feature bundles, and the undeployed features they contain that will be deployed.
3. Click the **Deploy** button to deploy the feature bundles and all their features.

Working with Products

A product is packaged from individual features or feature bundles and is associated with one or more license models. Before you create a product, it is important to create its features and to create the license model used for it.

Product is also used to refer collectively to any of the entities that can be ordered: a product, a suite, or maintenance.

Table 2-8 •

Task	Description
About Products	Discusses products and product creation concepts.
Viewing Products	Explains how to view and search for products on the Package Products page.
Creating a Product	Describes how create a product—either by creating it from scratch or starting with a copy of an existing product.
Adding Features or Feature Bundles to a Product	Shows how to add existing features or feature bundles to a product.
Linking License Models to a Product	Discusses how to link one or more license models to a product. A product must be linked to at least one license model before a license can be generated for that product.
Mapping a Product to a Part Number	Discusses how to map products to part numbers.
Relating Products to Other Products	Explains how to create relationships between products. Product relationships are typically used to facilitate upgrade and upsell operations.
Mapping a Product to a Product Line	Describes how to assign products to product lines. Product lines can be used to define access rights to product information as well as for search and reporting purposes.
Reviewing Products	Describes the review step in the product creation process.
Deploying a Product	Discusses how to change a product’s state from Draft (initial state for new products) to Deployed (available for entitlements).
Reviewing New Product Hierarchy	Explains how to review the features, feature bundles, and products that comprise the product hierarchy.


See Also

- [Working with Features](#)
- [Administering License Models](#)
- [About Packaging Products](#)

About Products

Products are a collection of features linked to a license model. They represent the basic orderable unit in FlexNet Operations. The figure below depicts the relationships among products, features, license models, product lines, and part numbers.

Product Data Model



Important - Prior to creating a product, you must deploy your license technology and at least one license model. You must also create the features that will make up your product.

A product's attributes vary by the licensing you use and by your needs. There are a number of attributes that are particular to one license technology. There are also a number of optional FlexNet Operations features, such as part numbers and product relationships, that are included in the product creation steps.

Adding a product is the third step in the four-step product packaging wizard. The product creation steps include

- Set product attributes.
- Add features and feature bundles.
- Link license models.
- Map part numbers (optional).
- Specify product relationships (optional).
- Map product lines (see note, below).
- Review product creation.



Note - Product lines are optional for most producers but required for producers who use FlexNet Operations for electronic software delivery. Product lines tie products to download packages, files, license agreements, and producers. See [Managing Product Lines](#) and [About Download Management and FlexNet Electronic Software Delivery](#) for more information.

See Also

[About Packaging Products](#)

Viewing Products

This **Package Products** page automatically displays recently accessed products, if applicable.

To view all products, select **Products** from the **Search For** choice list, and click the **Simple Search** button. (Empty searches match all products.) You can also search for products based on specific criteria by

- Specifying some particular value in the search criteria
- Changing the **Search For** setting to a more specific choice, like **Products with Part Number**
- Clicking **Advanced Search** to specify multiple product attributes as search criteria

From the **Package Products** page, you can also perform the following tasks:

Table 2-9 - Viewing Products Options

Capability	Description
Add a new product from scratch	To add a new product, click Add New Product . For details, see Creating a Product .
Make a new product from a copy of an existing product	To copy a product, select exactly one product and click Copy . Follow the guidelines to add a new product.
Edit a product	To edit a product, click its name. The product is opened in the wizard.
Delete a product	To delete a product, select one or more products and click the Delete button.
Change the state of a product	Products can be in one of the following states : Draft , Deployed , Inactive , or Obsolete .
Print a product	To print a product, select one or more products and click the Print button.
Export a product	Products can be exported as .jar files for importing into another instance of FlexNet Operations. For details about the export process, see Importing and Exporting Entities .

See Also

[Working with Products](#)

[Viewing Download Packages of a Product](#)

Creating a Product

There are several ways to navigate to the page where a new product is created. When creating a new product from the **Package Products** page, you can either start a new product from scratch or create a new product from a copy of another product.



Task To create a new product

1. Click **Products > Products**. This opens the **Package Products** page.
2. Click the **Add new Product** button.

Follow the steps below to [create the product](#).



Task To copy an existing product

1. Click **Products > Products**. This opens the **Package Products** page.
2. Search for a product to copy.
3. Select the product and click the **Copy** button.

Follow the steps below to [create the product](#).



Note - Required fields are indicated with a red asterisk.



Task To create the new product

Provide values for the following fields:

Table 2-10 -

Field	Description
Product Name	Name to uniquely identify this product. The name can contain spaces.
Description	The characteristics of this product that make it unique. The description can be edited at any time.
Version	A string that can contain any characters up to a maximum of 64, for example, 1.2.3 or SP1.

Table 2-10 -

Field	Description
State	<p>A product can be in one of four states: draft, deployed, inactive, or obsolete.</p> <ul style="list-style-type: none"> ● Draft: A product is created as a draft that can be modified or deleted; draft products can contain draft or deployed features and feature bundles. Draft or deployed products can be added to a suite in the draft state. ● Deployed: If the suite is deployed, all the draft features, feature bundles, and products it contains are also deployed. After a product is deployed to use in production, it cannot be deleted or modified, except to change the transaction key and to add or remove license models, part numbers, or relationships. A deployed product can be used to create an entitlement. ● Inactive: If a product is made inactive, its features and feature bundles are not made inactive. An inactive product cannot be deleted or modified. An inactive product cannot be used to create an entitlement or to be the parent of a maintenance product, but an inactive product can be activated, upgraded, upsold, or renewed from an existing entitlement item. ● Obsolete: Deployed and inactive products can be made obsolete. Obsolete products behave like inactive products, but can be deleted if they have no entitlements associated with them.
Package	<p>For FlexNet licenses only, specify that this product is a package if you want to:</p> <ul style="list-style-type: none"> ● Provide a way of distributing one line for a license file that has a large number of features, which share most of the same feature line arguments ● License this product as a suite <p>Even if a product is specified as a package, if a license model is specified for the product that does not support PACKAGEs (that is, Package Specification is None), the license model takes precedence and individual feature lines are generated.</p> <p>The count of unique features in a package must be the same. For example, if a feature bundle containing three counts of FeatureA and six counts of FeatureB is added to a product, then for that product to be licensed with a PACKAGE line, three more counts of FeatureA must be added to the product to make the count of FeatureA and FeatureB the same (six).</p>
Package Name	<p>Name to uniquely identify the package: The name must contain 30 characters or less and cannot contain spaces. (The Package Name setting is only shown when Package is set to Yes.)</p>
Package Version Format	<p>Select a Fixed or Date Based version format. See Creating a FlexNet Publisher Licensing Toolkit License Generator (VCG) Configuration for more information about this property. (The Package Version Format setting is only shown when Package is set to Yes.)</p>

Table 2-10 •

Field	Description
Package Version	If a Fixed version format is selected, enter the latest (highest-numbered) version of this package that is supported by a generated license certificate. The version consists of numbers and at most one decimal point, with a ten character maximum, for example, 1 or 1.5. (The Package Version setting is only shown when Package is set to Yes .)
License Technology	The license technology with which this product is licensed. The license technology you choose affects the set of controls you see on the Create a Product page. If you choose FlexNet Licensing , the next control in the list is Can Be Used on a Device . If you choose a custom (non-FlexNet) license technology, the next control in the list is Host Type .
Can Be Used on a Device	Shown when you choose FlexNet Licensing as the license technology, this control allows the user to select usage models. Yes —displays a drop-down list of available usage models No —no usage models are displayed
Host Type	The appearance of the Host Type control depends upon the license technology you chose: <ul style="list-style-type: none"> • Shown as a drop-down list when you choose a custom (non-FlexNet) license technology, Host Type lists of host types defined for the license technology you specified. Choose one host type from the list. • Shown as a collection of check boxes when you choose FlexNet Licensing as the license technology, Host Type shows a separate check box for each host type defined for FlexNet Licensing. Click the check boxes for the host types this product will support.

Table 2-10 -


Field	Description
Usage Models	<p>The Usage Models attribute is available when you choose Yes for Can be Used on a Device.</p> <p>Usage Models shows a drop-down list of possible usage models. These determine the statement interval and reset period for usage reports. (See About Usage Models.)</p>  <p>Important - Products using the same feature must be configured with the same usage model per account. For an account, the usage model that is specified for a product containing a specific feature will be the usage model that is used for subsequent entitlements or products containing that specific feature.</p> <p>Example:</p> <ul style="list-style-type: none"> • Product A (feature f1) and product B (features f1 and f2) • Account C is first entitled to product A (feature f1) with usage model Monthly Statements (No Reset) • Account C is then entitled to product B (features f1 and f2) with usage model Monthly Statements (Reset Monthly) • Account C will use usage model Monthly Statements (No Reset) for both products A and B because they both contain feature f1 which was included in the first entitlement. <p>If Account C was first entitled to product B (features f1 and f2) with usage model Monthly Statements (Reset Monthly), this usage model would be used for both products/entitlements for the account.</p>
License Generator	The license generator used to generate licenses for this product
Header Resource Bundle Key	<p>If you are creating a certificate-based license, this key allows you to identify certain text that appears as a comment at the beginning of the .lic file that is generated when you fulfill the license.</p> <p>This field is hidden if the Allow license headers and trailers flag is disabled. Configure this flag in System > Configure > FlexNet Operations.</p>
Header Text	This is the value assigned to the key specified in the Header Resource Bundle Key field. This field only displays the value; you cannot edit the value.
Trailer Resource Bundle Key	If you are creating a certificate-based license, this key allows you to identify certain text that will appear as a comment at the end of the .lic file which is generated when you fulfill the license. This field is hidden if the Allow license headers and trailers flag is disabled. Configure this flag in System > Configure > FlexNet Operations .
Trailer Text	This is the value assigned to the key specified in the Trailer Resource Bundle Key field. This field only displays the value; you cannot edit the value.

Table 2-10 -



Field	Description
FNP Version	<p>The FNP Version check boxes allow you to specify the cross-version signature support required by your product.</p> <p>Cross-version signatures are required when the product must use the same license for product binaries built with different versions of the FlexNet Publisher Licensing Toolkit, if you want to add license keywords to the product license that are not supported by all the licensing toolkit versions with which your product binaries are built.</p> <p>Cross-version signatures permit versions of your product built with a license kit that predates the introduction of a keyword to run successfully using the same license and license server as the newer versions of your product that use that keyword. (However, they do <i>not</i> permit the older versions of your product to use the functionality of the newer keyword.)</p> <p>Select the FNP Version based on the older version of the toolkit used to build the product binaries.</p> <p>For example, if you are required to use the same license to support the SUPERSEDE_SIGN keyword in product binaries built with toolkit versions 11.5 (when SUPERSEDE_SIGN was introduced) and 11.0, select FNP Version 11.4.</p> <p>For more information about choosing the FNP Version values and using cross-version signatures, see FlexNet Publisher Versions for Cross-Version Signature Support.</p>
Allow Obsolete Fulfillment Download in Producer Portal	<p>Permits or prohibits the download of obsolete (zero count) fulfillments from the Producer Portal. By default, licenses cannot be emailed or saved for obsolete fulfillments. Click Yes to permit the downloading of obsolete fulfillments from the Producer Portal. Click No to prohibit it.</p>
Allow Obsolete Fulfillment Download in End-User Portal	<p>Permits the download of obsolete fulfillments from the End-User Portal. By default, licenses cannot be emailed or saved for obsolete fulfillments. Click Yes to permit the downloading of obsolete fulfillments from the End-User Portal. Click No to prohibit it.</p>
Start Date	<p>Only used for automatic upgrade jobs, the Start Date value defines the beginning of a date range for which this product qualifies as an upgrade-to product, based on the upgrade relationships as defined when the upgrade job runs. The date range defined by Start Date and End Date has no impact on manually generated upgrades nor on bulk operations.</p> <p>Start Date is only available for products; it is not available for maintenance products nor for product suites.</p> <p></p> <p>Note - If the year that you want to set is not currently available from the calendar, select the year that is closest to the desired year. This automatically increases the list by 10 years from the year you selected.</p>

Table 2-10 -

Field	Description
End Date	<p>Only used for automatic upgrade jobs, the End Date value defines the end of the date range for which this product qualifies as an upgrade-to product, based on the upgrade relationships as defined when the upgrade job runs. The date range defined by Start Date and End Date has no impact on manually generated upgrades nor on bulk operations.</p> <p>End Date is only available for products; it is not available for maintenance products nor for product suites.</p> <p></p> <p>Note - <i>If the year that you want to set is not currently available from the calendar, select the year that is closest to the desired year. This automatically increases the list by 10 years from the year you selected.</i></p>
Email Template to Use for Product Upgrade	<p>Specify the variation of the Product Upgrade Job Email template to use when FlexNet Operations automatically creates upgrade lines as a result of running the Product Version Upgrade job. Producers can choose the default variation, another active variation, or none:</p> <ul style="list-style-type: none"> ● DEFAULT—FlexNet Operations uses the default variation of the Product Upgrade Job Email template for automatic upgrades to this product. ● None—FlexNet Operations does not send emails for automatic upgrades to this product. ● Another variation—FlexNet Operations uses the selected variation of the Product Upgrade Job Email template for automatic upgrades to this product. (Only active variations of the Product Upgrade Job Email template are available for selection. Draft variations are not shown.) <p>When automatic upgrade emails are sent, FlexNet Operations sends the upgrade email to the end-customer contact address in the parent entitlement (if one is available). If no end-customer contact address exists, FlexNet Operations sends the upgrade email to any addresses in the Ship To Email field in the parent entitlement as well as to all channel partner contacts in the parent entitlement (if any).</p> <p>For information about the Product Upgrade Job Email template, see Email Template Types in About Email Templates.</p> <p>For information about the Product Version Upgrade job, see FlexNet Operations Alert Types.</p>

Continue the product packaging process by adding features (recommended) on this page or moving on to link a license model to the product. Or you can save the product in its current state.

- To add features, click **Add Features** or **Add Feature Bundles**. These buttons open a pop-up window for selecting features or feature bundles to add. See [Adding Features or Feature Bundles to a Product](#) for instructions.

- To move on to link license models to this product, click **Next**. The Producer Portal shows the **Link License Models to Product** page. See [Linking License Models to a Product](#) for instructions.
- To save the product in its current state, click **Save**.

FlexNet Publisher Versions for Cross-Version Signature Support

This topic applies to the product creation and suite creation process only for FLEXenabled applications that use a certificate license model administered via a license server. For such applications, it may be necessary to select one or more FlexNet Publisher Versions for cross-version signature support when you are creating the product or suite in FlexNet Operations.

Who Needs Cross-Version Signature Support?

The purpose of a cross-version signature is to allow developers to use newer license keywords (such as SUPERSEDE_SIGN or TZ) without breaking the license for older versions of their product, when the older and newer versions of the product must use the same license.

Normally, an application built with a particular version of the FlexNet Publisher Licensing Toolkit cannot authenticate a license that includes keywords introduced in a newer version of FlexNet Publisher. Cross-version licenses enable you to issue license files containing new licensing keywords to customers who will continue to use older versions of your FLEXenabled application alongside newer versions of your application.

When a FLEXenabled application checks out a feature from a license server, it authenticates the information in the feature line against the signature. Typically, it must recognize all keywords present in the feature line in order to authenticate this information. Cross-version signatures allow the older application to ignore the newer keywords. When an older FLEXenabled application authenticates the feature line, it ignores the newer keyword and uses the FlexNet Publisher version-specific signature.

Determining which FNP Version Values are Required

The table, below, cross-references the keyword with the version of the FlexNet Publisher Licensing Toolkit client libraries your FLEXenabled application uses. Where a cross-version signature can be used, the table shows the correct FlexNet Publisher Version value. (Empty cells mean no cross-version signature is necessary.) For example, to use the VM_PLATFORMS keyword with a FlexEnabled application that uses toolkit version 11.0, use 11.4 for the FlexNet Publisher Version value.

Table 2-11 • FlexNet Publisher Versions for Cross-Version Keyword Support

Keyword	Toolkit Version in the FlexEnabled Application						
	7.1-7.2	8.0	8.1-8.3	8.4	9.0-10.8.n	11.0-11.4.1	11.5-11.6.1
BORROW	7.1						
COMPOSITE	7.1	8.0	8.1				
FLOAT_OK	7.1						
SUITE_RESERVED	7.1	8.0					

Table 2-11 • FlexNet Publisher Versions for Cross-Version Keyword Support (cont.)

Keyword	Toolkit Version in the FlexEnabled Application						
	7.1-7.2	8.0	8.1-8.3	8.4	9.0-10.8.n	11.0-11.4.1	11.5-11.6.1
SUPERSEDE_SIGN	7.1	8.0	8.1	8.4	10.8	11.4	
TZ	7.1	8.0	8.1	8.4	10.8	11.4	11.6
VM_PLATFORMS	7.1	8.0	8.1	8.4	10.8	11.4	11.6

Keyword Support in Deployed License Servers

When publishers choose to support the newer keywords with the same license and within the same environments used by prior versions of the same product or suite, they must also ship updated license servers (or vendor daemons) to their customers. License servers built with toolkit versions prior to the version in which a keyword was introduced cannot understand the keyword. (Product binaries are not required to be changed. The older products are still able to check-out/check-in licenses from a FlexNet Publisher license server.)

See Also

- [Creating a Product](#)
- [Creating a Suite](#)

Adding Features or Feature Bundles to a Product

Products are collections of features. Use the controls on the **Create a Product** page to add features and feature bundles to a product.



Task *To add a feature or feature bundles to a product*

1. A pop up window appears in which you can search for and select one or more of the **Available Features/Feature Bundles**. Note that the list may be large enough to appear on multiple pages in the pop-up window.
2. Click the right arrow to move those features to the **Selected Features/Feature Bundles** list.
3. When the list is complete, click the **Add** button to add the features or feature bundles to the product.
4. On the **Create a Product** page, if necessary, modify the **Quantity** to change the count of the feature or feature bundle in the product.
 - For example, say the count of Feature A is 3 in feature bundle FB1. When 2 units of FB1 are added to a product, a license generated for the product contains 6 counts of Feature A.
 - To remove one or more features or feature bundles from the product, select the features or feature bundles and click the **Remove Features or Feature Bundles** button. Click the **Reset** button to reset all the product fields.
5. On the **Create a Product** page, click the **Save** button to save the product or click the **Add New Product** button to save the product and start to create another product.



Note - After a product has been saved, the history of its state change can be viewed by clicking the **View History** button.

- Click the **Next** button to link license models to a product.



Note - Adding or removing features to or from an existing product with a line item mapped to a Cloud License Server (CLS) instance will result in the feature changes being cascaded to all CLS instances with that line item.

Linking License Models to a Product

Before a license can be generated for a product, the product must be associated with one or more license models. Only license models linked to a product can be used in an entitlement for the product.



Task To link a license model with a product

- Select a product.

Table 2-12 - Linking a License Model with a Product

Item	Description
Product or Suite	<p>Name of the product or suite to associate with one or more license models:</p> <ul style="list-style-type: none"> If you arrived at this page by clicking through the product packaging wizard, a name is loaded automatically into the Product or Suite field. Otherwise, click the Search button to open a pop-up window in which you can search for the product or suite to associate with license models. Alternatively, type the name of the product or suite into the Product or Suite field.

- After the product is selected, click the **Link License Models** button. This button opens the **Link License Models** page in a pop-up window. License models can be added or removed from draft or deployed products.
 - In the **Link License Models** pop-up window, select one or more license models from the **Available License Models** list. Note that the list of license models may be large enough to appear on multiple pages in the pop-up window.
 - Click the right arrow to move selected license models to the **Selected License Models** list.
 - When the **Selected License Models** list is complete, click **Add**. This button associates the selected license models with the specified product and closes the pop-up window.
- If you selected a trusted license model, specify **Transaction Keys**; otherwise, skip to the next step. Use the **Default** and **Virtual** controls to identify one default transaction key or one virtualization-aware transaction key, or both a default transaction key *and* a virtualization-aware transaction key.

4. Click the **Save** button to save the association of license models with the product.
5. Click the **Next** button to map a product to a part number.



Note - On the **Link License Models to Product** page, click the **Reset** button to reset the linked license models. To remove the link between selected license models and this product, select those license models and click the **Remove License Models** button.

Mapping a Product to a Part Number

A product can be mapped to one or more part numbers. Part numbers are optional and are selected from a group of unassigned part numbers that have been imported into FlexNet Operations.

A part number can also be mapped to a particular license model linked with a product. When a part number is mapped to a license model, only that license model can be used in the entitlement.



Task **To map a product to a part number**

1. Select a product.

Table 2-13 - Mapping a Product to a Part Number

Item	Description
Product, Suite, or Maintenance	Name of the product, suite, or maintenance to map to one or more unassigned part numbers: <ul style="list-style-type: none">• If you arrived at this page by clicking through the product packaging wizard, a name is loaded automatically into the Product, Suite, or Maintenance field.• Otherwise, click the Search button to open a pop-up window in which you can search for the product, suite, or maintenance to map to part numbers.

2. After the product is selected, click the **Map to Part Numbers** button.
 - a. A pop-up window appears in which you can search for and select one or more of the **Available Part Numbers**. Note that the list of part numbers may be large enough to appear on multiple pages in the pop-up window.
 - b. Click the right arrow to move those part numbers to the **Selected Part Numbers** list.
 - c. When the **Selected Part Numbers** list is complete, click the **Add** button to map the part numbers to the product.
3. If you want to map this part number to a specific license model that is already linked with this product, select that license model. This means that if the part number is used to specify a product in an entitlement, only this license model can be used.
 - Click the **Reset** button to reset the mapped part numbers. To remove the link between selected part numbers and this product, select those part numbers and click the **Remove Part Numbers** button.

4. Click **Save** to save the mapping of part numbers to the product.
5. Click **Next** to relate a product to other products.

Relating Products to Other Products

A product can be related to one or more products, including itself. To use the upgrade and upsell operations on entitlement line items, upgrade and upsell relationships must be defined. Demo and production relationships between products can also be defined, and demo relationships can be used to upgrade entitlements. Products can be related in draft or deployed states.



Tip - Upgrade relationships are essential for the automatic creation of upgrade line items by the Product Version Upgrade job. See [FlexNet Operations Alert Types](#).



Task To relate products to other products

1. Select a product.

Table 2-14 - Relating Products to Other Products

Item	Description
Product, Suite, or Maintenance	<p>Name of the product, suite, or maintenance to relate to a product, suite, or maintenance:</p> <ul style="list-style-type: none"> ● If you arrived at this page by clicking through the product packaging wizard, a name is loaded automatically into the Product, Suite, or Maintenance field. ● Otherwise, click the Search button to open a pop-up window in which you can search for the product, suite, or maintenance to specify product relationships. ● Alternatively, type the name of the product, suite, or maintenance into the Product, Suite, or Maintenance field.

2. After the product is selected, navigate to the **Relate to Different Products** page.
3. On the **Relate to Different Products** page, click **Select Related Products**. The Producer Portal shows the **Select Product** page in a pop-up window. There, you can search for and select one or more available products to relate to the current product.



Note - The list of products may be large enough to span multiple pages in the pop-up window. You can limit the number of products using the search controls.

- a. In the pop-up window, click one or more check boxes to select products for which you want to define product relationships.

- b. When you have selected all related products, click **OK**. The Producer Portal adds the relationships and closes the pop-up window.
4. On the **Relate to Different Products** page, specify the relationships between the current product and the related products.
 - Specify the relationships between the current product and the related products.

If the current product is maintenance, the relationship **Is Maintenance** is chosen automatically.

If the related product is maintenance, the relationship **Has Maintenance** is chosen automatically.

Otherwise, choose from one of the following relationships:

- **Production Version Of**
- **Demo Of**
- **Upgrade From**
- **Upgrade To**
- **Upsell From**
- **Upsell To**

The relationship setting defines how the related product is tied to the current product. For example, if the current product is a newly created version 2.0 of a product and, in the pop-up window, you selected version 1.0 of the same product, you would set the relationship to **Upgrade From**. If the current product is version 1.0 of the product and, in the pop-up window, you selected version 2.0 as a related product, you would set the relationship of **Upgrade To**.

- Optionally specify a default license model for the Product Version Upgrade job.

If, for the product relationship, you chose either **Upgrade To** or **Upgrade From**, the Producer Portal shows an **Upgrade Default Model** setting for the Upgrade-To product.

The license model choices available in Upgrade Default Model depend on the license models linked to the Upgrade-To product. (The *Upgrade-To product* is the product to which users can upgrade; depending on whether you chose Upgrade To or Upgrade From for the relationship, the Upgrade-To product will be either the related product or the current product.) If only one license model is linked to the Upgrade-To product, the Producer Portal automatically selects that license model. If multiple license models are linked to the Upgrade-To product, Upgrade Default Model allows you to choose from those license models or None.

- If you do not use the Product Version Upgrade job, leave **Upgrade Default Model** set to **None**.
- If you do use the Product Version Upgrade job, set **Upgrade Default Model** to the default license model to use in upgrade entitlements created by that job.

The default license model is only used in upgrade entitlements for the product relationship on which it is set. FlexNet Operations only applies the default license model if the related product is not linked to the license model on the entitlement to be upgraded.

For more information about the Product Version Upgrade job, see [More About the Product Version Upgrade Job](#) under [FlexNet Operations Alert Types](#).



Tip - Click the **Reset** button to reset the product relationships. To remove the relationship between related products and the current product, select those related products and click the **Remove Relationship** button.

5. Click the **Save** button to save the relationship to the product.
6. Click the **Next** button to review the products that have been recently created.

See Also

[Mapping a Product to a Product Line](#)
[Working with Products](#)

Mapping a Product to a Product Line

You can assign products to product lines, which can be used to group products for search and reporting purposes. In addition, product lines can be used to define access rights to product information for users.



Note - If product lines are disabled, follow the instructions in [Managing Product Lines](#) to enable product line functionality.



Task **To assign a product to a product line**

1. Locate the product for which you want to map a product line, and click the product to open its **Create a Product** page.
2. On the **Create a Product** page, navigate to the **Map Product to Product Line** page.
3. On the **Map Product to Product Line** page, specify the product line to be assigned to the product. Do one of the following:
 - Type the name of the product line.
 - Click the **Product Line** search button to search for a product line to be assigned to the product. The **Select Product Line for Product** window opens. Select a product line, then click **OK**. On the **Map Product to Product Line** page, the selected product line appears in the **Product Line** field followed by any defined product line attributes.
4. Click a product line, then click **OK**. On the **Map Product to Product Line** page, the selected product line appears in the **Product Line** field followed by any defined product line attributes.
5. Enter values for any required product line attributes (marked with a red asterisk). Optionally, enter values for any optional attributes.
6. Click **Save** to save the mapping, or click **Next** to review recently created products.

To grant a user access to a product line, link the product line to the user's account. See [Linking Product Lines to User Accounts](#).

See Also

[Managing Product Lines](#)

Reviewing Products

After you create products, you can review the products that have been recently created and perform the same operations on them as you could when [viewing products](#).

Deploying a Product

Before a product is deployed, all license models with which it has been linked must first be deployed. When a product is deployed, all the features and feature bundles it contains are also deployed.



Task *To change the state of one or more products:*

1. Select the products.
2. Click the **Change State** choice list, and select a state. Products can be in one of the following states: **Draft**, **Deployed**, **Inactive**, or **Obsolete**. A product is created and can be edited in the **Draft** state.
3. If you choose **Deploy**, the **Deploy Products** page appears displaying the list of products and the undeployed feature bundles and undeployed features they contain that will be deployed. Click the **Deploy** button to deploy the products and all of their feature bundles and features.

Reviewing New Product Hierarchy

After creating products, you can review the features, feature bundles, and products you have created. To do this, select **Show Product Definition** under **Step 3, Add Product**, on the **Package Products** page.

Working with Suites

A *suite* is packaged from individual products that are functionally complementary, and is associated with one or more [license models](#). One or more part numbers can be assigned to a suite.

Table 2-15 •

Topic	Description
Viewing Suites	Briefly describes viewing, adding, deleting, printing, and changing the state of suites.
Creating a Suite	Covers the suite creation process more thoroughly.
Adding Products to a Suite	Describes how to add products to a suite.
Linking License Models to a Suite	Explains how to link a suite to one or more license models.

Table 2-15 •

Topic	Description
Mapping a Suite to a Part Number	Shows how to map a suite to one or more part numbers.
Relating Suites to Other Products	Shows how to define relationships between a suite and one or more different products.
Deploying a Suite	Explains how to change a suite's state from Draft to Deployed.

Viewing Suites

This **Package Products** page automatically displays recently accessed suites, if applicable. To view all suites, select **Suites** from the **Search For** choice list, and click the **Simple Search** button. You can also search for suites based on specific criteria.

From this page, you can:

Table 2-16 • Viewing Suites Capabilities

Capability	Description
Add (create) a new suite from scratch	To add a new suite, click Create a Suite .
Make a new suite from a copy of an existing suite	To copy a suite, select exactly one suite and click the Copy button. Follow the guidelines in Creating a Suite .
Delete a suite	To delete a suite, select one or more suites and click the Delete button.
Change the state of a suite	Suites can be in one of the following states: Draft, Deployed, Inactive, or Obsolete.
Print a suite	To print a suite, select one or more suites and click the Print button.

Creating a Suite

There are several ways to navigate to the page where a new suite is created.



Task

To create a new suite

1. Click **Products > Suites**. This opens the **Package Products** page.
2. Click the **Add New Suite** button.

Follow the steps below to **create the suite**.



Task **To copy an existing suite**

1. Click **Products > Suites**. This opens the **Package Products** page.
2. Search for a suite to copy.
3. Select the suite and click the **Copy** button.

Follow the steps below to [create the suite](#).



Note - Required fields are indicated with a red asterisk.



Task *To create the new suite*

1. Provide values for the following fields:

Field	Description
Suite Name	Name to uniquely identify this suite. The name can contain spaces.
Description	The characteristics of this suite that make it unique.
Version	A string that can contain any characters up to a maximum of 64, for example, 1.2.3 or SP1.
State	<p>A suite can be in one of four states: draft, deployed, inactive, or obsolete.</p> <ul style="list-style-type: none"> ● Draft: A suite is created as a draft that can be modified or deleted; draft suites can contain draft or deployed products. ● Deployed: If the suite is deployed, all the draft features, feature bundles, and products it contains are also deployed. After a suite is deployed to use in production, it cannot be deleted or modified, except to change the transaction key and to add or remove license models, part numbers, or relationships. A deployed suite can be used to create an entitlement. ● Inactive: If a suite is made inactive, its products are not made inactive. An inactive suite cannot be deleted or modified. An inactive suite cannot be used to create an entitlement or to be the parent of a maintenance product, but an inactive product can be activated, upgraded, upsold, or renewed from an existing entitlement line item. ● Obsolete: Deployed and inactive suites can be made obsolete. Obsolete suites behave like inactive suites, but can be deleted.
Package	<p>Specify that this suite is a package if you want to:</p> <ul style="list-style-type: none"> ● Provide a way of distributing one line for a license file that has a large number of features, which share most of the same feature line arguments ● License this suite as a suite <p>Even if a suite is specified as a package, if a license model is specified for the suite that does not support PACKAGES (that is, Package Specification is None), the license model takes precedence and individual feature lines are generated.</p> <p>The count of unique features in a package must be the same. For example, if a feature bundle containing 3 counts of FeatureA and 6 counts of FeatureB is added to a product, then for that product to be licensed with a PACKAGE line, 3 more counts of FeatureA must be added to the product to make the count of FeatureA and FeatureB the same (6).</p>
Package Name	Name to uniquely identify the package. The name must contain 30 characters or less and cannot contain spaces.

Field	Description
Package Version Format	Select a Fixed or Date Based version format . See Creating a FlexNet Publisher Licensing Toolkit License Generator (VCG) Configuration for more information about this property.
Package Version	If a Fixed version format is selected, enter the version of the latest (highest-numbered) version of this package that is supported by a generated license certificate. The version consists of numbers and at most one decimal point, with a ten character maximum, for example, 1 or 1.5.
License Technology	The license technology with which this suite is licensed. The license technology you choose affects the set of controls you see on the Create a Suite page. If you choose FlexNet Licensing , the next control in the list is Can Be Used on a Device . If you choose a custom (non-FlexNet) license technology, the next control in the list is Host Type .
Can Be Used on a Device?	Shown when you choose FlexNet Licensing as the license technology, this control allows the user to select usage models. Yes —displays a drop-down list of available usage models No —no usage models are displayed
Host Type	The appearance of the Host Type control depends upon the license technology you chose: <ul style="list-style-type: none">• Shown as a drop-down list when you choose a custom (non-FlexNet) license technology, Host Type lists of host types defined for the license technology you specified. Choose one host type from the list.• Shown as a collection of check boxes when you choose FlexNet Licensing as the license technology, Host Type shows a separate check box for each host type defined for FlexNet Licensing. Select the check boxes for the host types this suite supports.
License Generator	The license generator used to generate licenses for this product.

Field	Description
FNP Version	<p>Only shown if the newer FlexNet Publisher keywords are used for renewals and upgrades. The FNP Version check boxes allow you to specify the cross-version signature support required by your suite.</p> <p>Cross-version signatures are required when the suite must use the same license to support the use of newer keywords (such as SUPERSEDE_SIGN and TZ) on binaries built with different versions of the FlexNet Publisher Licensing Toolkit. Cross-version signatures permit versions of your suite built with a license kit that predates the introduction of a keyword to be successfully activated under the same license and license server as the newer versions of your suite that use that keyword. (However, they do <i>not</i> permit the older versions of your suite to utilize the functionality of the newer keyword.)</p> <p>Select the FNP Version based on the older version of the toolkit used to build the suite binaries.</p> <p>For example, if you must use the same license to support the SUPERSEDE_SIGN keyword in binaries built with toolkit versions 11.5 (when SUPERSEDE_SIGN was introduced) and 11.0, select FNP Version 11.4.</p> <p>For more information about choosing the FNP Version values and using cross-version signatures, see FlexNet Publisher Versions for Cross-Version Signature Support.</p>
Allow obsolete fulfillment download in Producer Portal?	Permits or prohibits the download of obsolete (zero count) fulfillments from the Producer Portal. By default, licenses cannot be emailed or saved for obsolete fulfillments. Click Yes to permit the downloading of obsolete fulfillments from the Producer Portal. Click No to prohibit it.
Allow obsolete fulfillment download in End-User Portal?	Permits the download of obsolete fulfillments from the End-User Portal. By default, licenses cannot be emailed or saved for obsolete fulfillments. Click Yes to permit the downloading of obsolete fulfillments from the End-User Portal. Click No to prohibit it.

- Click the **Add Products** button to [continue creating the suite](#).

Continue the product packaging process by adding products on this page or moving on to link a license model to the suite. Or you can save the product in its current state.

- To add products, click **Add Products**. This button opens a pop-up window for selecting products to add to the suite. See [Adding Products to a Suite](#) for instructions.
- To move on to link license models to this suite, click **Next**. The Producer Portal shows the **Link License Models to Suite** page. See [Linking License Models to a Suite](#) for instructions.
- To save the suite in its current state, click **Save**.

Adding Products to a Suite

Use the controls on the **Create a Suite** page to add products to a suite.



Task

To add products to a suite

1. In the **Add Products** pop-up window, select one or more check boxes to select products.
Note that the list of products may be large enough to appear on multiple pages in the pop-up window.
2. When the list is complete, click the **OK** button to add the products to the suite.
3. On the **Create a Suite** page, if necessary, modify the **Quantity** to change the count of the product in the suite.
 - To remove one or more products from the list of products in the suite, select the products and click the **Remove Products** button. Click the **Reset** button to reset all the suite fields.
4. Continue the product packaging process by moving on to link a license model to the suite or saving the suite in its current state.
 - To move on to link license models to this suite, click **Next**. The Producer Portal shows the **Link License Models to Suite** page. See [Linking License Models to a Suite](#) for instructions.
 - To save the suite in its current state, click **Save**.



Note - After a suite has been saved, the history of its state change can be viewed by clicking the **View History** button.

Linking License Models to a Suite

Before a license can be generated for a suite, the suite must be associated with one or more license models. Only license models linked to a suite can be used in entitlements for the suite.



Note - License models linked to products in a suite are ignored when an entitlement is created for the suite.



Task *To associate a suite with a license model*

1. Select a suite.

Table 2-17 • Link License Models

Item	Description
Suite	<p>Name of the suite to associate with one or more license models:</p> <ul style="list-style-type: none"> ● If you arrived at this page by clicking through the product packaging wizard, a suite name is loaded automatically into the Suite field. ● Otherwise, click the Search button to open a pop-up window in which you can search for the suite to associate with license models ● Alternatively, type the name of the suite into the Suite field.

2. After the suite is selected, click the **Link License Models** button.
 - a. A pop-up window appears in which you can search for and select one or more of the **Available License Models**. Note that the list of license models may be large enough to appear on multiple pages in the pop-up window.
 - b. Click the right arrow to move those license models to the **Selected License Models** list.
 - c. When the **Selected License Models** list is complete, click the **Add** button to associate the license models with the suite.
3. Continue with the product packaging process by saving the suite with its current settings or moving on to map part numbers.
 - Click the **Save** button to save the association with the suite.
 - Click the **Next** button to map a suite to a part number. (See [Mapping a Suite to a Part Number](#) for instructions.)



Note • On the **Link License Models to Suite** page, click the **Reset** button to reset the linked license models. To remove the link between selected license models and this suite, select those license models and click the **Remove License Models** button.

Mapping a Suite to a Part Number

A suite can be mapped to one or more part numbers. Part numbers are optional and are selected from a group of unassigned part numbers that have been imported into FlexNet Operations. A part number can be mapped to a particular license model linked with a suite.



Task **To map a suite to a part number**

1. Select a suite.

Table 2-18 ▪ Mapping a Suite to a Part Number

Item	Description
Suite	Name of the suite to map to one or more unassigned part numbers: <ul style="list-style-type: none">● If you arrived at this page by clicking through the product packaging wizard, a suite name is loaded automatically into the Suite field.● Otherwise, click the Search button to open a pop-up window in which you can search for the suite to map to part numbers.● Alternatively, type the name of the suite into the Suite field.

2. After the suite is selected, click the **Map to Part Numbers** button.
 - a. A pop-up window appears in which you can search for and select one or more of the **Available Part Numbers**. Note that the list of part numbers may be large enough to appear on multiple pages in the pop-up window.
 - b. Click the right arrow to move those part numbers to the **Selected Part Numbers** list.
 - c. When the **Selected Part Numbers** list is complete, click the **Add** button to map the part number to the suite.
3. If you want to map this part number to a specific license model that is already linked with this suite, select that license model.
 - Click the **Reset** button to reset the mapped part numbers. To remove the link between selected part numbers and this suite, select those part numbers, and click the **Remove Part Numbers** button.
4. Continue with the product packaging process by saving the suite in its current state or moving on to relate the suite to other products.
 - Click the **Save** button to save the mapping of part numbers to the suite.
 - Click the **Next** button to relate a suite to other products. (See [Relating Suites to Other Products](#) for instructions.)

Relating Suites to Other Products

A suite can be related to one or more products, including itself. Products can be related in draft or deployed states.



Tip ▪ Upgrade relationships are essential for the automatic creation of upgrade line items by the Product Version Upgrade job. See [FlexNet Operations Alert Types](#).



Task *To relate a suite to another product*

1. Select a suite.

Table 2-19 • Relating Suites to Other Products

Item	Description
Suite	<p>Name of the suite to relate to a product, suite, or maintenance:</p> <ul style="list-style-type: none"> ● If arrived at this page by clicking through the product packaging wizard, a name is loaded automatically into the Suite field. ● Otherwise, click the Search button to open a pop-up window in which you can search for the suite to relate. ● Alternatively, type the name of the suite into the Suite field.

2. After the suite is selected, click the **Select Related Products** button.
 - a. A pop-up window appears in which you can search for and select one or more of the available products. Note that the list of products may be large enough to appear on multiple pages in the pop-up window.
 - b. Select one or more check boxes to select suites.
 - c. When the list is complete, click the **OK** button to add the related products.
 - d. On the **Relate to Different Products** page, select the relationship between the suite and the related product. Choose from one of the following relationships: **Production Version Of, Demo Of, Upgrade From, Upgrade To, Upsell From, Upsell To**.
3. Continue by saving the suite in its current state or moving on to review the suite settings.
 - Click the **Save** button to save the relationship to the suite.
 - Click the **Next** button to review the suites that have been recently created.



Note • On the **Relate to Different Products** page, click the **Reset** button to reset the suite relationships. To remove the relationship between selected products and this suite, select those products and click the **Remove Relationship** button.

Deploying a Suite

Before a suite is deployed, all license models with which it has been linked must first be deployed. When a suite is deployed, all the products it contains are also deployed.



Task **To change the state of one or more suites**

1. Select the suites.
2. Click the **Change State** choice list, and select a state. Suites can be in one of the following states: **Draft**, **Deployed**, **Inactive**, or **Obsolete**.
3. If you choose **Deploy**, the **Deploy Suites** page appears displaying the list of suites and the undeployed products, feature bundles, and features they contain will also be deployed. Click the **Deploy** button to deploy the suites and all of their products, feature bundles, and features.

Working with Maintenances

A maintenance is an unlicensed product that represents additional rights that a customer can purchase. For example, maintenance may give the customer the right to technical support, upgrades, updates, or new platforms for the duration of maintenance.

A maintenance product may be associated with one or more part numbers and can be related to one or more products or suites.

Table 2-20 ▪

Topic	Description
Creating a Maintenance	Explains how to create a maintenance.
Mapping a Maintenance to a Part Number	Shows how to map a maintenance to one or more part numbers.
Relating Maintenance to Other Products	Describes how to define relationships between a maintenance and other products.

Creating a Maintenance

You can create maintenances from the Producer Portal's **Administer** menu.



Tip ▪ To reset all the fields on the **Create Maintenance** page to their defaults at any time, click the **Reset** button.



Task *To create a new maintenance product*

1. Click **Products > Create Maintenance**. This opens the **Create Maintenance** page.
2. Provide values for the following fields. Required fields are indicated with a red asterisk.

Table 2-21 ▪ Creating Maintenance Fields

Field	Description
Name	Name of the maintenance
Version	A string that can contain any characters up to a maximum of 64, for example, 1.2.3 or SP1.
State	<p>A maintenance product can be in one of four states: draft, deployed, inactive, or obsolete.</p> <ul style="list-style-type: none"> ● Draft: A maintenance product is created as a draft that can be modified or deleted. After a maintenance product is deployed to use in production, it cannot be deleted or modified, except to add or remove part numbers. ● Deployed: A deployed maintenance product can be added to an entitlement. ● Inactive: An inactive maintenance product cannot be deleted or modified. An inactive maintenance product cannot be added to an entitlement. ● Obsolete: Deployed and inactive maintenance products can be made obsolete. Obsolete maintenance products behave like inactive maintenance products, but can be deleted.
Description	Describe the characteristics of this maintenance that make it unique.

3. Complete the maintenance creation process by clicking **Save, Add New Maintenance,** or **Next**.
 - Click **Save** to save the maintenance and remain on the current page.
 - Click **Add New Maintenance** to save this maintenance and start to create another maintenance.
 - Click **Next** to map a maintenance to a part number. (See [Mapping a Suite to a Part Number](#) for instructions.)

A maintenance product is created as a draft that can be modified. After a maintenance product is deployed to use in production, it cannot be modified.



Tip ▪ After a maintenance product has been saved, the history of its state changes can be viewed by clicking the **View History** button.

See Also

- [Mapping a Maintenance to a Part Number](#)
- [Relating Maintenance to Other Products](#)

Mapping a Maintenance to a Part Number

A maintenance product can be mapped to one or more part numbers. Part numbers are optional and are selected from a group of unassigned part numbers that have been added or imported into FlexNet Operations.



Note - If you are already on the **Map Part Numbers to Maintenance** page, skip to step 4.



Task

To map a maintenance to a part number

1. Click **Products > Products**. This opens the **Products** page. (Existing maintenances are shown, by default, on the **Products** page.)
2. Search, as necessary, to show the maintenance for which you want to map part numbers. Then click the name of the maintenance product. This opens the **Create Maintenance** page for that maintenance.
3. On the **Create Maintenance** page, click **Next**. This opens the **Map Part Numbers to Maintenance** page.
4. Click **Map to Part Numbers**. A pop-up window appears in which you can search for and select one or more of the **Available Part Numbers**. (Note that the list of part numbers may be large enough to appear on multiple pages in the pop-up window.)
 - a. Click the part numbers you want to map to the maintenance.
 - b. Click the right arrow to move those part numbers to the **Selected Part Numbers** list.
 - c. When the **Selected Part Numbers** list is complete, click **OK** to map the part numbers to the maintenance product.

If necessary, click the **Reset** button to reset mapped part numbers.

To remove the mapping between selected part numbers and this maintenance, select those part numbers and click the **Remove Part Numbers** button.

5. Complete the mapping process by clicking either **Save** or **Next**.
 - Click **Save** to save the mapping of part numbers to the maintenance product.
 - Click **Next** to relate a maintenance product to other products. (See [Relating Suites to Other Products](#) for instructions.)

See Also

[Relating Maintenance to Other Products](#)
[Creating a Maintenance](#)

Relating Maintenance to Other Products

Maintenance can be related to one or more products. Products can be related in draft or deployed states.



Note - If you are already on the **Map Part Numbers to Maintenance** page, skip to step 4.



Task *To relate maintenance to other products*

1. Click **Products > Products**. This opens the **Products** page. (Existing maintenances are shown, by default, on the **Products** page.)
2. Search, as necessary, to show the maintenance for which you want to map part numbers. Then click the name of the maintenance product. This opens the **Create Maintenance** page for that maintenance.
3. On the **Create Maintenance** page, click **Next**. This opens the **Map Part Numbers to Maintenance** page.
4. On the **Map Part Numbers to Maintenance** page, click **Next**. This button opens the **Relate to Different Products** page.
5. Click the **Select Related Products** button. A pop-up window appears in which you can search for and select one or more of the available products. (Note that the list of products may be large enough to appear on multiple pages in the pop-up window.)
 - a. Click one or more check boxes to select products.
 - b. When the list is complete, click the **OK** button to add the related products.
 - c. On the **Relate to Different Products** page, select the relationship **Is Maintenance** between the maintenance and the related product.

If necessary, click the **Reset** button to reset the maintenance relationships.

To remove the relationship between selected products and this maintenance, select those products and click the **Remove Relationship** button.

6. Complete the product relationship process by clicking **Save** or **Complete**.
 - Click **Save** to save the relationship to the maintenance product and remain on the current page.
 - Click **Complete** to save the relationship to the maintenance product and return to the **Products** page.

See Also

[Mapping a Maintenance to a Part Number](#)
[Creating a Maintenance](#)

Managing Part Numbers

Many publishers use part numbers to identify their products. Part numbers are also instrumental in making products available for free trials in the End-User Portal.

During product packaging in FlexNet Operations, part numbers can be mapped to products, suites, and maintenance. A product, suite, or maintenance can be mapped to one or more part numbers; a part number can be mapped to only one product, suite, or maintenance.

Part numbers can be added into FlexNet Operations, or imported from a properly-formatted text file.

You can search for existing part numbers by number, product, license model, part numbers mapped to products, or part numbers mapped to license models.

Table 2-22 -

Topic	Description
Adding Part Numbers	Describes how to manually input individual part numbers.
Deleting Part Numbers	Shows how to delete existing part numbers.
Mapping Part Numbers	Explains how to map a part number to a product.
Importing Part Numbers	Redirects producers to the Importing and Exporting Entities topic for information about importing part numbers.

See Also

[About Trial Products](#)

Adding Part Numbers

You can add part numbers on the **Part Numbers** page.



Task

To add a new part number

1. Click **Products > Part Numbers**. This link opens the **Part Numbers** page.
2. On the **Part Numbers** page, click **Add**.
3. In **Part Number**, enter the new part number.
4. In **Description**, enter a brief description of this part number.
5. In **Product Name**, search for a product and select a license model.
6. For **Available for Trial**, select the check box to indicate whether you want this part number to be part of a trial registration program.



Tip - The **Available for Trial** check box is not active until the part number has been mapped to a deployed product and a deployed license model.

7. Click **Save** to save the number, or click **Add New Part Number** to continue adding part numbers.

FlexNet Operations associates the new part number with the product and license model you chose.

See Also

[Managing Part Numbers](#)
[About Trial Products](#)
[Mapping Part Numbers](#)

Deleting Part Numbers

You can delete part numbers on the **Part Numbers** page.



Task *To delete a part number*

1. Select the part number to delete and click **Delete**.
2. Click **OK** to confirm deletion.

See Also

[Managing Part Numbers](#)
[Adding Part Numbers](#)

Mapping Part Numbers

Existing part numbers can be mapped to a product and a license model directly from the **Part Numbers** page (**Products > Part Numbers**). You can also map part numbers to products on the **Create a Part Number** page.



Task *To map a part number to a product and a license model*

1. On the **Part Numbers** page, select the part number and click **Map to Product**.
2. On the **Select Product** page, select the product you want to map to.
3. In the **License Model** drop-down, select the license model.
4. Click **OK**. The part number is now mapped to the product.

See Also

[Managing Part Numbers](#)
[Adding Part Numbers](#)

Importing Part Numbers

With FlexNet Operations, you can use the Import/Export functionality to import part numbers.

See [Importing and Exporting Entities](#) for more information.

Managing Product Lines

Product lines allow you to group, classify, and describe products.

Depending on your system configuration settings, product lines can also be used to define access rights to product information for internal users in large accounts with diverse product offerings. For example, a product manager for a CRM product might be authorized to view products and entitlements for only CRM products,

instead of viewing products across an account's entire product set. Likewise, product lines can be used on End-User Portal sites to ensure that customer users see only the items related to the product lines to which their accounts are linked.

For many producers, product lines are completely optional. However, there are two scenarios where product lines are required:

- For producers who use FlexNet Electronic Software Delivery, product lines are a high-level organizer for download files. In the End-User Portal, download files are grouped by producer, then product line, and then download package.
- For producers who use FlexNet Usage Management, product lines play a functional role in searching for and rendering usage history reports.

See Also

[Mapping a Product to a Product Line](#)
[Linking Product Lines to User Accounts](#)
[Configuring System Settings](#)

Enabling Product Lines

For most producers, product lines are optional. They must be enabled in the Producer Portal via the FlexNet Operations system configuration settings. There are two configuration settings that can be used. The one you choose depends on how your account uses product lines.

1. Product lines are available for use as product groups without restricting the visibility of products to different users or accounts. (This product line functionality is enabled by default.)
2. Product lines are available for use as product groups and also restrict visibility of products to different users and accounts.

Enabling Product Lines for Products

The default product line functionality can be enabled via the system configuration setting, **Enable Product Lines for Products**.



Task **To enable product lines for products**

1. Click **System > Configure**.
2. Click **FlexNet Operations** to open the configuration page for FlexNet Operations-specific settings.
3. Locate the **Enable Product Lines for Products** setting and select its check box.



Note - This setting is only effective if the check box for **Enable Product Lines for Products, Users, and Accounts** is not selected.

4. Click **Save Configs** to save changes.

Enabling Product Lines for Products and Visibility Restrictions

The addition of visibility restrictions to product line functionality can be enabled via the system configuration setting, **Enable Product Lines for Products, Users, and Accounts**.

Enabling this configuration setting restricts the visibility of products to the logged-in user. The logged-in user can only view the products and entitlements that use the product lines that the logged-in user created.



Task *To enable product lines for products and restrict visibility*

1. Click **System > Configure**.
2. Click **FlexNet Operations** to open the configuration page for FlexNet Operations-specific settings.
3. Locate the **Enable Product Lines for Products** setting and unselect its check box.
4. Locate the **Enable Product Lines for Products, Users, and Accounts** setting and select its check box.
5. Click **Save Configs** to save changes.

You define access rights by mapping products to product lines and then product lines to producer accounts or to customer users.

Two special product lines are automatically defined by FlexNet Operations:

- **All**—Applied to all customer users by default, this product line includes all products. When implementing product lines, FlexNet Operations includes All as the default to preserve product access for backward compatibility. Later, this product line can be removed and appropriate product lines linked to implement selective product line access for customer users.
- **Uncategorized**—Collects the set of products that have not been mapped to a product line. FlexNet Operations treats Uncategorized as a separate product line. Customer user accounts that have not been linked to the Uncategorized line cannot see uncategorized products.

Product lines can be the object of searches. In addition, product lines can include descriptive attributes that can be used to characterize them.

Enabling “Skip Confirmation” for Product Lines

Depending on configuration settings, producers can reduce the number of copies of a license for certain product lines without requiring a confirmation capability request. This ability is only available if the system configuration setting **Skip Confirmation for Product Line** (under **System > Configure > Embedded Devices > License Generation**) is selected.

If the setting **Skip Confirmation for Product Line** is selected, producers can select the product lines for which no confirmation capability request is required on the **Package Products | Product Lines** page (available under **Products > Product Lines**) in the **Skip Confirmation** column.



Important - The **Skip Confirmation** column is displayed regardless of whether the **Skip Confirmation for Product Line** is selected or unselected.

Adding Product Lines and Product Line Attributes

You can add product lines in the Producer Portal and add product line attributes to those product lines.



Task

To add a product line

1. In the Producer Portal, click **Products > Product Lines**. This link opens the **Package Products | Product Lines** page.
2. Click **Add Product Line**. This button opens the **Create Product Line** page.
3. On the **Create Product Line** page, in **Name**, enter the name of the product line.
4. In **Description**, enter an optional product line description.
5. Click **Save**.

Product lines can have product attributes. A product line's product attributes can be added or deleted on the **Create Product Line** page. (Recall, though, that FlexNet Operations limits alterations to a product line and its attributes after the product line is linked to a product.)



Task

To add a product attribute to a product line

1. On the **Create Product Line** page, click **Add Product Attribute**. This button opens the **Create Product Line Attribute** page.
2. On the **Create Product Line Attribute** page, in **Name**, enter the name of the attribute.
3. Indicate whether the attribute is required for the product line.
4. In **Type**, select the attribute type, then specify any additional details as needed.
 - **Boolean**: A pair of options for mutually exclusive choices, such as **Yes** or **No**.
 - **Long Text**: A text value that can be up to 16384 characters. The value can be typed or pasted into the text box. (The **Display Type** setting controls how a long text value is displayed: Text Area or Text Field.)
 - **Text**: An alphanumeric string. Specify Max Length (a number of characters), Text Type (Single Select, Free Form, or Multi Valued Text), and Display Type (Text Area or Text Field).
 - **Date**: A calendar date.
 - **Number**: A numeral, for example, **33452**. (Value must be an integer.)
5. Click **Save**.

Deleting Product Lines or Product Line Attributes

Product lines that have not yet been mapped to a product can be deleted. Likewise, product line attributes can be added to or deleted from a product line provided that product line has not yet been mapped to a product. After a product line is mapped to a product, it cannot be deleted, and alterations to its product line attributes are highly restricted—only the addition of optional attributes is permitted.



Task *To delete a product line*

1. In the Producer Portal, click **Products > Product Lines**. This link opens the **Package Products | Product Lines** page.
2. Select a product line, and click **Delete**.
3. Click **OK** to confirm the deletion.



Task *To delete a product line attribute from a product line*

1. On the **Create Product Line** page, select the attributes you want to remove, and click **Delete**.
2. Click **OK** to confirm the deletion.

Working with Updates



Version - *The Updates functionality is only available for producers who use the Software Delivery module.*

This section explains what Updates are and how they are implemented for products. The following topics are included:

Table 2-23 -

Topic	Description
About Updates	Discusses what Updates are and how they are used in FlexNet Operations.
Updates and Security	Provides basic information about ensuring that update information has not been tampered with.
Viewing Updates	Provides basic information about viewing and modifying existing Updates.
Creating or Modifying an Update	Provides detailed information about creating and modifying Updates.

About Updates

The Updates functionality enables producers to manage targeted product releases for their customer accounts.

With this functionality, producers are able to provide:

- security patches to keep devices up to date and reduce security risk,
- in-product updates to applications (2018 R2 and later versions),

- entitlement-driven updates to help prevent revenue loss by ensuring only those with valid entitlements get updates. (Entitlement checks can be disabled to deliver vital security patches.)

End users can keep up to date with automated security patches without having to manually download them from a portal, reducing security exposure. They will have access to updates on a per-platform basis, including custom platforms defined by the producer.

Updates are requested and delivered using a set of provided REST APIs.

For detailed information about the Updates functionality delivered by the Updates and Insights module, see [Getting Started with Updates and Insights](#).

See Also

[Updates and Security](#)
[Viewing Updates](#)
[Creating or Modifying an Update](#)
[Update Overview](#)
[Update Release From](#)
[Update Release To](#)
[Update Languages](#)

Updates and Security

It is important for devices to be able to verify that any information about updates has not been tampered with. In this way devices can ensure that they only use legitimate download files provided by their software supplier.

To enable verification that information is legitimate, responses sent by FlexNet Operations can be signed using a `/signed-updates/` REST API. The account owning the devices to be updated requires a public key to validate the signature. This public key can be displayed on the **Create an Account** page, after an account has been created. For more information about how to display the public key, see [Editing an Account or Sub-Account](#).

For detailed information about the security aspect when delivering Updates, see [Getting Started with Updates and Insights](#).

See Also

[About Updates](#)
[Editing an Account or Sub-Account](#)

Viewing Updates

A list of Updates can be viewed on the Updates page.




Task *To open the Updates page*

1. Click **Products > Updates**. The **Updates** page opens.
2. On the Updates page you can filter the list by active and inactive. See [To filter, search and sort the Update list](#) for more information. The list contains the following:

Column	Description
Update Name	The name of the Update. This is the internal name the publisher site uses to identify the Update but it is not shown to those who receive the Update. Click the name for detailed information about the Update.
Update ID	The alphanumeric identification of the Update.
Last Modified	Date/time stamp when the Update was last modified. By default, Updates are listed in descending order by the Last Modified date.



Task *To filter, search and sort the Update list*

1. On the **Updates** page hover, the cursor over the  filter icon to display the filter selection list. By default, the **Updates** page is set to display only updates with an Active status.
2. You can also search a filtered update list. Use the drop-down list to narrow your search to either **Update ID** or **Update Name**.
3. You can sort the list by **Update name**, **Update ID**, **Start date**, **End date** or **Last Modified**.

See Also

- [About Updates](#)
- [Updates and Security](#)
- [Creating or Modifying an Update](#)
- [Update Overview](#)
- [Update Release From](#)
- [Update Release To](#)
- [Update Languages](#)

Creating or Modifying an Update

This section explains how to create and modify Updates. The following topics are included.

Table 2-24 •

Topic	Description
Update Overview	Covers the primary details of an Update.

Table 2-24 -

Topic	Description
Update Release From	Lists the Release From download packages for a given update and covers how to add and remove associated download packages for the given Update.
Update Release To	Lists the Release To download package for a given update and covers how to add and remove an associated download package for the given Update.
Update Languages	Lists the Languages for a given update and covers how to add and remove languages for the given Update.



Task *To create an update*

1. Click **Products > Updates**. This link opens the Updates page.
2. Click **Create**. The Overview tab of the **Update** page opens. See [Update Overview](#) for more details on creating an Update.



Task *To modify an existing Update*

On the **Updates** page, click on the **Update name** of the update you want to modify. The **Update** page is displayed. See [Update Overview](#) for more details on modifying an Update.

See Also

- [About Updates](#)
- [Updates and Security](#)
- [Viewing Updates](#)
- [Update Overview](#)
- [Update Release From](#)
- [Update Release To](#)
- [Update Languages](#)

Update Overview



Task *To create or update the information in the Overview tab*

1. Select a status of **Active** or **Inactive** from the drop-down box. If Inactive is selected, the update is ignored when the client calls in.
2. Enter a name for the Update (required).
3. Enter an ID for the Update (required).
4. Enter or select a date when the Update will be available. If left blank, the Update will be available immediately.

5. Enter or select a date when the Update expires and the client will no longer be able to receive it when calling in.
6. Select the type of type of entitlement check to be performed:
 - **Account** (selected by default)—All devices owned by an account with an entitlement for the product associated with the Release To download package can get this Update.
 - **Device**—Devices which have been mapped to an entitlement for the product associated with the Release To download package can get this Update.
 - **None**—All devices can get the Update whether they are entitled to it or not. (This may be a suitable selection for an Update which deploys a security patch.)



Note ▪ If only anonymous devices are licensed (that is, devices which are not associated with an account), you can only create updates with the **Entitlement check** option set to **None**.

Served devices will only receive updates whose **Entitlement check** option is set to **Account** or **None**.

7. Click **Save**.



Note ▪ When you create a new Update, you must add information to all four tabs before you click the **Save** button.

See Also

[About Updates](#)
[Updates and Security](#)
[Viewing Updates](#)
[Creating or Modifying an Update](#)
[Update Release From](#)
[Update Release To](#)
[Update Languages](#)

Update Release From

The Release From defines the download packages that an Update is for. Release From can have one to many download packages.



Task To list Release From download packages

1. Select the **Release From** tab of the Update. A grid with the associated download package or packages appears. The grid includes the **Download package name**, **Download package ID**, **Description**, **State** and a Delete column. To remove a download package, click the X in the last column. You can search for download packages by **Name**.
2. You can sort the list by **Download package name** or **Download package ID**.



Task **To add a Release From download package**

1. Click the **Add** button. A **Release From** modal window appears. You can search for download packages by **Name**.
2. Use the check box to select the download package or packages to add. You can add download packages from multiple pages in the same session.
3. Click **Save** in the modal window.
4. Click **Save** in the Update page.



Note - When you create a new Update, you must add information to all four tabs before you click the **Save** button.

See Also

- [About Updates](#)
- [Updates and Security](#)
- [Viewing Updates](#)
- [Creating or Modifying an Update](#)
- [Update Overview](#)
- [Update Release To](#)
- [Update Languages](#)

Update Release To

Release To defines the download package that will be delivered for the Update. Only one Release To download package is allowed per platform.



Task **To list Release To download packages**

1. Select the **Release To** tab of the Update. A grid with the associated download package or packages appears. The grid includes the **Download package name**, **Download package ID**, **Description**, **Platform**, **State** and a Delete column. To remove a download package, click the X in the last column. You can search for download packages by **Name**.
2. You can sort the list by **Download package name** or **Download package ID**.



Task **To add a Release To download package**

1. Click the **Add** button. A Release To modal window appears. You can search for download packages by **Name**.
2. Select a Platform from the drop-down list. Custom platforms can be added from the FlexNet Operations system configuration. See the [Updates](#) section for more information.
3. Use the check box to select the download package.
4. Repeat with additional platforms as needed.

5. Click **Save** in the modal window.
6. Click **Save** in the Update page.



Note - When you create a new Update, you must add information to all four tabs before you click the **Save** button.

See Also

- [About Updates](#)
- [Updates and Security](#)
- [Viewing Updates](#)
- [Creating or Modifying an Update](#)
- [Update Overview](#)
- [Update Release From](#)
- [Update Languages](#)

Update Languages

Defines the language or languages for the Update.



Task To list Update language(s)

1. Click on the **Languages** tab of the **Update** page. A grid with the associated language or languages appears. The grid includes the **Language** name, **Title**, **Description** and a **Delete** column. To remove a language, click the **X** in the last column. You can search for languages by **Title** or **Description**.



Note - At least one language must be defined. If the Update is saved without defining a language, an error message appears asking you to add at least one language.

2. You can sort the list by **Language** or **Title**.



Task To add a language to an Update

1. Click the **Add** button. A **Language** modal window appears.
2. From the drop-down box, select a language.
3. Enter a title for the Update that is sent to the client.
4. Enter a description for the Update that is sent to the client.
5. Click the **Save** button in the modal window.
6. Click the **Save** button in the **Update** page.



Note - When you create a new Update, you must add information to all four tabs before you click the **Save** button.

See Also

- [About Updates](#)
- [Updates and Security](#)
- [Viewing Updates](#)
- [Creating or Modifying an Update](#)
- [Update Overview](#)
- [Update Release From](#)
- [Update Release To](#)

Managing Download Packages

Producers who use FlexNet Operations for electronic software delivery can create download packages on the Producer Portal and associate those download packages with products and download files.

FlexNet Electronic Software Delivery also supports the distribution of containerized applications (Docker images and Helm charts). Like file-based installers, containerized applications are distributed using download packages. However, they are stored in a separate registry (either hosted by Revenera or hosted by the software producer). For more information, see [Managing Containerized Applications](#).



Important - For the instructions in this section, it is expected that you are working on the Producer Portal with sufficient permissions to perform the tasks described.

Table 2-25 ▪

Topic	Description
About Download Packages	Describes what download packages are and how they are used by producers. <ul style="list-style-type: none">• About Download Package Attributes• About Download Package Restrictions• About Physical Distribution and Order Media Requests• About Export Compliance
Creating a Download Package	Explains how to add a download package.
Searching for a Download Package	Describes how to search for a download package using download package attributes.

Table 2-25 -

Topic	Description
Viewing Download Package Information	<p>Explains how to view a download package, see where it is used, its restrictions, its email notifications, its transactions, and its short-code transactions.</p> <ul style="list-style-type: none"> Viewing this Download Package Viewing Where a Download Package Is Used Viewing Download Package Restrictions Viewing Emails Related to a Download Package Viewing Download Package Transactions Viewing Download Packages of a Product
Editing Download Package Information	<p>Covers the options presented in the Edit menu on the View Download Package page.</p> <ul style="list-style-type: none"> Editing a Download Package Editing a Download Package File List Reidentifying a Download Package Restricting a Download Package Creating an Email Notification for a Download Package
Copying Download Packages	<p>Covers copying a download package with its files or without its files.</p> <ul style="list-style-type: none"> Copying a Download Package with Files Copying a Download Package without Files
Managing Download Package Associations	<p>Covers the management of download package associations with products and files.</p> <ul style="list-style-type: none"> About Download Package Associations Associating a Download Package to a Product Disassociating a Download Package from a Product Associating a Download Package to Files Disassociating a Download Package from Files

See Also


[Managing Download Files](#)

[About Download Management and FlexNet Electronic Software Delivery](#)

About Download Packages

Download packages are groups of files that can be related to one or more products and tied to a producer and a product line. Optionally, a download package can be associated with a license agreement as well. The figure below depicts the relationships among download packages, download files, and products.

Download Packages



It is through a download package's relationship to products that FlexNet Operations determines which download packages an end user is entitled to.

On the End-User Portal, download packages are grouped by producer and product line so that entitled users can navigate hierarchically through the producer, product line, product, and version to find the downloads they require. And when optional license agreements are associated with a download package, the End-User Portal shows the agreement before allowing end users to download files.

Download packages are also where producers specify export compliance settings that define how download delivery is controlled internationally.

Table 2-26 •

Topic	Description
About Download Package Attributes	Describes the attributes of download packages. These attributes apply to download package searches and to download package creation and editing.
About Download Package Restrictions	Discusses the optional restriction of end user access to download packages.
About Physical Distribution and Order Media Requests	Describes how to use download package attributes and End-User Portal configuration settings to support requests for download files on physical media in the End-User Portal.
About Export Compliance	Discusses export compliance concepts. Export compliance prevents the delivery of files to residents of certain countries, in keeping with U.S. restrictions on the sale of regulated technologies to these countries. The user-configurable export compliance settings are managed at the download package level.

See Also

[Managing Download Files](#)
[About Download Management and FlexNet Electronic Software Delivery](#)
[Managing Download Packages](#)

About Download Package Attributes

Download package attributes describe the download package, express its availability dates, specify its export compliance settings, and so forth.

Table 2-27 -

Attribute	Description
Download Package ID	<p>A unique ID used to associate the download package with products and files.</p> <p>If the download package is to support containerized applications, the download package ID must fulfill the following requirements:</p> <ul style="list-style-type: none"> • Allowed characters: letters, numbers, and the special characters dot (.), underscore (_), and minus (-). • Any letters must be lower case • Start with a letter or number • Maximum 100 characters
Download Package Name	<p>The name of the download package to be displayed to users in the End-User Portal. It should be brief but descriptive, for example, Enterprise Server 2.4 Solaris or Enterprise Server 2.4 Documentation.</p>
Extended Description	<p>An optional, additional description attribute for the download package. Maximum: 1000 characters.</p>
Container Delivery	<p>Specifies whether the download package supports the distribution of containerized applications, such as Docker images and Helm charts.</p> <ul style="list-style-type: none"> • Yes—Download package supports the distribution of containerized applications as well as file-based installers. • No—Download package supports only file-based installers. <p>See Managing Containerized Applications for more information.</p>
Version	<p>The version of the download package.</p>
Release Group	<p>An optional attribute to help sort the download package's appearance in the End-User Portal. Maximum: 20 characters.</p>
Effective Date	<p>The date when the download package becomes available on the End-User Portal. Accounts have access to the download package if the download package's effective date occurs within their entitlement's effective and expiration dates on the line item for that download package.</p>

Table 2-27 -

Attribute	Description
Expiration Date	<p>The date when the download package moves to the archive (Previous Versions) tab or becomes inaccessible from entitlement lines with start dates later than this expiration date.</p> <p>If the expiration date is in the future, the download package appears on the new versions section of the End-User Portal. If the expiration date is in the past, the download package moves to the release archives section. Accounts have access to the download package from the release archives section even if the download package is expired, provided there is an overlap between the download package's effective and expiration dates and the entitlement's effective and expiration dates.</p>
Archive Date	<p>The date on which the download package moves to the archive (Previous Versions) tab. Users may still download it if they have access through an overlap with their entitlement dates, but must find it on the archive tab on the End-User Portal. (New entitlements with beginning dates after the expiration date will not have access to this product at all.)</p>
Download Package Producer	<p>The producer of the product and the download package. (See Managing Producers.)</p>
Product Line	<p>The product line in which the download package appears.</p>
End User License Agreement	<p>An optional, click-through license agreement. (See Managing License Agreements.)</p>
Physical Distribution Available	<p>Specifies whether users on the End-User Portal have the option to request a copy of the download package on physical media. FlexNet Operations offers customizations to integrate with a physical distribution facility. When your site is integrated, this attribute shows whether or not end users have the option to request a physical copy of the download package. (See About Physical Distribution and Order Media Requests.)</p> <p>This option is not supported for containerized applications.</p>
Restrict to US/Canada	<p>Specifies whether to restrict delivery to users in the United States or Canada or to permit delivery outside those countries.</p> <p>Yes—Restricts delivery to users within the United States or Canada.</p> <p>No—Permits delivery to users outside the United States and Canada.</p> <p>If you choose No, ECCN, ENC, and CCATS attributes are required. Otherwise, they are not used. See About Export Compliance for more information.</p>
ECCN, ENC, CCATS	<p>See About Export Compliance.</p>

Table 2-27 •

Attribute	Description
Download Instructions	Directions to End-User Portal users. Download instructions can be plain text or HTML content and are shown to users along with the list of files in the download package. For example, Please refer to the release notes for installation instructions.



Note • A download package's editable attributes may also include the values for any custom download package attributes you have defined. To learn more about custom attributes, including custom download package attributes, see [Administering Custom Attributes](#).

Many attributes support localization. For localizable attributes, click **Show Languages** to reveal additional, locale-specific fields for those attributes.

See Also

- [Creating a Download Package](#)
- [Editing Download Package Information](#)
- [About Download Packages](#)

About Download Package Restrictions

Producers can set up download package restrictions to either permit or deny End-User Portal access to the download package. These restrictions can be specified for specific accounts or based on geographical information—country and/or region—of accounts.

Download package restrictions based on specific accounts can be useful in situations where a producer is delivering a beta release only to accounts who are participating in the beta test process or selectively make a hotfix available only to designated accounts.

Restrictions based on geographical information helps producers to ensure that software approved for a specific region can be downloaded only by users in that region. When restrictions are in place, the End-User Portal lists only download packages that the user is entitled to.

By default, a download package is unrestricted. If no restrictions are created for a download package, it is accessible to all entitled accounts and in all geographic areas.

The following sections provide information about how the restriction process works:

- [Restrictions for Specific Accounts](#)
- [Restrictions Based on Geographical Location](#)



Important • Export Compliance restrictions override any restrictions specified on the **Restrict Download Package** page.

Account-level restrictions and geographic restrictions have the same precedence. If restrictions set up for a specific account conflict with the restrictions based on geographical location, access to the download package is denied.

Restrictions for Specific Accounts

Accounts can be added to the **Account(s) Restricted to Download Package** list on the **Restrict Download Package** page one at a time. The process starts with a search for the account to permit or deny access by its account ID or its account name. Search results are shown on the **Find an Account** page in a pop-up window. When you choose to restrict a previously unrestricted download package, the **Find an Account** page provides the option of specifically permitting (**Restrict Allow**) or denying (**Restrict Deny**) access to the selected account. From that point on, any other accounts you add to the restrictions list must follow the choice (**Restrict Allow/Restrict Deny**) you made for the first account.

- **Restrict Allow**—Creates a file access “allow list” that stipulates the accounts that are permitted to access the download package. Any account not on the list is not permitted to access the package in the End-User Portal, even if they are otherwise entitled to the product.
- **Restrict Deny**—Creates a files access “block list” that stipulates the accounts that are not permitted to access the download package. None of the accounts on the list are permitted to access the package in the End-User Portal, even if they are otherwise entitled to the product.

Multiple accounts can be removed from the restrictions list on the **Restrict Download Package** page by selecting their check boxes in the **Remove this Account** column and then clicking **Remove Selected Accounts**.

For more information about restricting files, see [Restricting a Download Package](#). You can find step-by-step instructions in the subsection [Restricting Access Based on Account](#).

Restrictions Based on Geographical Location

Access to a download package can be restricted to accounts whose end-users are in a specific country and, optionally, a region in that country, as specified in the account’s geographical information.

When you add countries and regions to the **Restrict Access to Selected Countries** list on the **Restrict Download Package** page, you create an “allow list” which stipulates that only accounts from that country and region are permitted to access the download package. As a prerequisite, geographical information must be specified for accounts that are to be placed on such an “allow list”. You provide this information on an account’s **Create An Account** page, in the **Country** and **Region** fields. For more information, see [Creating a New Account](#).

Important Notes

- End-users belonging to an account with geographical information that is different to the country or region specified in the “allow list” are not permitted to access the package in the End-User Portal, even if they are otherwise entitled to the product.
- The names of any regions that you enter on the **Add Country** page in the **Region** field must match the spelling of the region names that are specified in the **Region** field of the customer accounts.
- Specifying a region is optional. If the **Restrict Access to Selected Countries** list contains only a country (without specifying a region), access is given to users associated with accounts that match the country, regardless of whether a region is specified in the account.
- If the **Restrict Access to Selected Countries** list contains a country and a region, only users associated with accounts that match the country AND the region are allowed to access the download package.
- The **Restrict Access to Selected Countries** list can have a maximum of 50 regions for each country.
- If you set up geographical restrictions and sell through channel partners, a channel partner's country and region must be included in a download package's geographical restriction list of countries and regions.

For more information about restricting files, see [Restricting a Download Package](#). You can find step-by-step instructions in the subsection [Restricting Access Based on Geographical Location](#).

See Also

[Restricting a Download Package](#)
[About Download Packages](#)

About Physical Distribution and Order Media Requests

For producers who want their end users to be able to request download files on physical media, the End-User Portal includes an **Order Media** control. Configuring the End-User Portal to handle these requests requires some configuration in the Producer Portal.

Download packages for which orders for physical media are supported must have the **Physical Distribution Available** attribute set to **Yes**.

The system configuration settings allow the End-User Portal to show the **Order Media** control and set a target email address for order media requests. The following settings must be configured on the **End-User Portal Setup** page.

- **Show Order Media Button**—selected
- **Order Media Destination Email Address**—email address to receive order media requests specified



Tip - To show the End-User Portal Setup page in the Producer Portal, click **System > Configure > End-User Portal Setup**.

See Also

[About Download Package Attributes](#)
[Configuring End-User Portal Settings](#)
[Creating a Download Package](#)

About Export Compliance

A download package's export compliance settings are defined on its **Add Download Package** or **Edit Download Package** page. These settings play a role in determining whether or not a collection of files can be delivered to a given End-User Portal user. Download packages that are not restricted to the United States and Canada must have valid ECCN, ENC, and CCATS values to be properly delivered to users in countries outside of the United States and Canada.

- [Export Compliance Requirement](#)
- [Export Compliance Evaluation](#)
- [Export Compliance Codes: ECCN, ENC, and CCATS](#)

Export Compliance Requirement

Deliveries of software outside the United States are subject to the Export Administration Regulations, which are administered by the Department of Commerce Bureau of Industry and Security. In addition to embargoed or terrorist countries, to which no products may be sold or delivered, a number of United States government

agencies maintain lists of individuals and entities to which software sales and delivery are barred. Revenera is prohibited from delivering to parties appearing on these lists, whether we are delivering from or to the United States or from or to another country.

Export Compliance Evaluation

FlexNet Operations distinguishes and acts on the different BIS-approved processes, depending on the product classification of a particular software product.

FlexNet Operations checks the following data elements for any individual who initiates a download using the service:

- User name on denial list
- User email address domain—check for country of origin/government
- User profile address—check for country of origin/government
- Account Name on denial list
- IP address lookup
- Domain from DNS lookup for IP address (only used if the user profile address check fails)

If any of these checks fail, access is denied—the export is not allowed. When a compliance check fails, FlexNet Operations automatically generates and sends an email message to an internal email alias and, optionally, also forwards it directly to a customer-designated email address. Contact Revenera, if necessary, to follow up for information relevant to the denial.

Export Compliance Codes: ECCN, ENC, and CCATS

The chart, below, displays the valid ECCN, ENC, and CCATS code combinations to comply with the Bureau of Industry and Security's (BIS) export rules. In the chart, "#####" indicates that any six digits following D, G, or Z are valid. All characters are upper-case. The Z##### CCATS numbers may also have -P appended to them to indicate that the temporary classification has expired and the final CCATS number is pending.

You can restrict downloads to the US and Canada by setting **Restrict to US/CANADA (NLR)** to **Yes**.

Use “TSR+” for 5D001 products with a TSR license exception, except for those products with "software" controlled by 5D001.a and specially designed for items controlled by 5A001.b.5.

Table 2-28 • Valid code combinations based on BIS compliance taxonomy

Encrypted?	ECCN	ENC	CCATS	Export Rules
Encryption	5D002	Unrestricted (RETAIL)	D##### G##### SELF Z#####-P	Broad export. No embargoed countries or “terrorist-supporting states.”
			Z#####	Limited export. No countries outside U.S., Canada, and EU+8 (EU+8 referred to in BIS regulations as “Supplement 3 Countries”).
		Restricted (NON_RETAIL)	D##### G##### Z#####-P	Limited export. No foreign governments outside the EU+8 (EU+8 referred to in BIS regulations as “Supplement 3 Countries”). No embargoed countries or “terrorist-supporting states.” Special click-through must be accepted by end user.
			Z#####	Limited export. No countries outside U.S., Canada, and EU+8 (EU+8 referred to in BIS regulations as “Supplement 3 Countries”).
		TSU	---	Broad export. No embargoed countries or “terrorist-supporting states.” Available for “publicly available” encryption source code.
		TMP_BETA	---	Broad export. No embargoed countries or “terrorist-supporting states.” Available for beta testing only. Certain terms must be agreed to by beta tester.
		UNKNOWN	---	Limited export. No countries outside U.S. and Canada.
		740.17(a)(1)	---	Provided only for informational purposes. It is the producer's responsibility to ensure that Export Rules are complied with
		740.17(a)(2)	---	
		740.17(b)(2)	---	

Table 2-28 • Valid code combinations based on BIS compliance taxonomy

Encrypted?	ECCN	ENC	CCATS	Export Rules
Encryption (cont.)	5D992	740.17(b)(1)	---	Provided only for informational purposes. It is the producer's responsibility to ensure that Export Rules are complied with
		740.17(b)(3)	---	
		---	--- D##### G##### SELF Z#####-P Z#####	Broad export. No embargoed countries or "terrorist-supporting states." CCATS=SELF available only for encryption that does not exceed 56 bits, or encryption that is limited to password protection or authentication.
No Encryption	EAR99	---	--- SELF	Broad export. No embargoed countries.
	3E201	---	---	No license required. Nuclear Nonproliferation.
	3D002	---	---	Limited export. No countries outside U.S. and Canada.
		TSR	---	Limited export. Group B countries only. Special click-through must be accepted by end user (written assurance).
	3D991	---	---	Broad export. No embargoed countries or "terrorist-supporting states."
	3E991	---	---	
	4D993	---	---	
	4D994	---	---	
	4E992	---	---	
	4E993	---	---	

Table 2-28 • Valid code combinations based on BIS compliance taxonomy

Encrypted?	ECCN	ENC	CCATS	Export Rules
No Encryption (cont.)	5D001	---	---	Limited export. No countries outside U.S. and Canada.
		TSR	---	Limited export. Subset of Group B countries only. Special click-through must be accepted by end user (written assurance).
		TSR+	---	Limited export. Group B countries only. Special click-through must be accepted by end user (written assurance).
	5D991	---	---	Broad export. No embargoed countries or “terrorist-supporting states.”
	5E991	---	---	
	5E992	---	---	
Unknown	NO_EXPORT	UNKNOWN	---	No export. U.S. only.
	UNKNOWN	UNKNOWN	---	No export. U.S. only.

See Also

[Creating a Download Package](#)
[About Download Packages](#)

Creating a Download Package

You can create a download package in the Producer Portal.



Note • Before creating a download package, you must have defined at least one deployed product and a product line. (For instructions about creating products and product lines, see [Creating a Product](#) and [Managing Product Lines](#), respectively.)

A download package contains one or more files for users to download from the End-User Portal. A typical use of download packages is as a container for the files that comprise, say, the installer, documentation, and release notes for a particular software release, but your account can group files together in any way that makes sense for its product offerings. Download packages must exist before they can be associated to products or have files associated to them.



Task **To create a download package**

1. Click **Products > Create Download Package**. This link opens the **Create Download Package** page.
2. Enter download package attributes.

Attribute	Description
Download Package ID	<p>A unique ID used to associate the download package with products and files.</p> <p>If the download package is to support containerized applications, the download package ID must fulfill the following requirements:</p> <ul style="list-style-type: none">● Allowed characters: letters, numbers, and the special characters dot (.), underscore (_), and minus (-).● Any letters must be lower case● Start with a letter or number● Maximum 100 characters
Download Package Name	<p>The name of the download package to be displayed to users in the End-User Portal.</p>
Extended Description	<p>An optional, additional description attribute for the download package. Maximum: 1000 characters.</p>
Container Delivery	<p>Specifies whether the download package supports the distribution of containerized applications, such as Docker images and Helm charts.</p> <ul style="list-style-type: none">● Yes—Download package supports the distribution of containerized applications as well as file-based installers.● No—Download package supports only file-based installers. <p>See Managing Containerized Applications for more information.</p>
Version	<p>The version of the download package.</p>
Release Group	<p>An optional attribute to help sort the download package's appearance in the End-User Portal. Maximum: 20 characters.</p>
Effective Date	<p>The date when the download package becomes available on the End-User Portal. Accounts have access to the download package if the download package's effective date occurs within their entitlement's effective and expiration dates on the line item for that download package.</p>

Attribute	Description
Expiration Date	<p>The date when the download package moves to the archive (Previous Versions) tab or becomes inaccessible from entitlement lines with start dates later than this expiration date.</p> <p>If the expiration date is in the future, the download package appears on the new versions section of the End-User Portal. If the expiration date is in the past, the download package moves to the release archives section. Accounts have access to the download package from the release archives section even if the download package is expired, provided there is an overlap between the download package's effective and expiration dates and the entitlement's effective and expiration dates.</p>
Archive Date	<p>The date on which the download package moves to the archive (Previous Versions) tab. Users may still download it if they have access through an overlap with their entitlement dates, but must find it on the archive tab on the End-User Portal. (New entitlements with beginning dates after the expiration date do not have access to this product at all.)</p>
Download Package Producer	<p>The producer of the product and the download package. (See Managing Producers.)</p>
Product Line	<p>The product line in which the download package appears.</p>
End User License Agreement	<p>An optional, click-through license agreement. (See Managing License Agreements.)</p>
Physical Distribution Available	<p>Specifies whether users on the End-User Portal have the option to request a copy of the download package on physical media. FlexNet Operations offers customizations to integrate with a physical distribution facility. When your site is integrated, this attribute shows whether or not end users have the option to request a physical copy of the download package.</p> <p>This option is not supported for containerized applications.</p>
Restrict to US/Canada	<p>Specifies whether to restrict delivery to users in the United States or Canada or to permit delivery outside those countries.</p> <p>Yes—Restricts delivery to users within the United States or Canada.</p> <p>No—Permits delivery to users outside the United States and Canada.</p> <p>If you choose No, ECCN, ENC, and CCATS attributes are required. Otherwise, they are not used. See About Export Compliance for more information.</p>

- Optionally, add **Download Instructions**. Download instructions are directions for End-User Portal users that can be entered as plain text or as HTML content. These instructions are shown to users along with the list of files in the download package. For example, "Please refer to the release notes for installation requirements."
- Complete or continue the download package creation process:

- Click **Save Download Package** to save with current settings. The Producer Portal shows the download package's **View Download Package** page.
- Click **Save & Add Another** to save the current download package and begin creating another download package.
- Click **Save & Add File** to save the current download package and upload a file image for it.
- Click **Save & Associate File** to save the current download package and associate it with a file.
- Click **Save & Copy to Product** to save the current download package and associate it with a product.

See Also

[Associating a Download Package to a Product](#)
[Associating a Download Package to Files](#)
[About Download Packages](#)

Searching for a Download Package

Existing download packages can often be most easily located by performing a quick search based on some attribute of the download package you want to see.



Tip ▪ To return a list of all download packages, leave the search criteria blank and click **Search**. Empty searches match all download packages.



Task

To search for a download package

1. Click **Products > Search Download Packages**. The **Search Download Packages** page opens.
2. Enter your download package search criteria and click **Search**. The Producer Portal shows a list of the download packages that match your search criteria on the **Search Results: Download Packages** page.

From the **Search Results: Download Packages** page, you can click:

- **Search Again** to run another download package search
- **Mass Update** to edit the download packages listed on the **Search Results: Download Packages** page
- **Export** to export a set of download packages as a Data Import Template file (see [Importing and Exporting Entities](#))

See [About Download Package Attributes](#) for more information about attributes available in the search criteria.

3. Click the **Download Package ID** for the download package you want to view.

The Producer Portal shows the **View Download Package** page for the download package you selected.

On the **View Download Package** page, you can perform any of the download package management activities—such as associating the download package to a product or to one or more files—that are permitted by your user account permissions.

See Also

- [Editing Download Package Information](#)
- [Copying Download Packages](#)
- [Managing Download Package Associations](#)
- [About Download Packages](#)
- [Importing and Exporting Entities](#)

Viewing Download Package Information

Users typically search for a download package they want to view and then click that download package’s name to open the **View Download Package** page. The **View** menu on the **View Download Package** page includes several commands to get more details about the download package, where it is used, how it has been managed, who it has been delivered to, and so on. With the commands in the View menu, you can perform the following tasks.

In addition, users can access the download packages associated with a product from the **Create A Product** page

Table 2-29 -

Topic	Description
Viewing this Download Package	Explains how to return to the basic View Download Package page when performing other download package-related operations.
Viewing Where a Download Package Is Used	Shows how to determine which products a download package is associated with.
Viewing Download Package Restrictions	Describes how to view a list of accounts that are permitted or denied access to a download package. Restricting download package access to designated accounts is optional. By default, download packages are accessible to all entitled accounts.
Viewing Emails Related to a Download Package	Shows how to view email messages sent for a download package.
Viewing Download Package Transactions	Shows how to view transaction history related to a download package.
Viewing Download Packages of a Product	Explains how to access the download packages associated with a specific product from the Create A Product page.

See Also

- [Searching for a Download Package](#)
- [Editing Download Package Information](#)
- [About Download Packages](#)

Viewing this Download Package

When working with download packages, you can return to the basic **View Download Package** page by clicking **View this Download Package**. Download package-related operations might be checking where the download package is used, associating the package to a product, and so forth. On these download package-related pages, **View this Download Package** is a link in the **View** menu.

The Producer Portal also shows the **View Download Package** page when you add a download package.



Task *To return to the basic View Download Package page*

- Click **View** > **View this Download Package**.

See Also

[Viewing Download Package Information](#)
[Editing Download Package Information](#)
[About Download Packages](#)

Viewing Where a Download Package Is Used

You can display a list of the products that use a download package from the download package's **View Download Package** page.



Task *To view where the current download package is used*

- On the **View Download Package** page, click **View** > **View Where Used**.

The Producer Portal opens the **Where Download Package Used** page. This page lists the products with which the download package is associated. Clicking on the name of a product in the **Products** list opens the **View Product** page for that product.

See Also

[Managing Download Package Associations](#)
[Editing Download Package Information](#)
[About Download Packages](#)

Viewing Download Package Restrictions

Describes how to view a list of accounts that are permitted to see a download package in the End-User Portal. Restricting download package access to designated accounts is optional. By default, download packages are accessible to all entitled accounts.



Task *To view download package restrictions*

- On the **View Download Package** page, click **View** > **View Restrictions**.

The Producer Portal opens the **View Download Package Restrictions** page. Depending on how restrictions were defined, this page either lists the accounts that are permitted or denied access the current download package. (Download package restriction lists can be lists of permitted accounts or denied accounts.)

If no accounts appear in the **Download Package Restricted To** list, then the download package is accessible by all accounts.

See Also

[Restricting a Download Package](#)
[About Download Package Restrictions](#)
[About Download Packages](#)

Viewing Emails Related to a Download Package

You can view email messages sent for a download packages from its **View Download Package** page. These messages appear in a list on the **Search Results: Email** page. The email messages are sorted from newest (most recently sent) to oldest.



Task *To view emails related to a download package*

- On the **View Download Package** page, click **View > View Emails**.

The Producer Portal opens the **Search Results: Email** page. Click the System Email ID to show the **View Email** page for that email message.

If no emails have been sent for products to which the current download package is associated, the Producer Portal shows an error message that reports: No email messages found.

See Also

[Managing Download Package Associations](#)
[Viewing Where a Download Package Is Used](#)

Viewing Download Package Transactions

You can view transactions related to a download package from the download package's **View Download Package** page. These transactions appear in a list on the **Search Results: Transactions** page.



Task *To view transactions related to a download package*

- On the **View Download Package** page, click **View > View Transactions**.

The Producer Portal opens the **Search Results: Transactions** page. Transactions are ordered by date with the most recent Transaction first. Click on the System Transaction ID to open its **View Transaction** page.

A transaction is recorded by the Producer Portal as users make changes to the system. Download Package transactions are recorded for changes like adding a download package or associating a download package with a product.

See Also

- [Managing Download Package Associations](#)
- [Creating a Download Package](#)
- [About Download Packages](#)

Viewing Download Packages of a Product

You can view the download packages associated with a specific product from the **Create A Product** page.



Task *To view the download packages of a specific product*

1. In FlexNet Operations go to **Products > Products**.
2. In the **Package Products** page, click on the name of the product.
3. In the **Create A Product** page, click on the **Download Packages** tab. A table of download packages appears.
4. Click on the ID of the download package to open the **View Download Package** page.

See Also

- [Managing Download Package Associations](#)
- [Creating a Download Package](#)
- [About Download Packages](#)

Editing Download Package Information

Users typically search for a download package they want to view and then click that download package's name to open the **View Download Package** page. The **Edit** menu on the **View Download Package** page includes several commands for actions like altering, restricting, or creating an email message for an existing download package. With the commands in the **Edit** menu, you can perform the following tasks.

Table 2-30 -

Topic	Description
Editing a Download Package	Describes how to change a download package's details.
Editing a Download Package File List	Shows how to use Edit File List to modify the sort order of the files associated with a download package and optionally exclude selected files from download limit enforcement.
Reidentifying a Download Package	Discusses how to reidentify a download package to change the download package ID of an existing download package.
Restricting a Download Package	Explains how to restrict access to a download package to designated accounts.

Table 2-30 •

Topic	Description
Creating an Email Notification for a Download Package	Describes how to create an email notification for a download package.

See Also

- [Managing Download Package Associations](#)
- [Searching for a Download Package](#)
- [About Download Packages](#)

Editing a Download Package

You can edit download package details from the **View Download Package** page. Most of the download package information that you enter when you add a download package can be edited on the **Edit Download Package** page.

Some commonly edited download package details include

- **Download Package Description**—The name of the download package that End-User Portal users see. It should be brief but descriptive, for example, **Enterprise Server 2.4 Solaris** or **Enterprise Server 2.4 Documentation**.
- **Download Package Name**—The name of the download package as it will appear in the Producer Portal.
- **Extended Description**—An optional, additional description field that can show more information about the download package to your End-User Portal users. Maximum: 1000 characters.
- **Download Instructions**—Additional information that is displayed above the file list on the download page of the End-User Portal. For example, **Please refer to the release notes for installation instructions**.



Note • A download package's editable attributes may also include the values for any custom download package attributes you have defined. To learn more about custom attributes, including custom download package attributes, see [Administering Custom Attributes](#).

Many attributes support localization. For localizable attributes, click **Show Languages** to reveal additional, locale-specific fields for those attributes.

For more information about download package attributes, see [About Download Package Attributes](#).



Task

To edit download package details

1. On the **View Download Package** page, click **Edit > Edit this Download Package**. This link opens the **Edit Download Package** page for the current download package.
2. Make your changes to one or more download package details.
3. Click **Save**.

The Producer Portal saves your changes and returns to the **View Download Package** page for the current download package.



Tip - Some download package details, such as its Download Package ID, cannot be altered on the **Edit Download Package** page. To change a download package's ID, you must reidentify the download package (**Edit > Reidentify**).

See Also

[Reidentifying a Download Package](#)
[About Download Package Attributes](#)

Editing a Download Package File List

You can edit the file list for a download package from the package's **View Download Package** page.

The **Edit File List** page shows all of the files associated with the current download package and allows you to create and edit the file sort order. On the End-User Portal, the files that are part of this package are sorted in ascending order according to the numeric values you enter here. If no sort order is specified or when more than one file has the same Sort Order number, the files are sorted in the alphabetical order by their file description.

The file sort order only applies to the current download package. Therefore, the same file used in more than one download package may have a different sort order value in different packages.



Task **To edit the file list of a download package**

1. On the **View Download Package** page, click **Edit > Edit File List**. This command opens the **Edit File List** page.
2. In the **Files in this Download Package** list, specify **Sort Order** values for each file.



Tip - The **Edit File List** page also allows you to indicate which, if any, of the files in this download package should ignore download limits inherited from the product. To control whether a file can be downloaded more times than the download limit, in the **Ignore Download Limit** column, select **Yes** or **No**.

3. Click **Save File List**.

The Producer Portal saves the file list with the specified sort order values.

See Also

[Managing Download Package Associations](#)
[About Download Packages](#)

Reidentifying a Download Package

You can change the download package ID of an existing download package from that download package's **View Download Package** page.



Note - You can only reidentify download packages associated with files. Download packages associated with containerized applications cannot be reidentified.



Task *To reidentify a download package*

1. On the **View Download Package** page, click **Edit > Reidentify**. This link opens the **Reidentify Download Package** page.
2. In the **Download Package ID** field, type a new download package ID value.
3. Click **Reidentify**.

The Producer Portal changes the download package ID of the current download package and returns to the download package's **View Download Package** page. Other download package details are preserved, including its associated products and files.

See Also

[Creating a Download Package](#)
[About Download Packages](#)

Restricting a Download Package

You can restrict access to a download package in the Producer Portal. You can set up restrictions to:

- deny or allow access to a download package for one or more specified accounts
- allow access to a download package only for accounts from a specified geographical location (country or region).

Download packages are not restricted by default.



Note - You can only restrict access to download packages associated with files. Access to download packages associated with containerized applications cannot be restricted.



Note - When no accounts are listed on a download package's **Restrict Download Package** page, access to the download package is not restricted. See [About Download Package Restrictions](#) for more information about how the restriction process works.

Restricting Access Based on Account

When you restrict access to a download package, you use a search function to locate and identify the account to which you want to permit or deny download package access. Accounts can be added to the **Account(s) Restricted to Download Package** list one at a time.



Task *To set download package restrictions for specific accounts*

1. On the **View Download Package** page, click **Edit > Restrict**. This link opens the **Restrict Download Package** page.
2. Locate the **Grant Access to Accounts** section (by clicking the **Grant or Deny Access to Accounts** link or scrolling down to the section).

3. Type search criteria and click **Search Accounts**. The Producer Portal opens the **Find an Account** page in a pop-up window. This page shows a list of accounts that match your search criteria.
4. On the **Find an Account** page, click **Restrict Allow** or **Restrict Deny** for an account.
 - If you choose **Restrict Allow**, only the accounts you choose are permitted to access the download package.
 - If you choose **Restrict Deny**, the accounts you choose are expressly denied access to the download package.

The Producer Portal closes the **Find an Account** window and returns to the **Restrict Download Package** page.

The **Restrict Download Package** page shows the account you chose in the **Account(s) Restricted to Download Package** list.

Repeat the steps above for any additional accounts for which you want to restrict access. Any other accounts you add to the restrictions list must follow the choice (**Restrict Allow/Restrict Deny**) you made for the first account.



Tip - To remove an account from the **Accounts Restricted to Package** list, select the account's check box in the **Remove this Account** column and then click **Remove Selected Accounts**.

Restricting Access Based on Geographical Location

Restrictions are based on the country and region specified in the account that the end-user is associated with. You provide geographical information on an account's **Create An Account** page, in the **Country** and **Region** fields. For more information, see [Creating a New Account](#).



Task

To set download package restrictions based on geographical location

1. On the **View Download Package** page, click **Edit > Restrict**. This link opens the **Restrict Download Package** page.
2. Locate the **Restrict Access to Selected Countries** section (by clicking the **Restrict Access to Selected Countries** link or scrolling down to the section).
3. Click **Add**. The Producer Portal opens the **Add Country** page in a pop-up window.
4. On the **Add Country** page, select the countries that should have access to the download package. To add all countries in the list, select the check box next to the **Country** column header.

Optionally, to add regions, click the + sign and type the region name. You can select up to 50 regions per country.



Important - Ensure that the names of any regions that you enter on the **Add Country** page match the spelling of the region names that are specified for the customer accounts.

5. Click **Select** to confirm your selection and close the **Add Country** page.

The **Restrict Download Package** page shows the countries and regions (if specified) you chose in the **Restrict Access to Selected Countries** list.



Tip - To remove a county or region from the **Restrict Access to Selected Countries** list, click the **Delete** icon for the country or region.

See Also

- [Restricting a Download Package](#)
- [Viewing Download Package Restrictions](#)
- [About Download Packages](#)

Creating an Email Notification for a Download Package

You can create an email notification for the download packages from the **View Download Package** page.



Tip - To successfully send an email notification for a download package, the default variation of the Update Notification Email template must be active and permitted to send messages (**Will Email Be Sent** set to **Yes**).



Task *To create a notification email for a download package*

1. On the **View Download Package** page, click **Edit > Notify**. This link opens the **Create Notification Email by Download Package** page.
2. Set Distribution List Options for the email message.

Setting	Description
Effective Date	The first date (inclusive) that this entitlement is available to the end user.
Include Expired Entitlements	Determines whether or not to include expired entitlements in the distribution list. By default, only users with active entitlements are included in the distribution list.
Exclude Email Filters	Allows you to identify specific email addresses or email address ranges to exclude from the distribution list. For a single address, type the address in the space provided. For multiple addresses, add a comma-separated list of email addresses in the space provided. Use an asterisk as a wildcard to exclude ranges of email addresses. For example, *@somedomain.com, *.edu .
Limit to Countries	<p>Restricts the delivery of notifications to countries identified by their two-character country code. Use a comma-separated list of country codes to permit delivery to multiple countries. For example, specifying US,FR permits notification delivery to users in the United States and France.</p> <p>When no country codes are specified, FlexNet Operations places no notification delivery restrictions based on the recipient's country.</p>

Setting	Description
Send Separate Email for Each Download Package	Determines whether to send a single message for all download packages (when multiple download packages have been selected) or to send a separate message for each download package.
Send Email Immediately	Determines whether the message is sent as soon as it is created or sent later. If you select this check box, the Producer Portal sends the message as soon as you click Create on this page. Do not use this option if you want to modify the message before it is sent.

3. **Choose an Email Template** variation for this message.

Download Package notification messages use the Update Notification Email template. Select any active variation of that template for the download package notification.



Tip - You can manage your email templates in the Producer Portal. For more information about email templates, see [Managing Email Templates](#).

4. Click **Create**. The Producer Portal creates the email message for the download packages you specified, using the settings you provided, and shows the **View Email** page.
5. On the **View Email** page, click **Edit > Send Email**. The Producer Portal opens the **Send Email** page.
6. On the **Send Email** page, choose to send the email or schedule its delivery.
 - To send immediately, click **Send**.
 - To schedule delivery for a later date,
 1. Click **Queue to be sent at**.
 2. Set the Send Date.
 3. Specify the Send Time (24-hour format).
 4. Click **Send**.

The Producer Portal sends the email notification.



Note - For more information about managing email messages and email templates, see [Managing Email and Email Templates](#).

See Also

- [Viewing Emails Related to a Download Package](#)
- [Creating an Email Notification for a File About Download Packages](#)

Copying Download Packages

You can create a copy of an existing download package using the controls on its **View Download Package** page.



Tip - Often, the quickest way to create a new download page for a product update or service pack, for example, is to start with a copy of the original product's download package.

Table 2-31 -

Topic	Description
Copying a Download Package with Files	Describes how to create a copy of a download package that includes the files currently associated with that download package.
Copying a Download Package without Files	Describes how to create a copy of a download package that excludes the files associated with the original download package.

See Also

- [Creating a Download Package](#)
- [Searching for a Download Package](#)
- [About Download Packages](#)

Copying a Download Package with Files

Use the following instructions to create a copy of a download package that includes the file associations in the original download package.



Note - You can only copy download packages associated with files. Download packages associated with containerized applications cannot be copied.



Task

To copy a download package

1. On the **View Download Package** page, click **Copy > Copy with Files**. The Producer Portal shows the **Add Download Package** page with product detail values that match those of the original download package.
2. On the **Add Product** page, make your changes to the product details. (See [Creating a Download Package](#) for information about the product detail fields or download instructions.)
3. Edit the download instructions, as necessary.
4. Click **Save Download Package**.

The Producer Portal creates the new download package and shows its **View Download Package** page.

See Also

- [Copying a Download Package without Files](#)
- [Creating a Download Package](#)

Copying a Download Package without Files

Use the following instructions to create a copy of a download package that excludes the file associations in the original download package.



Task *To copy a download package*

1. On the **View Download Package** page, click **Copy > Copy without Files**. The Producer Portal shows the **Add Download Package** page with product detail values that match those of the original download package.
2. On the **Add Product** page, make your changes to the product details. (See [Creating a Download Package](#) for information about the product detail fields or download instructions.)
3. Edit the download instructions, as necessary.
4. Click **Save Download Package**.

The Producer Portal creates the new download package and shows its **View Download Package** page.

See Also

[Copying a Download Package with Files](#)
[Creating a Download Package](#)

Managing Download Package Associations

The download packages you add to the Producer Portal can be associated with one or more existing products and to one or more files from the package's **View Download Package** page.

Users typically search for a download package they want to view and then click that download package's name in the search results to open the **View Download Package** page. The **Associate** menu on the **View Download Package** page includes commands for adding and removing both product and file associations. With the commands in the Associate menu, you can perform the following tasks.

Table 2-32 -

Topic	Description
About Download Package Associations	Discusses the relationships you can create between files, download packages, and products.
Associating a Download Package to a Product	Explains how to set up relationships between download packages and products. Two commands in the Associate menu facilitate making download package-product associations: <ul style="list-style-type: none">● Associate to Products● Associate Where
Disassociating a Download Package from a Product	Explains how to remove a previously built relationship between a download package and one or more products.

Table 2-32 •

Topic	Description
Associating a Download Package to Files	Explains how to build relationships between files and the download package.
Disassociating a Download Package from Files	Explains how to remove a previously built relationship between a download package and one or more files.

See Also

[Viewing Download Package Information](#)
[Editing Download Package Information](#)
[About Download Packages](#)

About Download Package Associations

Download packages tie products and together with their download files. A download package can be associated with multiple products. Likewise, a download package can be associated with one or more files.

When you associate a download package to a product, you can either specify the product ID or, if you do not know the ID, you can search for products and select it from a list. (In both cases, you can specify or select multiple products, as necessary.)

One potential difficulty in identifying products to associate arises due to the way FlexNet Operations identifies products. A product ID is a combination of the product name and version. The syntax for product IDs is <product name>::<product version>. For example, SalesView Standard::1.0.

See Also

[Managing Download Package Associations](#)
[Managing Download Packages](#)

Associating a Download Package to a Product

You can associate a download package to one or more products from the download package's **View Download Package** page. The Associate menu on the **View Download Package** page includes two different commands for building download package-product associations:

- **Associate to Products**—Allows you to identify one or more products by providing a product ID or searching for products to associate.
- **Associate Where**—Allows you to quickly associate a number of products with the current download package by copying the product associations from one or more other download packages.

Using Associate to Products to Build Download Package-Product Associations

When you associate a download package to a product, you are indicating that the download package is included within the product. The **Associate to Product** command allows you to associate this download package to one or more products. Enter the product IDs or search for the products you want to associate with this download package. An existing customer with access to the product has immediate access to new download packages associated to the product.



Task To associate a download package to products

1. On the **View Download Package** page, click **Associate > Associate to Products**. This link opens the **Associate Download Package to Products** page.
2. Identify the products to associate. Choose whether to enter product IDs or to search for products:
 - Enter product IDs when you already know the product IDs or system product IDs of the products you want to associate.
 1. In the **Product IDs** field, type the product IDs as a comma-separated list or enter them one per line. Note: If you enter system product IDs, remember to select the **Use System IDs** check box.
 2. Click **Associate Products**.
 - Search for products by entering search criteria if you do not know the IDs of the products you want to associate.
 1. Type your search criteria into the product search fields.
 2. Click **Search**. The Producer Portal shows a list of products that match your criteria.
 3. Select the products to associate and click **Associate Download Package to Selected Products**.



Important - A product ID is a combination of the product name and product version with a syntax like the following: `<product name>::<product versions>`. For example, `SalesView Standard::1.0`. One ramification of the product ID syntax is that a search for the product by its product name does not match the product ID. For best results, use an asterisk as a wildcard character to be sure your product search captures the product you are looking for. For example, `SalesView Standard*`.

The Producer Portal creates associations between the current download package and the products you identified and opens the **Where Download Package Used** page for the current download package.

Using Associate Where to Copy Product Associations from Other Download Package

Associate Where copies the product associations of one or more existing download packages. This approach allows you to quickly associate the current download package with all the products to which one or more other download packages are already associated.



Task *To associate a download package with another download package's files*

1. On the **View Download Package** page, click **Associate > Associate Where**. This link opens the **Associate this Download Package to Files Where Other Download Packages Are Found** page.
2. Identify the download packages from which to copy product associations. Choose whether to enter download package IDs, directly, or to search for download packages:
 - Enter download package IDs when you already know the download package IDs or system IDs of the download packages from which you want to copy associations.
 1. In the **Download Package IDs** field, type the download package IDs as a comma-separated list or enter them one per line. Note: If you enter system IDs, remember to select the **Use System IDs** check box.
 2. Click **Associate**.
 - Enter file search criteria if you do not know the IDs of the download packages you want to associate.
 1. Type your search criteria into the download package search fields.
 2. Click **Search**. The Producer Portal shows a list of download packages that match your criteria.
 3. Select the download package to associate and click **Associate to Files of Selected Download Packages**.

The Producer Portal creates associations based on the product associations of the download packages you identified and opens the **Where Download Package Used** page for the current package. All products associated with the download packages you identified are now also associated with the current download package.

See Also

- [About Download Package Associations](#)
- [Disassociating a Download Package from Files](#)
- [Viewing Where a Download Package Is Used](#)

Disassociating a Download Package from a Product

You can remove a download package's product associations from its **View Download Package** page.



Task *To disassociate a download package from a product*

1. On the **View Download Package** page, click **Associate > Disassociate from Products**. This link opens the **Disassociate this Download Package from Products** page.
2. Choose the products to disassociate and click **Disassociate from Selected Products**.

The Producer Portal removes associations from the selected products and refreshes the **Disassociate this Download Package from Products** page to show the current download package-product associations, if any.



Tip - If a download package is associated with multiple products and you intend to remove all product associations, you can skip the step in which you choose the products and just click **Disassociate from All Products**.

See Also

- [About Download Package Associations](#)
- [Associating a Download Package to Files](#)
- [Viewing Where a Download Package Is Used](#)

Associating a Download Package to Files

You can associate a download package to one or more files from the **View Download Package** page. The products to which you associate the download package can be identified by their product IDs, their system IDs, or located via a file search.



Task **To associate a download package to files**

1. On the **View Download Package** page, click **Associate > Associate Files**. This link opens the **Associate Download Package to Files** page.
2. Identify the files to associate. Choose whether to enter file IDs or to search for files:
 - Enter file IDs when you already know the file IDs or system IDs of the files you want to associate.
 - a. In the **File IDs** field, type the file IDs as a comma-separated list or enter them one per line. Note: If you enter system file IDs, remember to select the **Use System IDs** check box.
 - b. Click **Associate Files**.
 - Search for files by entering search criteria if you do not know the IDs of the files you want to associate.
 - a. Type your search criteria into the file search fields.
 - b. Click **Search**. The Producer Portal shows a list of files that match your criteria.
 - c. Select the files to associate and click **Associate File to Selected Files**.

The Producer Portal creates associations between the current download package and the files you identified and opens the **Where Download Package Used** page for the current download package.

See Also

- [About Download Package Associations](#)
- [Disassociating a Download Package from Files](#)
- [Viewing Where a Download Package Is Used](#)

Disassociating a Download Package from Files

You can remove a download package's file associations from its **View Download Package** page.

To remove a bad file from a download package or correct a file association that was made in error, follow the instructions below.



Task *To disassociate a download package from a file*

1. On the **View Download Package** page, click **Associate > Disassociate Files**. This link opens the **Disassociate this Download Package from Files** page.
2. Choose the files to disassociate and click **Disassociate from Selected Files**.

The Producer Portal removes associations from the selected files and refreshes the **Disassociate this Download Package from Files** page to show the current download package-file associations, if any.



Tip - If a download package is associated with multiple files and you intend to remove all file associations, you can skip the file choosing step and just click **Disassociate from All Files**.

Managing Containerized Applications



Version - This functionality is only available for producers who use the Software Delivery module.

This section explains how to manage and distribute containerized applications. Containerized applications are distributed by means of associating them with a download package that supports the distribution of containerized software. Download packages are groups of files that can be related to one or more products and tied to a producer and a product line (see [About Download Packages](#)). It is recommended that you read the section [Managing Download Packages](#) in full first, to gain an understanding of the concepts of download packages.

The containerized applications are stored in a separate registry (either hosted by Reverera or hosted by the software producer).



Important - For the instructions in this section, it is expected that you are working on the Producer Portal with the "View and Manage Download Packages" permission.

Topic	Description
About Containerized Applications	Discusses what containerized applications are.
Working with the Reverera Registry	Discusses how to access the Reverera registry, what "projects" are, and how users are created.
Distributing Containerized Applications	Describes the workflow of distributing containerized applications.

See Also

[Managing Download Packages](#)
[About Download Packages](#)
[About Download Management and FlexNet Electronic Software Delivery](#)

About Containerized Applications

Producers who use FlexNet Operations for electronic software delivery can distribute file-based installers as well as containerized applications. In this documentation, the term “containerized applications” refers to Docker images and Helm charts.

Using the Software Delivery functionality for delivering containerized applications to customers ensures that only those customers with valid entitlements receive the application.

See Also

[Managing Containerized Applications](#)
[Managing Download Packages](#)
[About Download Management and FlexNet Electronic Software Delivery](#)

Working with the Reverera Registry

Just like file-based installers, you distribute containerized applications by associating them with a download package. However, unlike file-based installers, containerized applications are stored in a separate registry that is either hosted by Reverera or by you, the software producer.

You manage your containerized applications by tagging and pushing them to the Reverera registry, using a Docker or Helm command-line interface (CLI).

Entitled customers, who have a Docker or Helm client installed, can pull applications directly from the registry.

This section includes the following topics:

- [About the Reverera Registry](#)
- [Accessing the Reverera Registry](#)
- [About Projects in the Reverera Registry](#)
- [About Users in the Reverera Registry](#)
- [About Entitlement and Security Checks in the Reverera Registry](#)

See Also

[Managing Containerized Applications](#)
[Managing Download Packages](#)
[About Download Management and FlexNet Electronic Software Delivery](#)

About the Reverera Registry

The Reverera registry is a central place to manage and distribute your Docker images and Helm charts. Software producers and end-users use a Docker or Helm CLI to connect to the registry.

The following deployment options of a Reverera registry are available:

- **Shared Registry**—A registry that supports multiple tenants in the Reverera datacenter. To distinguish between tenants, each download package (as well as the resulting projects in the registry, see [About Projects in the Reverera Registry](#)) is automatically prefixed with the 4-character tenant ID. For tag, push, and pull operations, the path of Docker images or Helm charts must be edited to include this tenant ID.
- **Dedicated Registry**—Tenants have exclusive access to one registry instance in the Reverera datacenter. Download packages and projects do not require a prefix.
- **Open Registry (Bring Your Own)**—Software producers provision their own registry, which must be a Harbor instance. Software producers who choose this option need to communicate the connection details for their Harbor registry to Reverera to enable FlexNet Operations to interact with this registry.

Refer to the standard Docker and Helm documentation for information about viewing images and charts in a registry.

See Also

[Working with the Reverera Registry](#)
[Distributing Containerized Applications](#)


Accessing the Reverera Registry

This section describes the URL for the Reverera registry and how to find your registry secret that is required to log in to the Reverera registry.

You need the "View and Manage Download Packages" permission to access the Reverera registry.

Reverera Registry URL

The URL for accessing the Reverera registry depends on the deployment type and has the following format:

Deployment Type	URL
Shared registry	<ul style="list-style-type: none"> ● UAT: <code>https://container-registry.uat-uswest1.reverera.com</code> ● Production: <code>https://container-registry.uswest1.reverera.com</code>
Dedicated registry	<ul style="list-style-type: none"> ● UAT: <code>https://container-registry.uat<tenant-ID>-uswest1.reverera.com</code> ● Production: <code>https://container-registry.<tenant-ID>-uswest1.reverera.com</code>
	 <p>Note ▪ Replace <tenant-ID> with your 4-character tenant ID.</p>
Open Registry (Bring Your Own)	<p>URLs are as specified by the software producer.</p> <p>Producers who use the Open Registry model need to communicate the URL to their respective producer users.</p>



Tip - The registry URL can be displayed on the **View Download Package** page in the Producer Portal (see [Identifying Syntax for “pull” Command](#)) or in the pull command tooltip on the **Download List** page in the End-User Portal (see [Viewing Details of Containerized Applications in the FlexNet Operations End-User Portal Help Library](#)).

Logging in to the Revenera Registry

Producer users use their FlexNet Operations user name and the container registry secret found in their profile page to log on to the Revenera registry. Customer users use their End-User Portal login and their container registry secret to log on to the Revenera registry.

A registry secret is available for all users (producer user and end users) who have been copied by FlexNet Operations to the Revenera registry and have been associated by FlexNet Operations as members to a project. (This step cannot be carried out manually.)

The Revenera registry can only be accessed using the Docker or Helm CLI.



Task **To determine your container registry secret**

Point to the **User** menu (next to the **System** menu at the top right corner of the Producer Portal page) and click **My Profile**. The option **Container registry secret** shows your secret. You can use **Copy** to copy the secret to the clipboard.



Task **To log in to the Revenera registry**

1. In a command prompt, enter the following to log in:

```
docker login <registry-hostname>
```

where <registry-hostname> is the location of the Revenera registry (see [Revenera Registry URL](#), above).

2. You are then prompted to enter your username and password. Your user name is your FlexNet Operations user name. Your password is the container registry secret, which you can find in your user profile (see above).

Important Information for Open Registry Users

All configuration tasks (such as adding and removing projects or users) are handled by FlexNet Operations. Software producers who use the Open Registry (Bring Your Own) model must not do any of the following:

- Alter the project structure in the registry, either by adding projects or removing them
- Alter the user lists directly in the registry, either by adding users or removing them, or by editing membership information

See Also

[Finding Your Container Registry Secret](#)
[Working with the Revenera Registry](#)
[Distributing Containerized Applications](#)

About Projects in the Reverera Registry

When you create a download package in FlexNet Operations that supports the distribution of containerized applications, a “project” is created in the Reverera registry. A download package supports the distribution of Docker images and Helm charts when the option **Container Delivery** is selected on the Create Download page. For more information, see [Preparing a Download Package in FlexNet Operations](#).

A project reflects the information that FlexNet Operations holds about the corresponding download package, such as, for example, the producer users that are associated with the download package. A project is empty until it is mapped to the images and charts that you push to the registry.



Note - The project name is prefixed with your tenant ID unless you are using a dedicated or open registry.



Important - All configuration tasks (such as adding and removing projects or users) are handled by FlexNet Operations. Software producers must not attempt to alter the project structure or user lists, regardless of the registry model they are using.

See Also

[Working with the Reverera Registry](#)
[Distributing Containerized Applications](#)

About Users in the Reverera Registry



Important - All configuration tasks (such as adding and removing projects or users) are handled by FlexNet Operations. Software producers must not attempt to alter the project structure or user lists, regardless of the registry model they are using.

This section explains the user information that is available in the Reverera registry.

About Producer Users in the Reverera Registry

When FlexNet Operations creates a project in the Reverera registry, information about producer users that are currently associated with the download package in FlexNet Operations is automatically propagated to the Reverera registry. This includes all producer users from the producer account and its sub-accounts who have the "View and Manage Download Packages" permission. In the registry, these producer users are added as “members” to the project. They are assigned the role “Developer”, which allows them to map Docker images and Helm charts to the project.

When producer users with the "View and Manage Download Packages" permission are added to the producer account or its sub-accounts in FlexNet Operations, the information in the Reverera registry is updated accordingly. Producer users that are removed from the producer account or its sub-accounts are removed as members from the associated project, but remain as users in the registry.

About End Users in the Revenera Registry

Any end users who are entitled to a product that is mapped to the download package which supports delivery of containerized applications are automatically added to the Revenera registry. These end-users are added as members to the corresponding projects and have the role "Guest". The "Guest" role allows end-users to pull Docker images and Helm charts from the registry.

The list of end users with the "Guest" role is updated each time entitled end users are added to a mapped product. If entitled end users are removed from a mapped product, they are also removed as members from the associated project, but remain as users in the registry. Also, users are added when new entitlements are created, and removed when entitlements are inactivated.

About Roles in the Revenera Registry

The following table describes the roles in the Revenera registry:

Role	Description
Developer	Has read and write privileges for a specified project (tag/push/pull Docker commands and repo add/push/pull Helm commands).
Guest	Has read-only privilege for a specified project. Guests can pull but not push images and charts (pull Docker/Helm command).

See Also

[Working with the Revenera Registry](#)
[Distributing Containerized Applications](#)

About Entitlement and Security Checks in the Revenera Registry

Distributing containerized applications using the download packages helps ensure that only entitled users can pull the images and charts. The entitlement that covers customer access to that product also results in the addition of customer users to the Revenera registry project. Any customer user with the permission to access downloads is also able to log in to the Revenera registry to gain access to those Helm charts and images.

See Also

[Working with the Revenera Registry](#)
[Distributing Containerized Applications](#)

Distributing Containerized Applications

The distribution of containerized applications involves initial steps in FlexNet Operations, followed by steps in the Revenera registry and steps using a Docker or Helm CLI:

- [Preparing a Download Package in FlexNet Operations](#)—creating a download package that supports Docker images and Helm charts, and associating it to a product
- [Uploading Containerized Applications](#)—tagging images or charts and pushing them to the Revenera registry
- [Downloading Containerized Applications](#)—pulling images or charts from the Revenera registry

The following are optional steps which help you manage your images and charts:

- [Viewing Containerized Applications](#)—shows how to display the Docker images and Helm charts that are associated with a download package
- [Identifying Syntax for “pull” Command](#)—shows how to copy the `pull` command to the clipboard
- [Identifying Syntax for “helm repo add” Command](#)—explains how to display a popup which shows the syntax and URL required for the `helm repo add` command

See Also

- [Managing Containerized Applications](#)
- [Managing Download Packages](#)
- [About Download Management and FlexNet Electronic Software Delivery](#)

Preparing a Download Package in FlexNet Operations

The first steps on the FlexNet Operations side involve creating a download package that supports containerized applications, and associating it with one or more products:

- [Creating a Download Package for Containerized Applications](#)
- [Associating a Download Package to a Product](#)



Note - Before creating a download package, you must have defined a producer, at least one deployed product and a product line. (For instructions about creating products and product lines, see [Creating a Product](#) and [Managing Product Lines](#), respectively.)

Creating a Download Package for Containerized Applications



Task *To create a download package that supports containerized applications*

1. In the Producer Portal, click **Products > Create Download Package**. This link opens the **Create Download Package** page.
2. Enter the download package attributes. Ensure that you select **Yes** for the option **Container Delivery**.

Attribute	Description
Download Package ID	<p>A unique ID used to associate the download package with products and files.</p> <p>For download packages that support containerized applications, the download package ID must fulfill the following requirements:</p> <ul style="list-style-type: none"> ● Allowed characters: letters, numbers, and the special characters dot (.), underscore (<code>_</code>), and minus (<code>-</code>). ● Any letters must be lower case ● Start with a letter or number ● Maximum 100 characters

Attribute	Description
Download Package Name	The name of the download package to be displayed to users in the End-User Portal.
Extended Description	An optional, additional description attribute for the download package. Maximum: 1000 characters.
Container Delivery	Specifies whether the download package supports the distribution of containerized applications, such as Docker images and Helm charts. <ul style="list-style-type: none"> ● Yes—Download package supports the distribution of containerized applications as well as file-based installers. ● No—Download package supports only file-based installers.
Version	The version of the download package.
Release Group	An optional attribute to help sort the download package's appearance in the End-User Portal. Maximum: 20 characters.
Effective Date	The date when the download package becomes available on the End-User Portal. Accounts have access to the download package if the download package's effective date occurs within their entitlement's effective and expiration dates on the line item for that download package.
Expiration Date	The date when the download package moves to the archive (Previous Versions) tab or becomes inaccessible from entitlement lines with start dates later than this expiration date. If the expiration date is in the future, the download package appears on the new versions section of the End-User Portal. If the expiration date is in the past, the download package moves to the release archives section. Accounts have access to the download package from the release archives section even if the download package is expired, provided there is an overlap between the download package's effective and expiration dates and the entitlement's effective and expiration dates.
Archive Date	The date on which the download package moves to the archive (Previous Versions) tab. Users may still download it if they have access through an overlap with their entitlement dates, but must find it on the archive tab on the End-User Portal. (New entitlements with beginning dates after the expiration date do not have access to this product at all.)
Download Package Producer	The producer of the product and the download package. (See Managing Producers .)
Product Line	The product line in which the download package appears.
End User License Agreement	An optional, click-through license agreement. (See Managing License Agreements .)

Attribute	Description
Physical Distribution Available	<p>Specifies whether users on the End-User Portal have the option to request a copy of the download package on physical media. FlexNet Operations offers customizations to integrate with a physical distribution facility. When your site is integrated, this attribute shows whether or not end users have the option to request a physical copy of the download package.</p> <p>This option is not supported for containerized applications.</p>
Restrict to US/Canada	<p>Specifies whether to restrict delivery to users in the United States or Canada or to permit delivery outside those countries.</p> <p>Yes—Restricts delivery to users within the United States or Canada.</p> <p>No—Permits delivery to users outside the United States and Canada.</p> <p>If you choose No, ECCN, ENC, and CCATS attributes are required. Otherwise, they are not used. See About Export Compliance for more information.</p>

3. Leave the **Download Instructions** field blank.
4. Complete or continue the download package creation process:
 - Click **Save** to save with current settings. The Producer Portal shows the download package’s **View Download Package** page.
 - Click **Save & add another** to save the current download package and begin creating another download package.

After FlexNet Operations created the download package, a project of the same name is created in the Revenera registry. Any producer users who are part of the account or sub-account of the producer user who created the download package are added as members to the project. For more information, see [About Users in the Revenera Registry](#).



Note - The project name is prefixed with your tenant ID unless you are using a dedicated or open registry.

Associating a Download Package to a Product

It is through a download package’s relationship to products that FlexNet Operations determines which download packages an end user is entitled to. When you associate a download package to a product, you are indicating that end users who are entitled to the product have access to the download package. Any customers who are entitled to the product are added as members with the “Guest” role to the corresponding project in the Revenera registry (see [About End Users in the Revenera Registry](#) for more information).

For detailed information about associating and disassociating download packages to a product, see [Managing Download Package Associations](#).



Task **To associate a download package to a product**

1. On the **View Download Package** page, click **Associate > Associate to Product**. This link opens the **Associate this Download Package to Products** page.
2. Identify the products to associate. Choose whether to enter product IDs or to search for products:
 - Enter product IDs when you already know the product IDs or system product IDs of the products you want to associate.
 - a. In the **Product IDs** field, type the product IDs as a comma-separated list or enter them one per line. Note: If you enter system product IDs, remember to select the **Use System IDs** check box.
 - b. Click **Associate Products**.
 - Search for products by entering search criteria if you do not know the IDs of the products you want to associate.
 - a. Type your search criteria into the product search fields.
 - b. Click **Search**. The Producer Portal shows a list of products that match your criteria.
 - c. Select the products to associate and click **Associate Download Package to Selected Products**.



Important ▪ A product ID is a combination of the product name and product version with a syntax like the following: `<product name>::<product versions>`. For example, `SalesView Standard::1.0`. One ramification of the product ID syntax is that a search for the product by its product name does not match the product ID. For best results, use an asterisk as a wildcard character to be sure your product search captures the product you are looking for. For example, `SalesView Standard*`.



Tip ▪ Use the **Associate Where** option from the Associate menu to quickly associate a number of products with the current download package by copying the product associations from one or more other download packages.

The Producer Portal creates associations between the current download package and the products you identified and opens the **Where Download Package Used** page for the current download package. This page lists the products with which the download package is associated. Clicking on the name of a product in the **Products** list opens the **View Product** page for that product.

See Also

[About Users in the Reverera Registry](#)
[About Download Packages](#)
[Managing Download Package Associations](#)
[Creating a Download Package](#)
[Creating a Product](#)
[Managing Product Lines](#)

Uploading Containerized Applications

Now that there is a project in the registry, you can upload the containerized applications that you want to make available to your end users. The following procedure walks you through the steps to log in to the Revenera registry, and tag and push the desired images or charts to the registry.



Note - If you are using a shared registry, the project name is prefixed with your tenant ID. As a result, you might need to adapt the paths accordingly when performing the tasks described in this section.



Important - All configuration tasks (such as adding and removing projects or users) are handled by FlexNet Operations. Software producers must not attempt to alter the project structure or user lists, regardless of the registry model they are using.

Refer to the Docker and Helm documentation for more detailed information about Docker and Helm commands, respectively.

Pushing Docker Images



Important - You must have a Docker client (CLI) installed to perform the steps in this section.



Task To tag and push a Docker image to the Revenera registry

1. Log in to the Revenera registry (see [Accessing the Revenera Registry](#)).
2. Enter the following to tag a target image that refers to a source image (you can skip this step if the Docker image was tagged when it was built):

```
docker tag <source_image>:<tag> <registry-hostname>/<project-name>/<target_image>:<tag>
```

where <registry-hostname> is the location of the Revenera registry, and <project-name> is the name of the project to which you want to associate the image.

The following shows an example command:

```
docker tag demo-image:latest container-registry.uat-1234.revenera.com/demo-project/new-demo-image:6.0
```

3. Use a command like the following to share the image to the Revenera registry:

```
docker push <registry-hostname>/<project-name>/<image>:<tag>
```

The following shows an example command:

```
docker push container-registry.uat-1234.revenera.com/demo-project/new-demo-image:6.0
```

Pushing Helm Charts



Important - You must have a Helm client (CLI) installed to perform the steps in this section.



Task **To push a Helm chart to the Reverera registry**

1. Use a command like the following to add a repository:

```
helm repo add --username=<username> --password=<cli-secret> <repo-name> <registry-hostname>/  
<path-to-project>/<project-name>
```

The following shows an example command:

```
helm repo add --username=example-user --password=password demo-repo https://container-  
registry.uat-1234.reverera.com/chartrepo/demo-project
```

2. Then use a command like the following to share a Helm chart to the Reverera registry:

```
helm push --username=<username> --password=<cli-secret> <chart-name> <repo-name>
```

The following shows an example command:

```
helm push --username=example-user --password=password demo-chart demo-repo
```

See Also

- [About Users in the Reverera Registry](#)
- [Working with the Reverera Registry](#)
- [Accessing the Reverera Registry](#)
- [About Projects in the Reverera Registry](#)
- [Downloading Containerized Applications](#)
- [Identifying Syntax for “helm repo add” Command](#)

Downloading Containerized Applications

Once an image or chart has been uploaded to the Reverera registry and associated with a project, it is available for entitled end-users to download to their local repository. This section outlines the steps and commands that an end-user would use.



Tip ▪ The pull command for downloading an image or chart from the Reverera registry is displayed on the **View Download Package** page in the Producer Portal (see [Identifying Syntax for “pull” Command](#)) and the **Download List** page in the End-User Portal (see “Viewing Details of Containerized Applications” in the FlexNet Operations End-User Portal Help Library).



Note ▪ If you are using a shared registry, the project name is prefixed with your tenant ID. As a result, you might need to adapt the paths accordingly when performing the tasks described in this section.



Important ▪ All configuration tasks (such as adding and removing projects or users) are handled by FlexNet Operations. Software producers must not attempt to alter the project structure or user lists, regardless of the registry model they are using.

Refer to the Docker and Helm documentation for detailed information about Docker and Helm commands, respectively.

Downloading Docker Images



Important - End users must have a Docker client (CLI) installed to perform the steps in this section.



Task To pull an image from the Revenera registry

1. The end user logs in to the Revenera registry, as described in [Accessing the Revenera Registry](#).
2. The end user then uses a command like the following to pull an image from the Revenera registry:

```
docker pull <registry-hostname>/<project-name>/<image>:<tag>
```

The following shows an example command:

```
docker pull container-registry.uat-1234.revenera.com/demo-project/new-demo-image:6.0
```

Downloading Helm Charts



Important - End users must have a Helm client (CLI) installed to perform the steps in this section.



Task To pull a Helm chart from the Revenera registry

1. The end user logs in to the Revenera registry, as described in [Accessing the Revenera Registry](#).
2. The end user then uses a command like the following to pull a chart from the Revenera registry:

```
helm pull <repo-name><chart>
```

The following shows an example command:

```
helm pull demo-repo demo-chart
```

See Also

[About Users in the Revenera Registry](#)
[Working with the Revenera Registry](#)
[Accessing the Revenera Registry](#)
[About Projects in the Revenera Registry](#)
[Uploading Containerized Applications](#)
[Viewing Containerized Applications](#)
[Identifying Syntax for “pull” Command](#)
[Identifying Syntax for “helm repo add” Command](#)

Viewing Containerized Applications

You can view the containerized applications that are associated with a download package from the **View Download Package** page.



Task *To view containerized applications associated with a download package*

1. Click **Products** > **Search Download Packages**. The **Search Download Packages** page opens.
2. Enter your download package search criteria and click **Search**. The Producer Portal shows a list of the download packages that match your search criteria on the **Search Results: Download Packages** page.
3. Click the **Download Package ID** for the download package you want to view. The Producer Portal shows the **View Download Package** page for the download package you selected.
4. On the **View Download Package** page, scroll down to see details about files, Docker images and Helm charts that are associated with the download package.

Identifying Syntax for “pull” Command

In the **Container Images** and **Helm Charts** sections, the **View Download Package** page shows a **Copy** button (in the **Pull command** column). Click the **Copy** button to copy the `pull` command for downloading the image or chart from the Reverera registry to the clipboard.

You can then paste the command into your Docker or Helm client to pull the desired image or chart from the Reverera registry.

See Also

[Accessing the Reverera Registry](#)

[Viewing Containerized Applications](#)

[Identifying Syntax for “helm repo add” Command](#)

Identifying Syntax for “helm repo add” Command

The **View Download Package** page shows an **Add Repo Command** button in the **Helm Charts** section. When clicked, the button shows the syntax and registry URL for the `helm repo add` command which is needed to add a local chart repository. This helps you and your end-users to determine the registry URL in cases where no images have been added yet.

The following shows the syntax of the `helm repo add` command:

```
helm repo add --username=<username> --password=<cli-secret> <repo-name>  
<registry-hostname>/<path-to-project>/<project-name>
```

Here is an example command:

```
helm repo add --username=example-user --password=mypassword myrepo  
https://container-registry.uat1102-uswest1.reverera.com/chartrepo/container-package-demo
```

For information about finding your registry secret, see [Logging in to the Reverera Registry](#).



Tip ▪ *In the End-User Portal, the Add Repo Command button is located on the Downloads page.*

See Also

- [Accessing the Revenera Registry](#)
- [Viewing Containerized Applications](#)
- [Identifying Syntax for “pull” Command](#)

Managing Download Files

Producers who use FlexNet Operations for electronic software delivery can add files and upload file images on the Producer Portal. Producers can add files in the Producer Portal and associate them to products via download packages.

This section discusses download file management activities and concepts.



Important - For the instructions in this section, it is expected that you are working on the Producer Portal with sufficient permissions to perform the tasks described.

Table 2-33 -

Topic	Description
About Files and File Images	Discusses the Producer Portal's approach to files and file images and how those concepts are related to download packages, producers, and products. It also explains some important file management concepts, such as file restrictions and file aliases. Additionally, this section includes the following subtopics: <ul style="list-style-type: none"> ● About File Attributes ● About Aliases ● About File Restrictions
Adding Files	Describes how to add files. Once a file has been added, you can perform file-management activities like uploading a file image for it and associate it with download packages.
Searching for Files	Shows how to search for files.
Viewing File Information	Shows how to view information related to the files in FlexNet Operations. Users typically search for a file they want to view and then click that file's name to open the View File page. The following options are available from the View File page: <ul style="list-style-type: none"> ● Viewing this File ● Viewing Where a File Is Used ● Viewing File Restrictions ● Viewing Emails Related to a File ● Viewing File Transactions ● Viewing File Downloads

Table 2-33 •

Topic	Description
Editing File Information	Shows how to edit, delete, or otherwise manipulate files in FlexNet Operations. <ul style="list-style-type: none">• Editing a File• Aliasing a File• Uploading a File Image• Deleting a File Image• Reidentifying a File• Restricting a File• Creating an Email Notification for a File
Managing File Associations	Discusses the methods of associating download files with products. <ul style="list-style-type: none">• About File Associations• Associating a File to Download Packages• Using Associate Where to Copy Associations from Another File• Disassociating a File from a Download Package

See Also

[About Download Management and FlexNet Electronic Software Delivery](#)
[Managing Download Packages](#)

About Files and File Images

On the Producer Portal, you can add and manage the files you want to make available for your customers to download. You can add a file and then upload a file image. Adding a file is little more than creating a placeholder for the actual file and specifying a file description and file ID. Uploading the file image copies the actual file from your local system into FlexNet Operations. Without the file image upload, the file in FlexNet Operations has no payload when a customer or channel partner tries to download it from the End-User Portal. For instructions, see [Adding Files](#) and [Uploading a File Image](#).

This section provides a brief overview of file management concepts and options and provides additional information on the upload manager and other file upload methods as well as a discussion of supported file hosting options.

Download File Management Overview

The creation of a download file adheres, at least, to the following sequence:

1. Add the file—Create a placeholder for the file image in FlexNet Operations and give the file, at minimum, a file ID. Other file details are optional at this point.
2. Upload the file image—Copy the actual file bits into FlexNet Operations. The file bits are what gets delivered to End-User Portal users when they download the file.

3. Associate the file with one or more download packages—Download packages collect one or more files and tie them to a product. Without any association to a download package, the file will never appear for download on the End-User Portal.

Once a file has been added and associated with a download package, it is available for End-User Portal users to download from any product to which the download package is associated and to which the End-User Portal user is entitled. No further actions are necessary; however, there are a number of options in the Producer Portal for editing a file's details, changing its associations, restricting access to it, and sending email notifications to users who are entitled to the products that include it.

- Editing file information and reidentifying a file—Most file details can be edited on the **Edit File** page, but to change a file's ID, you must reidentify the file. (See [Editing a File](#) and [Reidentifying a File](#), for instructions.)
- Aliasing a file creates a duplicate of an existing file that points to the same file image but can be managed separately. File aliases allow you to avoid uploading multiple copies of the same file image. (See [About Aliases](#) and [Aliasing a File](#).)
- Restricting access to a file—controls whether a file is shown to specified customers in the End-User Portal. (See [About File Restrictions](#) and [Restricting a File](#).)
- Sending a notification email for users who have access to the file—Initiate an email message to all End-User Portal users who have access to the file. (See [Creating an Email Notification for a File](#).)
- Adding and removing download package associations—Reuse the file in other download packages by making additional associations or disassociate the file from a currently associated download package. (See [Managing File Associations](#).)

These file management activities are covered in greater detail in this section. Likewise, instructions are presented in this section for researching a file's associations and restrictions as well as its transaction and download history. See [Viewing File Information](#) for instructions.

Anonymous File Download

You can also make files available for users to download without requiring users to log in to the End-User Portal. This enables you as the producer to post a link to a file on your own website, or you can send a URL in an email to your end-users. Typically you would use the anonymous file download for informational files, but not actual software files.

The following instructions describe the sequence for creating an anonymous download. The result is a URL that you can make available to customers. Customers who click on this URL can download the associated file without providing credentials. Note that these instructions assume that you already created a download package and associated it with a file (containing a file image) for the anonymous download.



Task

To make a file available for anonymous download:

1. Create a custom attribute called ANONYMOUS_ALLOWED. This involves the following steps:
 - a. Click **Administer > Custom Attributes**. The **Custom Attributes** page opens.
 - b. On the **Custom Attributes** page, click **Add Attribute**.
 - c. On the Create Custom Attribute page, specify the following custom attribute settings:
 - Name: **ANONYMOUS_ALLOWED** (in capital letters)

- Entity type: **File**
- Status: **Active**
- Type: **Text**
- Text type: **Single select**. Add the valid values **TRUE** and **FALSE**.

For more information about custom attribute settings, see [Custom Attribute Settings](#).

d. Click **Save** to save the custom attribute.

2. Assign the ANONYMOUS_ALLOWED custom attribute that you created to the file that you want to make available to your customers.

For information about adding attributes to a file, see [Editing a File](#).

3. Open the **View Download Package** page and make note of the export compliance values assigned to the download package. This information is required to build the URL.

For more information, see [Viewing Download Package Information](#).

4. Build the download URL. The format of the URL depends on whether export controls apply to the file, and whether you use the system file ID or file ID to identify the file.

- When no export controls apply, use either of the following formats:
 - `https://<siteID>-esd.flexnetoperations.com/flexnet/operations/AnonymousDownload?systemFileID=<systemFileID>`
 - `https://<siteID>-esd.flexnetoperations.com/flexnet/operations/AnonymousDownload?fileID=<fileID>`

Replace <siteID> with your organization's DNS name or the specific site ID supplied by Revenera, <systemFileID> with the system file ID, and <fileID> with the file ID. You find the system file ID and file ID on the **View File** page. For more information about the site ID, see [FlexNet Operations Environments](#).

- When export controls apply, use either of the following formats:
 - `https://<siteID>-esd.flexnetoperations.com/flexnet/operations/AnonymousDownload?fileID=<fileID>&eccnNum=<ECCNcode>&leEnc=<ENCcode>&ccats=<CCATScore>&nlr=<T/F>`
 - `https://<siteID>-esd.flexnetoperations.com/flexnet/operations/AnonymousDownload?systemFileID=<systemFileID>&eccnNum=<ECCNcode>&leEnc=<ENCcode>&ccats=<CCATScore>&nlr=<T/F>`

Replace <siteID> with your organization's DNS name or the specific site ID supplied by Revenera, <systemFileID> with the system file ID, and <fileID> with the file ID. You find the system file ID and file ID on the **View File** page. For more information about the site ID, see [FlexNet Operations Environments](#).

Replace <ECCNcode>, <ENCcode>, and <CCATScore> with the relevant export compliance codes. Replace <T/F> with the value selected for **Restrict to US/CANADA (NLR)**. You obtain these values from the **View Download Package** page for the download package that is associated with the file that you want to make available.

5. Use the URL to make the file available to your customers.

About Enabling Channel Partners to Download Files

A producer can enable a channel partner to download files, on behalf of end users, for product demonstration and support purposes.

After the product is deployed and associated with a download package, the producer creates the channel partner user, creates an entitlement line item for the product for the channel partner user's account, and assigns an end customer user account to the entitlement.



Important - This option is limited to entitlements with end customer and channel partner user accounts. It does not work for entitlements with only channel partner users.

The channel partner user logs in to the FlexNet Operations End-User Portal with the line item's activation ID, navigates to the **List Entitlements** page, and locates the entitlement in the table. From there, the file can be downloaded using the standard download procedure.

About File Localization

Some aspects of a file can be localized: File Description, Extended Description, and Content Detail. To show the locale-specific fields for a localizable attribute, click **Show Languages**.

See Also

[About Download Management and FlexNet Electronic Software Delivery](#)
[Associating a File to Download Packages](#)

About File Attributes

The following attributes apply to files, and are especially important when you are adding files or editing file information.

Table 2-34 •

Attribute	Description
File ID	A unique ID used to associate the file with its file image and with download packages.
System File ID	A unique internal numeric identifier of the file.
File Description	The name of the file to be displayed to users in the End-User Portal (maximum 500 characters). The file description is required when adding a new file. It should be brief but descriptive, for example, Enterprise Server 2.4 Solaris or Enterprise Server 2.4 Documentation.
Alias	A read-only attribute that indicates if the current file is an alias of another file or if any aliases have been created for the current file. If aliases exist for the current file, their IDs are listed here. If the current file is an alias, the ID of the original file appears here. Click a file ID to go to the View File page for that file.

Table 2-34 •



Attribute	Description
Extended Description	An optional attribute for providing additional information about the file (maximum 1000 characters).
Delivery Source	Indicates if the file is an external source or uploaded to FlexNet Operations.  Note • The External delivery source should only be selected if you are using the Updates and Insights module to deliver file download URLs programmatically via the REST APIs. For all files that should be available for download via the End-User Portal, use FlexNet Operations as the Delivery Source.
External Source	If the External delivery source is selected, the URL where the file is located.
File Size (bytes)	The file size in bytes. For files with a FlexNet Operations delivery source, this is automatically calculated and cannot be changed by the user. For files with an External delivery source, this field can be changed by the user either manually or using the calculator icon to automatically calculate the file size.  Note • The calculator icon only works on external sources that use either the HTTP or HTTPS protocols. Any other protocol returns a file size of 0.
MD5 CheckSum	A 32-character hash algorithm used for validating data integrity. For files with a FlexNet Operations delivery source, this field is maintained by the Application and cannot be changed by the User. For files with an External delivery source, this field is manually entered by the user.
SHA2 CheckSum	The 64-character hash algorithm used for validating data integrity. For files with a FlexNet Operations delivery source, this field is maintained by the Application and cannot be changed by the User. For files with an External delivery source, this field is manually entered by the user.
Execute Upon Download?	When selected, the FlexNet Embedded client will execute it as part of the software update download process.
File Name	The name of the file image to be uploaded, for example <code>filename.zip</code> (maximum 255 characters). When you add a file, the file name is optional and, when the file image is uploaded, its filename overwrites any value in the File Name field. (The file name is required after a file image has been uploaded.) After the file image is uploaded, the file name can be edited to show a different file name to End-User Portal users. Non-ASCII characters are not allowed in the file name.

Table 2-34 •

Attribute	Description
File Status	<p>A read-only attribute that shows the status of a file. A file's status can be</p> <ul style="list-style-type: none"> ● Loaded—A file image has been uploaded for the file. ● Not Loaded—No file image is currently related to the file because no image has been uploaded or because the upload process has not completed. ● Deleted—A previously uploaded file image has been deleted. (If you successfully upload a new file image, the file's status changes to Loaded.)
Download Available	<p>The status of the download.</p> <ul style="list-style-type: none"> ● No—Download not available ● Yes—Download available.
Owner	<p>A read-only attribute that shows whether or not your account is the owner of the file. (Files can be shared with other accounts, but only the file's owner can change the file and only one account can be the owner.)</p>
Restricted	<p>Indicates whether or not the file has any restrictions.</p>
File Size	<p>The size of the uploaded file image in bytes.</p>
MD5 CheckSum	<p>The MD5 checksum value for the file.</p>
SHA2 CheckSum	<p>The SHA2 checksum value for the file.</p>
Last Uploaded	<p>The most recent date a file image was uploaded for the file.</p>
Last Retrieved From Location	<p>The location from which the most recent file image upload originated.</p>
Content Detail	<p>An optional attribute for additional details to be shown to End-User Portal users when they click the Content Detail expansion for this file. If the file image is a ZIP or JAR file, the zipinfo data is added to this field during the file image upload.</p> <p>If necessary, you can edit the information in Content Detail, after the file image has been uploaded, to change what End-User Portal users see when they expand the Content Detail.</p>

Files can also have custom (Producer-defined) attributes. To learn more about custom attributes, including custom file attributes, see [Administering Custom Attributes](#).

See Also

[Adding Files](#)

[Searching for Files](#)

[Editing File Information](#)

About Aliases

Aliases behave just like separate files after they have been created, with one exception: they always use the same file image as their original file. At creation time, an alias is a copy of the original file and includes its file associations and other file attributes. After it is created, any changes made to the alias apply only to the alias itself; they have no impact on the original file. Therefore, an alias can be altered to have attributes and download package associations that differ from the original file. However, all the aliases of a file share the file image of the original file. And if you change the file image uploaded for the original file, all that file's aliases also use the new file image. (You cannot otherwise change the file image for an alias.)

An alias can be edited, reidentified, aliased, restricted independently of its original file. Likewise, you can send notification emails specifically for the alias file.



Note - When you choose **Edit > Alias this File** on the **View File** page of an alias, you create a new alias based on the current alias. This alias takes the attributes and associations of the current alias and uses the file image from the original file.

When viewing files on the Producer Portal, notice that the **Alias** field in the file details indicates whether or not the file is an alias.

- If a file is an alias file, the **Alias** field shows **Yes (Alias of System FileID <fileID>)**, where <fileID> is the system file ID for the original file.
- If the file is an original, non-alias file, the **Alias** field shows one or more system file IDs. These file IDs are links to the file's aliases.



Note - For instruction on creating an alias, see [Aliasing a File](#).

About File Restrictions

Producers can set up file restrictions to either permit or deny End-User Portal access to the file for the specified accounts.



Note - By default, a file is unrestricted. If no restrictions are created for a file, it is accessible to all entitled accounts.

Accounts can be added to the Restrict File list one at a time. The process starts with a search for the account to permit or deny access by its account ID or its account name. Search results are shown on the **Find an Account** page in a pop-up window. When you choose to restrict a previously unrestricted file, the **Find an Account** page provides the option of specifically permitting (**Restrict Allow**) or denying (**Restrict Deny**) access to the file for the selected account. For that file, any accounts you add to the restrictions list must follow the choice (**Restrict Allow/Restrict Deny**) you made for the first account.

- **Restrict Allow**—Creates a file access “allow list” that stipulates the accounts that are permitted to access the file. Any account not on the list is not permitted to access the file in the End-User Portal, even if they are otherwise entitled to the product.

- **Restrict Deny**—Creates a file access “block list” that stipulates the accounts that are not permitted to access the file. None of the accounts on the list are permitted to access the file in the End-User Portal, even if they are otherwise entitled to the product.

Multiple accounts can be removed from the restrictions list on the **Restrict File** page by selecting their check boxes in the **Remove this Account** column and then clicking **Remove Selected Accounts**.



Note ▪ For instructions about restricting files, see [Restricting a File](#).

Adding Files

The first step in making files available to your customers in the End-User Portal is to add the files to FlexNet Operations.



Important ▪ Only the following characters are allowed in file names: lowercase alphabet (a-z), uppercase alphabet (A-Z), digits (0-9), minus (-), underscore (_), and dot (.). Filenames must not start with a dot (.). Using other characters might cause the file upload to fail.

After a file is added, you can upload a file image and associate the file with one or more download packages. See [Editing File Information](#) and [Managing File Associations](#) for more information about the actions you can take once a file has been added.



Task

To add a file

1. Click **Products** > **Create File**. This link opens the **Add File** page.
2. On the **Add File** page, enter file-related details for the file you want to add.
 - **File Description**—(required) The name the End-User Portal displays for the file. Maximum length: 500 characters.
 - **File ID**—(required) Your account’s unique identifier for the file. Maximum length: 100 characters.
 - **Delivery Source**—Indicate whether the file is uploaded to FlexNet Operations or if it is provided via an external source.



Note ▪ The **External** delivery source should only be selected if you are using the *Updates and Insights* module to deliver file download URLs programmatically via the REST APIs. For all files that should be available for download via the End-User Portal, use *FlexNet Operations* as the **Delivery Source**.

If **External** is selected as a **Delivery Source**, enter the following details:

- **External Source**—(required) The URL for the externally sourced file.
- **File Size (bytes)**—(required) Enter a number or use the calculator icon to automatically calculate the file size.



Note - The calculator icon only works on external sources that use either the HTTP or HTTPS protocol. All other protocols will return a value of 0.

- **MD5 CheckSum** and/or **SHA2 CheckSum**—(required) At least one of these must be entered, though, optionally both may be.

Other fields are optional. For more information about file attributes, see [About File Attributes](#).

3. Complete the file addition process by clicking **Save**, **Save and Add Another**, or **Save and Upload File**.
 - Click **Save** to add the file and upload the file image later. The Producer Portal saves the file and shows its **View File** page.
 - Click **Save and Add Another** to save the current file and start adding a new download file. The Producer Portal saves the current file and resets the **Add File** page fields for new input.
 - Click **Save and Upload File** to add the file and upload the file image. The Producer Portal saves the file and shows the **Upload File** page. See [Uploading a File Image](#) for file image upload instructions.

See Also

[Uploading a File Image](#)
[About Files and File Images](#)

Searching for Files

Producers can use the file search feature to locate previously uploaded files on the Producer Portal. Files have a several attributes which you can use to locate the files you are interested in. Some of these searchable attributes include

- **File ID**—Unique value by which your company identifies individual files. The File ID may come from a release management or source code control system.
- **System File ID**—Unique identifier assigned by the Producer Portal when a new file object is created.
- **File Description**—A more descriptive name of the file. The File Description functions as the file name that users see on the End-User Portal download page.
- **File Name**—Actual system level name of the file. For example, `installer_2_7.zip`.
- **File Status**—You can search all files, files for which an image has been loaded, or files for which an image has not been loaded.
- **Created in Date Range (Begin)**—Specifies the start of the date range in which the file was created. Used in conjunction with **Created in Date Range (End)** to express the beginning date of that range.
- **Created in Date Range (End)**—Specifies the end of the date range in which the file was created. Used in conjunction with **Created in Date Range (Begin)** to express the ending date of that range.
- **Last Uploaded (Begin)**—Specifies the start of the date range in which the file was last uploaded. Used in conjunction with **Last Uploaded (End)** to express the beginning date of that range.
- **Last Uploaded (End)**—Specifies the end of the date range in which the file was last uploaded. Used in conjunction with **Last Uploaded (Begin)** to express the ending date of that range.



Note - A file's searchable attributes may also include the values for any custom file attributes you have defined. To learn more about custom attributes, including custom file attributes, see [Administering Custom Attributes](#).

For more information about file attributes, see [About File Attributes](#).



Tip - To return a list of all files, leave the search criteria blank and click **Search**. Empty searches match all files.



Task **To search for a file**

1. Click **Products** > **Search Files**. The **Search Files** page opens.
2. Enter your file search criteria and click **Search**. The Producer Portal shows a list of the files that match your search criteria on the **Search Results: Files** page.

From the **Search Results: Files** page, you can click:

- **Search Again** to run another file search.
 - **Export** to export a set of files as a Data Import Template file (see [Importing and Exporting Entities](#)).
 - **Upload files** to upload the files to FlexNet Operations so they are available for your customers to download from the End-User Portal.
3. Click the **File ID** for the file you want to view.

The Producer Portal shows the **View File** page for the file you selected.



Note - The file search is not case sensitive and supports the use of the asterisk character as a wildcard. (Wildcards cannot be used for System ID values.)

Click on the file ID of a file to show its **View File** page. On a file's **View File** page, you can

- View file details, restrictions, transactions, emails, and downloads.
- Find all the products where this file is used (**View** > **Where Used**).
- Edit the file information.
- Upload a file (that is, upload the actual bits associated with this file object).
- Associate the file with one or more download packages.
- Associate the file with all the download packages to which some other file is associated. (For example, use `Widget_2_1.ReadMe.txt` wherever `Widget_2_1.exe` is found.)

See the table of topics in [Managing Download Files](#) for a list of tasks you can perform on a file.

See Also

[Viewing File Information](#)
[Editing File Information](#)
[Managing File Associations](#)
[Importing and Exporting Entities](#)

Viewing File Information

Users typically search for a file they want to view and then click that file's name to open the **View File** page. The View menu on the **View File** page includes several commands to get more details about the file, where it is used, how it has been managed, who it has been delivered to, and so on. With the commands in the View menu, you can perform the following tasks.

Table 2-35 -

Topic	Description
Viewing this File	Explains how to return to the basic View File page when performing other file-related operations.
Viewing Where a File Is Used	Shows how to determine which products a file is associated with.
Viewing File Restrictions	Describes how to view a list of accounts that are permitted or denied access to a file. Restricting file access to designated accounts is optional. By default, files are accessible to all entitled accounts.
Viewing Emails Related to a File	Illustrates how to view email messages related to a file—email messages sent for products to which the current file is associated.
Viewing File Transactions	Shows how to view transactions related to a file.
Viewing File Downloads	Explains how to view download activity for a file.

See Also

- [Searching for Files](#)
- [Editing File Information](#)
- [About Files and File Images](#)

Viewing this File

When working with files, you can return to the basic **View File** page by clicking **View this File**. File-related operations might be checking where the file is used, associating the file to download packages, and so forth. On these file-related pages, **View this File** is a link in the **View** menu.

The Producer Portal also shows the **View File** page when you add a file.



Task

To return to the basic View File page

- Click **View > View this File**.

See Also

[Viewing File Information](#)
[Editing File Information](#)
[About Files and File Images](#)

Viewing Where a File Is Used

You can display a list of the download packages that use a file from the **View File** page.



Task *To view where the current file is used*

- On the **View File** page, click **View > View Where Used**.

The Producer Portal opens the **Where File Used** page. This page lists the download packages with which the file is associated. Clicking on the name of a download package in the list opens its **View Download Package** page.

See Also

[Managing File Associations](#)
[Editing File Information](#)
[About Files and File Images](#)

Viewing File Restrictions

You can view a list of accounts that are permitted to access a file in the End-User Portal. Restricting file access to designated accounts is optional. By default, files are accessible to all accounts.



Task *To view file restrictions*

- On the **View File** page, click **View > View Restrictions**.

The Producer Portal opens the **View File Restrictions** page. Depending on how the file restrictions were specified, this page lists the accounts that are permitted or denied access to the current file. (File restriction lists can be lists of permitted or denied accounts.)

If no accounts appear in the **File Restricted To** list, then the file is accessible by all accounts.

See Also

[Restricting a File](#)
[About File Restrictions](#)

Viewing Emails Related to a File

You can view email messages sent for products to which the current file is associated. These messages appear in a list on the **Search Results: Email** page. The email messages are sorted from newest (most recently sent) to oldest.



Task **To view emails related to a file**

- On the **View File** page, click **View > View Emails**.

The Producer Portal opens the **Search Results: Email** page. Email messages are shown in order of recency (most recently sent first). Click the System Email ID to show the **View Email** page for that email message.

If no emails have been sent for products to which the current file is associated, the Producer Portal shows an error message that reports: No email messages found.

See Also

[Managing File Associations](#)
[Viewing Where a File Is Used](#)
[Creating an Email Notification for a File](#)

Viewing File Transactions

You can view transactions related to a file from the file's **View File** page. These transactions, such as adding a file, associating it to a download package, and uploading its file image, appear in a list on the **Search Results: Transactions** page.



Task **To view transactions related to a file**

- On the **View File** page, click **View > View File Transactions**.

The Producer Portal opens the **Search Results: Transactions** page. Transactions are ordered by date with the most recent Transaction first. Click on the System Transaction ID to open its **View Transaction** page.

A transaction is recorded by the Producer Portal as users make changes to the system. File transactions are recorded for changes like adding a file or associating a file with a product.

See Also

[Managing File Associations](#)
[Adding Files](#)
[About Files and File Images](#)

Viewing File Downloads

You can view download activity for a file from the file's **View File** page.



Task **To view a downloads for a file**

- On the **View File** page, click **View > View Downloads**.

The Producer Portal opens the **File Downloads** page for the current file. The **File Downloads** page shows file details and lists the download history for that file. Each entry in the **Download History** list shows the date of the download, the account and user who downloaded the file, and the user's email address, as well as the IP address where the file was downloaded, the country where the download request originated, and the download method used.

By default, the **File Downloads** page shows download activity within the last 180 days.

See Also

[Viewing File Information About Files and File Images](#)

Editing File Information

Users typically search for a file they want to view and then click that file's name to open the **View File** page. The Edit menu on the **View File** page includes several commands for actions like altering, restricting, or creating a notification for an existing file. With the commands in the Edit menu, you can perform the following tasks.

Table 2-36 -

Topic	Description
Editing a File	Describes how to change a file's details.
Aliasing a File	Shows how to create an alias of a file. In FlexNet Operations, an alias for a file uses the same file image as an existing file but has its own meta data.
Uploading a File Image	Explains how to upload a file image for an existing file.
Deleting a File Image	Explains how to delete a file image.
Reidentifying a File	Discusses how to reidentify a file to change the file ID of an existing file.
Restricting a File	Explains how to restrict access to a file for designated accounts.
Creating an Email Notification for a File	Describes how to create an email notification for a file.

See Also

[Managing File Associations](#)
[Searching for Files](#)
[About Files and File Images](#)

Editing a File

You can edit file details from the **View File** page. Most of the file information that you enter when you add a file can be edited on the Edit File page.

Some commonly edited file details include

- **File Description**—(required) The name of the file that End-User Portal users see. It should be brief but descriptive, for example, **Enterprise Server 2.4 Solaris** or **Enterprise Server 2.4 Documentation**.
- **File Name**—(required) The name of the file as it will appear in the End-User Portal. Please note that during the upload of a file whose delivery source is **FlexNet Operations**, this field is overwritten with the name of the file that is being uploaded.



Important - Only the following characters are allowed in file names: lowercase alphabet (a-z), uppercase alphabet (A-Z), digits (0-9), minus (-), underscore (_), and dot (.). Filenames must not start with a dot (.). Using other characters might cause the file upload to fail.

- **Content Detail**—Additional information that is displayed when the end user clicks the + to see additional file information in the End-User Portal. If the file is a ZIP or JAR file, the Producer Portal automatically sets Content Detail to the file's zipinfo during the file upload process.
- **Delivery Source**—Indicate whether the file is uploaded to FlexNet Operations or if it is provided via an external source.



Note - The **External** delivery source should only be selected if you are using the Updates and Insights module to deliver file download URLs programmatically via the REST APIs. For all files that should be available for download via the End-User Portal, use FlexNet Operations as the Delivery Source.

If **External** is selected as a **Delivery Source**, enter the following details:

- **External Source**—(required) The URL where the file is located.
- **File Size (bytes)**—(required) The size of the file. This can be manually entered or calculated using the calculator icon.



Note - The calculator icon only works on external sources that use either the HTTP or HTTPS protocols. Any other protocol will return a file size of 0.

- **MD5 CheckSum**—(required if SHA2 CheckSum is empty) A 32-character hash algorithm for validating data integrity.
- **SHA2 CheckSum**—(required if MD5 CheckSum is empty) A 64-character hash algorithm for validating data integrity.

Either MD5 or SHA2 CheckSum is required for externally sourced files. Optionally, both can be populated.



Note - A file's editable attributes may also include the values for any custom file attributes you have defined. To learn more about custom attributes, including custom file attributes, see [Administering Custom Attributes](#).

Many attributes support localization. For localizable attributes, click Show Languages to reveal additional, locale-specific fields for those attributes.

For more information about file attributes, see [About File Attributes](#).



Task **To edit file details**

1. On the **View File** page, click **Edit > Edit this File**. This link opens the Edit File page for the current file.
2. Make your changes to one or more file details.
3. Click **Save**.

The Producer Portal saves your changes and returns to the **View File** page for the current file.



Tip ▪ Some file details, such as *Alias*, *File Status*, *Owner*, *Restricted*, and *File ID* cannot be altered on the *Edit File* page. To change a file's ID, you must reidentify the file. To change a whether a file is restricted you must use the *Restrict File* page (*Edit > Restrict*). To create an alias for the current file, use *Edit > Alias this File*.

See Also

[Reidentifying a File](#)
[About File Attributes](#)

Aliasing a File

You can create an alias of an existing file from the file's **View File** page. In FlexNet Operations, an alias for a file uses the same file image as an existing file but has its own attributes. Initially, the file ID, file description, and other attributes are copied from the current file.

The main benefit of creating an alias is that you can maintain a separate file, with its own description, restrictions, and download package associations, without the need to upload redundant file images.



Task **To add a file alias**

1. On the **View File** page, click **Edit > Alias this File**. This link opens the **Add File Alias** page.
2. Edit the details for the file alias. The File ID must be unique; hence, you must at least provide a different File ID.
3. Click **Save**.

The Producer Portal adds the file alias and opens the **View File** page for the file alias.



Note ▪ The *Alias* field value is **Yes (Alias of System FileID <fileID>)**, where *fileID* is the system file ID for the original file (the file on which this file alias was based). If you want to view or make changes to the original file, click its system file ID.

See Also

[About Files and File Images](#)
[Viewing File Information](#)

Uploading a File Image

You can upload a file image for an existing file. During the upload process, you select a file from your local file system to upload it to the Producer Portal.




Note - Uploaded files cannot be downloaded until the **Download Available?** field of the **View File** page indicates **Yes**. This action is only available when the delivery source is **FlexNet Operations**.



Task To upload a file image

1. On the **View File** page, click **Edit > Upload File**. This link opens the **Upload File** page.
2. On the **Upload File** page there are four upload options. Select the tab for the option you want to use and do the following:

Upload Option	Procedure
HTTP Upload	<ol style="list-style-type: none">1. Click Browse and navigate to the file located on your PC to upload. (The user experience varies depending on the web browser you are using.) The Producer Portal shows the name of the upload file.2. Optionally, type the expected MD5 checksum value.3. Click Upload.
FTP Upload	<ol style="list-style-type: none">1. Click Browse to select a file that has been uploaded to the Revenera FTP Server. A window appears with the list of files that are available. Select the box of the desired file.2. Optionally, type the expected MD5 checksum value.3. Click Upload.
Remote FTP Server	<ol style="list-style-type: none">1. Enter the FTP Hostname, Username and Password as well as the path and filename of the file located on the remote FTP server.2. Optionally, type the expected MD5 checksum value.3. Click Upload.
High Speed Upload	<ol style="list-style-type: none">1. Click Upload to select a file on your PC to begin a high-speed upload.  Note - You must have the Aspera Connect high-speed plug-in to use this option. If it is not already installed on your computer, click the link on the tab to access the download file.2. Optionally, type the expected MD5 checksum value.



Note - For MD5 checksums, the value must be a 32 character hexadecimal value. When you enter a value in this field, the Producer Portal checks that the file it received has the same checksum as the value you enter.

The Producer Portal initiates the file image upload process and returns to the **View File** page for the current file. Once the upload is complete and successful, the file is available for end users to download (provided the file is properly associated to products and download packages to which the end user is entitled).



Note - It is possible to upload files without using the Producer Portal. For example, files can be uploaded via web services to automate the process or upload files into FlexNet Operations from your account's system.

See Also

[Adding Files](#)

[About Files and File Images](#)

Deleting a File Image

You can delete a file image previously uploaded for a file from the file's **View File** page.



Note - This action is only available when the delivery source is **FlexNet Operations**.



Task **To delete a file**

1. On the **View File** page, click **Edit** > **Delete File Image**. This link opens the Delete File Image page.
2. Click **Delete**.

The Producer Portal deletes the file image and returns to the **View File** page for the current file.

See Also

[Viewing File Information](#)

[Adding Files](#)

[About Files and File Images](#)

Reidentifying a File

You can change the file ID of an existing file from that file's **View File** page.

A file might have to be reidentified if it was entered in error, or if your account wants to change its file ID naming conventions.



Task **To reidentify a file**

1. On the **View File** page, click **Edit** > **Reidentify**. This link opens the Reidentify File page.
2. In the **File ID** field, type a new file ID value.

3. Click **Reidentify**.

The Producer Portal changes the file ID of the current file and returns to the file's **View File** page. Other file details are preserved, including relationships with the original file's aliases as well as its associated download packages.

See Also

[Adding Files](#)

[About Files and File Images](#)

Restricting a File

You can restrict access to a file in the Producer Portal for the users of designated accounts. Files are not restricted by default. When you restrict access to a file, you use a search function to locate and identify the account for which you want to grant or deny file access.



Note - When no accounts are listed on a file's **Restrict File** page, access to the file is not restricted. See [About File Restrictions](#) for more information about how the file restriction process works.



Task

To set file restrictions

1. On the **View File** page, click **Edit > Restrict**. This link opens the **Restrict File** page.
2. Type search criteria and click **Search Accounts**. The Producer Portal opens the **Find an Account** page in a pop-up window. This page shows a list of accounts that match your search criteria.
3. On the **Find an Account** page, click **Restrict Allow** or **Restrict Deny** for an account.
 - If you choose **Restrict Allow**, only the accounts you choose are permitted to access the file.
 - If you choose **Restrict Deny**, the accounts you choose are expressly denied access to the file.

The Producer Portal closes the **Find an Account** window and returns to the **Restrict File** page.

The **Restrict File** page shows the account you chose in the **Accounts Restricted to File** list.



Tip - To remove an account from the **Accounts Restricted to File** list, select the account's check box in the **Remove this Account** column and then click **Remove Selected Accounts**.

See Also

[Viewing File Restrictions](#)

[Restricting a File](#)

[About Files and File Images](#)

Creating an Email Notification for a File

You can create an email notification for the download packages that include the current file. (You cannot create an email notification for a file that is not associated with a download package.)



Task *To create a notification email for a file*

1. On the **View File** page, click **Edit > Notify**. This link opens the **Create Notification Email by File** page, which lists the download packages with which the file is associated.
2. In the **Download Packages and Files** list, select the check box for the download packages for which you want to create the notification email.
3. Click **Create**. The **Create Notification Email by File** page shows **Distribution List Options** and **Choose an Email Template** sections.
4. Set Distribution List Options for the notification email message.

Setting	Description
Effective Date	The first date (inclusive) that this email notification is available to entitled end users.
Include Expired Entitlements	Determines whether or not to include expired entitlements in the distribution list. By default, only users with active entitlements are included in the distribution list.
Download Status	Limits message delivery according to whether the file has been downloaded: <ul style="list-style-type: none"> ● All users—Deliver to all entitled users regardless of whether they have downloaded the file. ● Users with Download Activity—Deliver to entitled users who have downloaded the file. ● Accounts with Download Activity—Deliver to entitled users who are part of an account in which at least one user has downloaded the file.
Exclude Email Filters	Allows you to identify specific email addresses or email address ranges to exclude from the distribution list. For a single address, type the address in the space provided. For multiple addresses, add a comma-separated list of email addresses in the space provided. Use an asterisk as a wildcard to exclude ranges of email addresses. For example, *@yourdomain.com, *.edu .
Limit to Countries	Restricts the delivery of notifications to countries identified by their two-character country code. Use a comma-separated list of country codes to permit delivery to multiple countries. For example, specifying US,FR permits notification delivery to users in the United States and France. When no country codes are specified, FlexNet Operations places no notification delivery restrictions based on the recipient's country.
Send Separate Email for Each Download Package	Determines whether to send a single message for all download packages (when multiple download packages have been selected) or to send a separate message for each download package.

Setting	Description
Send Email Immediately	Determines whether the message is sent as soon as it is created or sent later. By default, Send Email Immediately is not selected, and email notifications are queued for sending. If you select this check box, the Producer Portal sends the message as soon as you click the Create button. Do not use this option if you want to modify the message before it is sent.

5. **Choose an Email Template** variation for this message.

File notification messages use the Update Notification Email template. Select any active variation of that template for the file notification message.



Tip • You can manage your email templates in the Producer Portal. For more information about email templates, see [Managing Email Templates](#).

6. Click **Create**. The Producer Portal creates the email message for the files you specified, uses the settings you provided, and shows the **View Email** page.
7. On the **View Email** page, click **Edit** > **Send Email**. The Producer Portal opens the **Send Email** page.
8. On the **Send Email** page, choose to send the email or schedule its delivery.
 - To send immediately, click **Send**.
 - To schedule delivery for a later date,
 1. Click **Queue to be sent at**.
 2. Set the Send Date.
 3. Specify the Send Time (24-hour format).
 4. Click **Send**.

The Producer Portal sends the email notification.



Note • For more information about managing email messages and email templates, see [Managing Email and Email Templates](#).

See Also

[Viewing Emails Related to a File](#)

[Creating an Email Notification for a Download Package](#)

Managing File Associations

The files you add to the Producer Portal can be associated with or disassociated from download packages on the file's **View File** page.

Users typically search for a file they want to view and then click that file's name in the search results to open the **View File** page. The Associate menu on the **View File** page includes commands for adding and removing file-download package associations. With the commands in the Associate menu, you can perform the following tasks.

Table 2-37 ▪

Topic	Description
About File Associations	Discusses the relationships you can create between files, download packages, and products and addresses the use of Associate Where in more detail.
Associating a File to Download Packages	Explains how to build relationships between a file and one or more download packages by specifying the download packages to associate with the file.
Using Associate Where to Copy Associations from Another File	Explains how to build relationships between a file and one or more download packages by copying the download package associations from one or more other files.
Disassociating a File from a Download Package	Explains how to remove a previously built relationship between a file and one or more download packages.

See Also

- [About Files and File Images](#)
- [Searching for Files](#)
- [Viewing Where a File Is Used](#)

About File Associations

A file can be associated with multiple download packages or with none at all. A file only appears in the End-User Portal within the download packages with which it has been associated. Therefore, you can control the visibility of a file and your customers' access to it (in part) by managing the file's associations with your download packages.

You can manage a file's download package associations from the file's **View File** page. There, you can see which download packages a file is associated to, make new associations, or remove existing associations. Use the following commands on the **View File** page:

- **View > View Where Used**—To see existing download package associations. See [Viewing Where a File Is Used](#).
- **Associate > Associate to Download Packages**—To make new download package associations. See [Associating a File to Download Packages](#).
- **Associate > Associate Where**—To make download package associations that match the associations from one or more existing files. See [Using Associate Where to Copy Associations from Another File](#).

Persistence of Associations

A file's download package associations remain even if the file is edited, reidentified, or if its file image is deleted.

Aliases behave just like separate files after they have been created with one exception: they always use the same file image as their original file. At creation time, an alias is a copy of the original file and includes its file associations and other file attributes. After it is created, any changes made to the alias apply only to the alias itself; they have no impact on the original file. Therefore an alias can be altered to have download package associations that differ from the original file.

The Association Where Command

Typically, simple download package associations can be quickly defined using the **Associate to Download Packages** command—explicitly specifying one or more download packages. In some cases, though, it may be cumbersome to itemize all the download packages to which you want this file associated. **Associate Where** is a shortcut that copies the download package associations of another file. That is, the Producer Portal associates the current file with all the download packages with which another file is already associated.

See Also

[Viewing Where a File Is Used](#)

[Associating a File to Download Packages](#)

[Disassociating a File from a Download Package](#)

Associating a File to Download Packages

You can associate a file to one or more download packages from the file's **View File** page. The download packages to which you associate the file can be identified by their download package IDs, their system IDs, or located via a download package search.



Note - If your existing files have the same download package associations you want to make for the current file, it may save time to use the **Associate Where** command instead. See [Using Associate Where to Copy Associations from Another File](#).



Task **To associate a file to download packages**

1. On the **View File** page, click **Associate > Associate to Download Packages**. This link opens the **Associate File to Download Packages** page.
2. Identify the download packages to associate. Choose whether to enter download package IDs or to search for download packages:
 - Enter download package IDs when you already know the download package IDs or system download package IDs of the download packages you want to associate.
 - a. In the **Download Package IDs** field, type the download package IDs as a comma-separated list or enter them one per line. Note: If you enter system IDs, remember to select the **Use System IDs** check box.
 - b. Click **Associate Download Packages**.
 - Search for download packages by entering search criteria if you do not know the IDs of the download packages you want to associate.
 - a. Type your search criteria into the download package search fields.

- b. Click **Search**. The Producer Portal shows a list of download packages that match your criteria.
- c. Select the download packages to associate and click **Associate File to Selected Download Packages**.

The Producer Portal creates associations between the current file and the download packages you identified and opens the **Where File Used** page for the current file.

See Also

[About File Associations](#)

[Disassociating a File from a Download Package](#)

[Viewing Where a File Is Used](#)

Using Associate Where to Copy Associations from Another File

You can use the **Associate Where** command to quickly build associations between a file and a number of download packages by copying the associations of one or more existing files.

When you click **Associate Where**, the Producer Portal shows a file search page. If you know the IDs of the files from which you want to copy associations, you can enter them manually. If not, you can search for them based on their file attributes. (You can use an asterisk as a wildcard to search for and select the files from which to copy download package associations.)



Task **To associate a file with another file's download packages**

1. On the **View File** page, click **Associate > Associate Where**. This link opens the **Associate this File to Download Packages Where Other Files Are Found** page.
2. Identify the files from which to copy download package associations. Choose whether to enter file IDs, directly, or to search for files:
 - Enter file IDs when you already know the file IDs or system file IDs of the files from which you want to copy associations.
 - a. In the **File IDs** field, type the file IDs as a comma-separated list or enter them one per line. Note: If you enter system file IDs, remember to select the **Use System IDs** check box.
 - b. Click **Associate**.
 - Enter file search criteria if you do not know the IDs of the files you want to associate.
 - a. Type your search criteria into the file search fields.
 - b. Click **Search**. The Producer Portal shows a list of files that match your criteria.
 - c. Select the download packages to associate and click **Associate to Download Packages of Selected Files**.

The Producer Portal creates associations based on the download package associations of the files you identified and opens the **Where File Used** page for the current file. All download packages associated with the files you identified are now also associated with the current file.



Note • The **Associate Where** function updates all download packages that contain the files you identified.

See Also

[About File Associations](#)
[Associating a File to Download Packages](#)
[Viewing Where a File Is Used](#)

Disassociating a File from a Download Package

You can remove associations between a file and one or more download packages from the **View File** page. You might need to disassociate a file from a download package to replace it with a new version of the file for a hotfix or to correct a file-download package that had been made in error.



Note - Remember that a file must be associated with a download package for it to appear in the End-User Portal. Therefore, you can effectively cease distribution of an existing file by disassociating it from all download packages.



Task **To disassociate a file from a download package**

1. On the **View File** page, click **Associate > Disassociate from Download Packages**. This link opens the **Disassociate this File from Download Packages** page.
2. Choose the download packages to disassociate and click **Disassociate from Selected Download Packages**.

The Producer Portal removes associations from the selected download packages and refreshes the **Disassociate this File from Download Packages** page to show the current file-download package associations, if any.



Tip - If a file is associated with multiple download packages and you intend to remove all download package associations, you can skip the step in which you choose the download packages and just click **Disassociate from All Download Packages**.

See Also

[About File Associations](#)
[Associating a File to Download Packages](#)
[Viewing Where a File Is Used](#)

Managing License Agreements

Producers can use the Producer Portal to create license agreements to show to their users in the End-User Portal. On the End-User Portal, users must accept the terms of the agreement before they are permitted to access your download packages.



Tip - For the instructions in this section, it is expected that you are working on the Producer Portal with sufficient privileges/permissions to perform the tasks described.

End-user license agreements (EULAs) can be defined by Producer Portal users and are related to product lines and download packages. A license agreement commonly contains content supplied by your legal department. End-users are prompted to agree to the terms before proceeding to the download page. The agreement is an attribute of a download package.

Table 2-38 •

Topic	Description
About Agreements	Discusses agreements and their use in FlexNet Operations.
Listing Agreements	Shows how to list your account's agreements.
Creating an Agreement	Explains how to add an agreement to FlexNet Operations.
Viewing an Agreement's Transactions	Describes how to display a transaction history list for a selected agreement.
Editing an Agreement	Shows how to change an agreement's name or content.

See Also

[About Download Management and FlexNet Electronic Software Delivery](#)

About Agreements

In FlexNet Operations, producers can add agreements that can be tied to one or more download packages.

A click-through or end-user license agreement (EULA) commonly contains content supplied by your legal department. The license agreement is an optional attribute of a download package.

In the Producer Portal, producers add agreements by providing an agreement name and the content for the agreement text. (The agreement content can be plain text or HTML.) Then, the agreement can be linked to a download package on the **Edit Download Package** page.

When an agreement is connected to a download package, the End-User Portal prompts users to agree to the terms of that agreement before proceeding with the download.



Note • *Once created, a license agreement cannot be deleted. To ensure an existing license agreement is not shown in the End-User Portal, you must remove any references to it in your download packages. (On the **Search Download Packages** page, you can search for download packages by their license agreement.)*

See Also

[About Download Management and FlexNet Electronic Software Delivery](#)

[Creating an Agreement](#)

[Managing License Agreements](#)

Listing Agreements

You can show a list of your account's agreements in the Producer Portal.



Task **To list agreements**

- Click **Products** > **List Agreements**.

The Producer Portal shows a list of agreements in a table. There you can see the agreement's ID and name. Click an agreement ID to see its **View Agreement** page.

See Also

[Creating an Agreement](#)
[About Agreements](#)

Creating an Agreement

You can create an agreement, such as an end-user license agreement (EULA) or a support agreement, on the Producer Portal.



Task **To create an agreement**

1. Click **Products** > **Create Agreement**. This opens the Add Agreement page.
2. Type an **Agreement Name**.
3. Type the content for the agreement in **Agreement Content**.



Note ▪ The Producer Portal accepts HTML content and plain text as input for Agreement Content.

4. Click **Save**.

The Producer Portal saves the agreement. This agreement is now available for use in download packages.

See Also

[Creating a Download Package](#)
[About Agreements](#)

Viewing an Agreement's Transactions

You can see the transaction history of an agreement from its **View Agreement** page. Transactions are recorded when an agreement is created or edited.



Task **To view transactions related to an agreement**

- On the **View Agreement** page, click **View** > **Transactions**.

The Producer Portal opens the **Search Results: Transactions** page with a list of all the transactions that have occurred for the current agreement. You can view details about a listed transaction by clicking its transaction ID.

See Also

[Creating an Agreement](#)
[About Agreements](#)

Editing an Agreement

You can change the name of an existing agreement on its **View Agreement** page.



Task

To edit an agreement

1. On the **View Agreement** page, click **Edit > Edit this Agreement**. This opens the **Edit Agreement** page.
2. Edit the **Agreement Name**.
3. Click **Save**.

The Producer Portal saves the agreement with the new name you provide. The agreement name is the display name shown to your users in the End-User Portal.

See Also

[Creating an Agreement](#)
[About Agreements](#)

Managing Producers

Producers can be created, modified, deactivated, and reactivated on the Producer Portal. The following topics provide information about producers and instructions on how to manage them.

Table 2-39 •

Topic	Description
About Producers	Discusses how producers are used in the Producer Portal and how they appear to End-User Portal users.
Listing Producers	Shows how to display all producers.
Creating a Producer	Explains how to add a producer.
Viewing a Producer's Transactions	Explains how to view the transaction history of a selected producer.
Editing a Producer	Describes how to change a producer's name.
Reidentifying a Producer	Describes how to use the Reidentify command to change a producer's ID.
Deactivating a Producer	Shows how to change an active producer's status to Inactive.

Table 2-39 -

Topic	Description
Reactivating a Producer	Shows how to change a deactivated producer's status back to Active.

See Also

[About Download Management and FlexNet Electronic Software Delivery](#)

About Producers

A producer typically identifies an account that creates the software presented for download on the End-User Portal. You can create any number of producers your account requires. To facilitate the creation of download packages, you must have at least one producer, as it is a required attribute of download packages.

Many companies only use a single producer. Others use the Producer attribute to distinguish between different product groups or families. When you click **List Producers** in the **Products** menu, the Producer Portal displays a list of all the producers your account has created. Click a producer name to view the producer information, and if necessary, modify it.

On the End-User Portal, the producer acts as the top level category for the files your users can download. Users who are entitled to products of more than one producer see a list of producers when they look for downloads. For example, users who click **Downloads > List All** in the End-User Portal must first choose from a list of producers and then from a list of product lines and then product versions to show a list of download packages. So, in normal situations, the producer serves only as a method of grouping products, download packages, and files for display on the End-User Portal.

See Also

[About Download Management and FlexNet Electronic Software Delivery](#)

[Listing Producers](#)

[Creating a Producer](#)

Listing Producers

You can show a list of producers on the Producer Portal.



Task

To list producers

- Click **Products > List Producers**.

The Producer Portal shows a list of producers in a table. There you can see the producer's ID, name, and status. Click a producer ID to see its **View Producer** page.

See Also

[Creating a Producer](#)

[Deactivating a Producer](#)

[About Producers](#)

Creating a Producer

You can create a producer on the Producer Portal.



Task **To create a producer**

1. Click **Products > Add Producer**. This opens the **Add Producer** page.
2. Type a **Producer ID**.
3. Type a **Producer Name**. This value is what the End-User Portal shows to your users when they are choosing among producers.
4. Click **Save**.

The Producer Portal saves the producer with the ID and name you provide and shows the **List Producers** page. This producer is subsequently available as an option for setting a producer when you create or edit a download package.



Note - New producers are automatically set to Active status.

See Also

[Creating a Download Package](#)
[About Producers](#)
[Managing Producers](#)

Viewing a Producer's Transactions

You can see the transaction history of a producer from its **View Producer** page. Transactions are recorded when a producer is created, edited, or reidentified, and when its status is changed.



Task **To view transactions related to a producer**

- On the **View Producer** page, click **View > Transactions**.

The Producer Portal opens the **Search Results: Transactions** page with a list of all the transactions that have occurred for the current producer. You can view details about a listed transaction by clicking its transaction ID.

See Also

[Creating a Producer](#)
[About Producers](#)
[Managing Producers](#)

Editing a Producer

You can change the name of an existing producer on its **View Producer** page.



Note - You cannot change the producer ID on the **Edit Producer** page. To change the ID value, you must use the **Reidentify** command. See [Reidentifying a Producer](#).



Task **To edit a producer**

1. On the **View Producer** page, click **Edit > Edit this Producer**. This opens the **Edit Producer** page.
2. Edit the **Producer Name**.
3. Click **Save**.

The Producer Portal saves the producer with the new name you provide. The producer name is the display name shown to your users in the End-User Portal.

See Also

[Reidentifying a Producer](#)
[About Producers](#)
[Managing Producers](#)

Reidentifying a Producer

Reidentifying a producer is how you change its producer ID. This is a separate process from editing a producer.



Task **To reidentify a producer**

1. On the **View Producer** page, click **Edit > Reidentify**. This opens the **Reidentify Producer** page.
2. Edit the **Producer ID**.
3. Click **Reidentify**.

The Producer Portal saves the producer with the new ID value you provide and shows the **List Producers** page.

See Also

[Editing an Agreement](#)
[About Producers](#)
[Managing Producers](#)

Deactivating a Producer

You can deactivate an active producer from its **View Producer** page. All newly created producers start out with Active status.



Task **To deactivate a producer**

1. On the **View Producer** page, click **Edit > Inactivate**. This opens the **Inactivate Producer** page.
2. Click **Inactivate**.

The Producer Portal changes the producer's status to Inactive.

See Also

[Creating a Producer](#)
[Reactivating a Producer](#)
[About Producers](#)

Reactivating a Producer

You can reactivate an inactive producer from its **View Producer** page.



Task **To reactivate a producer**

1. On the **View Producer** page, click **Edit > Reactivate**. This opens the **Reactivate Producer** page.
2. Click **Reactivate**.

The Producer Portal changes the producer's status to Active.

See Also

[Creating a Producer](#)
[Deactivating a Producer](#)
[About Producers](#)

Entitling Customers and Activating Licenses

This section describes how to entitle customers to licenses and activate licenses.

Table 3-1 ▪

Topic	Description
Entitling Customers to Licenses	Defines entitlement terms and explains how to view entitlements, create entitlements, manage bulk operations, merge entitlements, and transfer entitlements.
Activating Licenses	Defines activation terms and describes how to view entitlements to activate, email entitlement line items, activate licenses, transfer entitlement line items, email licenses, perform manual activations, and manage short code activations.

Entitling Customers to Licenses

Entitling a customer to a license is the process of a software producer giving a customer account the right to obtain a license for a product:

- Identifying the customer account that is entitled to the product licenses
- Adding products for which the account is entitled to obtain licenses
- Associating an order ID and line item on that order with an entitlement line item (optional)
- Specifying values for license model attributes that are set at entitlement time

This section includes the following main topics.

Table 3-2 ▪

Topic	Description
Entitlement Terms	Defines terms related to entitlement.

Table 3-2 -

Topic	Description
Viewing Entitlements	Describes how to view entitlements.
Creating an Entitlement	Explains how to create an entitlement and configure entitlement line items and maintenance line items.
Creating a Bulk Entitlement	Describes how to create a bulk entitlement, configure a bulk entitlement line item, and manage web register keys.
Bulk Operations: Upgrade, Upsell, or Renew a Product	Discusses bulk upgrades, upsells, and renewals.
Verifying the Status of a Bulk Operation	Describes how to display the status of bulk operations in general, and of upgrade bulk operations using auto-fulfill for embedded licenses in particular.
Emailing Bulk Operation Notifications	Describes how to initiate the sending of email notifications for bulk operations.
Merging Entitlements	Explains how to merge entitlements.
Transferring Entitlements	Explains how to transfer entitlements.
Viewing Fulfillment History	Describes how to view fulfillment history of a line item.
Viewing Entitlement History	Describes how to view the transaction history of an entitlement.

Entitlement Terms


The following terms are referred to when entitling customers to licenses:

- [What is an Entitlement?](#)
- [What is an Entitlement Line Item?](#)
- [What is an Upgrade?](#)
- [What is a Test Upgrade?](#)
- [What is an Upsell?](#)
- [What is a Test Upsell?](#)
- [What is a Renewal?](#)
- [What is a Test Renewal?](#)
- [What is a Merge?](#)

- [What is a Transfer?](#)

What is an Entitlement?

An entitlement represents your customers' rights to use your software. An entitlement acts as a container for the licenses purchased in a single order. It is analogous to a bank account: an entitlement contains rights to one or more licenses, and the customer can redeem licenses from or return licenses to this account. The figure below depicts the relationships among entitlements, customers, and line items.



Entitlements are created through the Producer Portal or imported using the Entitlement Order Web service. Entitlements are associated with:

- Multiple tiers of an account
- One or more products

See Also

[Viewing Entitlements](#)

[Creating an Entitlement](#)

[Creating a Bulk Entitlement](#)

What is an Entitlement Line Item?

Each line item in an entitlement is an activatable unit and has an activation ID.

The details of an entitlement line item specify the product and its options, the quantity, and the duration of the license rights; for example, “15 copies of MyApplication and selected options for two years.”

See Also

- [Viewing Entitlements](#)
- [Creating an Entitlement](#)
- [Creating a Bulk Entitlement](#)

What is a Bulk Entitlement?

A Bulk Entitlement can be created when licenses are distributed through a reseller or channel. The producer creates a bulk entitlement for a single product and generates one or more Web register keys that each provides rights to one or more licenses. The reseller then gives one or more Web register keys to the consumer that purchases the software.

The consumer registers the software with the producer or manufacturer using the Web register key. This allows software producers and device manufacturers to track two pieces of information:


- who purchased the bulk entitlement (the reseller)
- who registered the license (the consumer)

In addition, the reseller can access the End-User Portal to view the bulk entitlements that they purchased, the Web register keys for these bulk entitlements that have not yet been allocated, and the Web register keys that were registered from these bulk entitlements.

What is an Upgrade?

A product is upgraded when a customer replaces an older version of the product with a newer version, such as moving from MyProgram Version 4.5 to MyProgram Version 5.0. The figure below depicts an upgrade of Product A from version 1.0 to version 2.0.

Product Relationships



To enable an upgrade in the Producer Portal, both versions of the product must have been added, and a relationship between them (such as **Upgrade To** or **Upgrade From**) must be defined on the **Relate to Different Products** page. Then, go to the **Entitle Customers** page and select Upgrade or Test Upgrade.



Tip - FlexNet Operations can automatically create upgrade line items for qualifying products and line items with the Product Version Upgrade job. See [FlexNet Operations Alert Types](#).

See Also

[Upgrade, Upsell, or Renew a Fulfillment](#)
[Bulk Operations: Upgrade, Upsell, or Renew a Product](#)

What is a Test Upgrade?

A test upgrade can be created using a draft product and draft license models for testing purposes. It remains in TEST state only. A test upgrade lets software producers and device manufacturers ensure that the products, license models, and relationships are defined properly before deploying them into production.

To enable a test upgrade in the Producer Portal, both versions of the product must have been added, and a relationship between them (such as **Upgrade To** or **Upgrade From**) must be defined on the **Relate to Different Products** page. You can then open the **Entitle Customers** page and upgrade the entitlement line item.




Tip ▪ FlexNet Operations can automatically create upgrade line items for qualifying products and line items with the Product Version Upgrade job. See [FlexNet Operations Alert Types](#).

See Also

[Upgrade, Upsell, or Renew a Fulfillment](#)
[Bulk Operations: Upgrade, Upsell, or Renew a Product](#)

What is an Upsell?

A product is upsold when a customer replaces the product with another product that provides a superset of the original's functionality, such as moving from the MyProgram Standard Edition to the MyProgram Professional Edition. The figure below depicts an upsell of Product A version 1.0 to Product B version 1.0.



To enable an upsell in the Producer Portal, both “editions” of the product must have been added, and a relationship between them (such as **Upsell To** or **Upsell From**) must be defined on the **Relate to Different Products** page.

See Also

[Upgrade, Upsell, or Renew a Fulfillment](#)
[Bulk Operations: Upgrade, Upsell, or Renew a Product](#)

What is a Test Upsell?

A test upsell can be created using a draft product and draft license models for testing purposes. A test upsell operation enables software producers and device manufacturers to ensure that the products, license models, and product relationships are defined correctly before deploying them into production. To define a test upsell entitlement, you can use draft products and license models.

To enable a test upsell in the Producer Portal, both “editions” of the product must have been added, and a relationship between them (such as **Upsell To** or **Upsell From**) must be defined on the **Relate to Different Products** page.

See Also

[Upgrade, Upsell, or Renew a Fulfillment](#)

[Bulk Operations: Upgrade, Upsell, or Renew a Product](#)

What is a Renewal?

A renewal is used when you want to extend the expiration date of a product’s original entitlement, or its version date, to a date further in the future. It is not necessary to define a relationship for a renew operation because the product involved does not change.

See Also

[Upgrade, Upsell, or Renew a Fulfillment](#)

[Bulk Operations: Upgrade, Upsell, or Renew a Product](#)

What is a Test Renewal?

A test renewal can be created for testing purposes. A Test Renewal operation lets software producers and device manufacturers use draft products and license models to renew entitlements. This ensures that products and license models are defined correctly before deploying them into production. It is not necessary to define a relationship for a renew operation because the product involved does not change.

See Also

[Upgrade, Upsell, or Renew a Fulfillment](#)

[Bulk Operations: Upgrade, Upsell, or Renew a Product](#)

What is a Merge?

If Company A acquires Company B and wants to move all license entitlements, fulfillments, and users belonging to Company B over to Company A, a Merge is used. Mergers of company license assets can be accomplished using the FlexNet Producer Portal and Web services.

See Also

[Merging Entitlements](#)

What is a Transfer?

If a company spins off a division and sets up a separate company, it can transfer some of its license entitlements to the new company by using the Transfer facility in the Producer Portal. Using Web services and the Producer Portal, the producer can transfer the entitlement, or one line item of an entitlement, to the new company. However, an entitlement can be transferred only if there are no active fulfillments against any of its line items. Unfulfilled copies of a line item can be transferred to a different company or entitlement.

See Also

[Transferring Entitlements](#)

[Transferring Entitlement Line Items](#)

Viewing Entitlements

The **List Entitlements by Order** page displays entitlements. To view all entitlements, select **Entitlement ID** from the **Search for** drop-down, and click the **Simple Search** icon. You can also search for entitlements based on specific criteria by

- Specifying some particular values in the simple search, like **Entitlement ID Starts With**
- Clicking **Advanced Search**, which lets you specify multiple search attributes.



Tip ▪ When an entitlement has been upgraded, upsold, or renewed, the *Map Entitlements* page shows only the most recent entitlement in its lifecycle chain. Earlier entitlements are grouped under the most recent entitlement but initially hidden. These entitlement groups have a **Show Upgrades** button to reveal earlier entitlements in the list.

From this page, you can:

Table 3-3 ▪ Viewing Entitlements

Action	Description
Edit an entitlement	To edit an entitlement, click its entitlement ID. This opens the entitlement's Create an Entitlement (or Create a Bulk Entitlement) page.
Add a new entitlement	To add a new entitlement, click Add > Add entitlement .
Add a new bulk entitlement	To add a new bulk entitlement, click Add > Add bulk entitlement .
Copy	To create a copy of an entitlement, select one entitlement and click Add > Copy . A new entitlement is created. Copies of all line items in the selected entitlement are also created.
Transfer	To transfer an entitlement to a different company, select the entitlement and click Transfer .

Table 3-3 ▪ Viewing Entitlements


Action	Description
<p>Change the state of an entitlement</p>	<p>To change the state of one or more entitlements, select the entitlements, click the Change state drop-down, and select a state. Entitlements can be in one of the following states: Draft, Deployed, Test, Inactive, or Obsolete.</p> <ul style="list-style-type: none"> ● Draft: Draft entitlements can be created only from deployed products and suites. ● Deployed: Deploying a draft entitlement automatically deploys all line items on the entitlement and allows the line items to be activated, upgraded, upsold, or renewed. Line items added to a deployed entitlement must be manually deployed before they can be activated. ● Inactive: If an entitlement is made inactive, all of the line items in the entitlement are made inactive and cannot be activated, upgraded, upsold, or renewed. Existing fulfillments against an inactive line item cannot be returned, repaired, or rehosted. ● Obsolete: An entitlement can be made obsolete if it is no longer required or it was created and deployed in error. An obsolete line item cannot be fulfilled. Fulfillments of an obsolete entitlement line item cannot be rehosted. ● Test: Test entitlements cannot be changed to any other state. They can be created from draft products and suites. Test entitlement line items can be activated, upgraded, upsold, renewed, or deleted. Test fulfillments created from test entitlements can be returned, repaired, rehosted, and deleted. <p></p> <p>Note ▪ An entitlement that has been activated on a device can have its state changed to Inactive or Obsolete only if the configuration option Allow used entitlement/line item state change to Inactive or Obsolete is selected.</p> <p>When this configuration option is selected, an entitlement or line item that has been activated on a device can still be used until the license expires, even if the entitlement or line item has been deactivated or made obsolete.</p> <p>For more information, see General Options in Configuring System Settings.</p>
<p>Activate licenses for an entitlement</p>	<p>To activate licenses for an entitlement, select the entitlement and click Activate. The activatable line items on the entitlement are displayed.</p>
<p>Delete an entitlement</p>	<p>To delete an entitlement, select one or more entitlements and click Delete.</p>

Table 3-3 • Viewing Entitlements

Action	Description
Export entitlement(s)	To export an entitlement or entitlements, click Export and select an export option from the drop-down menu. Options displayed on the drop-down menu are controlled by a user's Export and Import permission. Users without Export and Import permission see only data export options with low impact, such as Selected Items , on an entity's Export drop-down menu. Users with Export and Import permission see the complete list of data export options, including those with high impact, such as All Items .
Print an entitlement	To print an entitlement, select one or more entitlements and click Print .

Creating an Entitlement

In the **Entitle Customers** view, you can create a new entitlement or test entitlement.

Test entitlements allow testing of draft products and license models before they are deployed. All entitlement actions can be performed on test entitlements, but test entitlements cannot be moved to any other state. When a test entitlement is deleted, any fulfillments against it are also deleted. (The fulfillment records in FlexNet Operations *are* deleted; however, any client-side fulfillment records created in trusted storage as a result of the activation of a test entitlement *cannot* be deleted.)



Task

To create a new entitlement

1. Click **Entitlements > Create**. This link opens the **Create an Entitlement** page. (Click **Entitlements > Create Test** to create a test entitlement.)
2. Required fields are indicated by a red asterisk. Provide values for the following fields:

Table 3-4 • Creating an Entitlement Fields

Field	Description
Entitlement ID	The entitlement identifier uniquely identifies the entitlement. Select Auto Generate to let FlexNet Operations assign an entitlement ID, or select Specify to enter an entitlement ID of your choice. If the entitlement is in the draft or test state, you can regenerate the activation IDs of draft line items or the entitlement ID by clicking Regenerate IDs . If the IDs are based on characteristics of the entitlement that were not set when the entitlement was created, you can use Regenerate IDs to regenerate these IDs after you have set the characteristics.
Allow Portal Login?	If Yes is selected, the end customer can use the entitlement ID or activation ID to log into the End-User Portal.

Table 3-4 ▪ Creating an Entitlement Fields

Field	Description
State	An entitlement is created in a draft or test state. Entitlements in draft or test states can be modified or deleted. When the entitlement is ready for use, it can be changed to a deployed state. See Viewing Entitlements for more information about changing the state of an entitlement.
Description	A brief, optional description of the entitlement.
Ship to email	Email address that FlexNet Operations sends the license to.
Ship to mail	Postal address that FlexNet Operations sends the license to.
Email Template variation	Optional. Select an email template from the drop-down menu. If not specified, then the email template configured for the license technology is used. If there is no email template configured for the license technology, then the default email template is chosen. If the chosen template is not active or the send indicator is not switched on, no email is sent.
Channel Partners	Under End Customer and Channel Partners : <ol style="list-style-type: none"> 1. Click Add to assign a channel partner to the entitlement. 2. On the Channel Partner page, select a Distribution Tier Type for the partner. 3. Under Accounts, select the partner account. Click Next. 4. Under Contacts, select a contact to assign to the entitlement. 5. Click Save.

3. Configure line items and maintenance line items for this entitlement.

- To configure a new line item, click the **Line Items** tab. Then, click **New line item**. See [Configuring an Entitlement Line Item](#).
- To configure a new maintenance line item, click the **Maintenance Line Items** tab. Then, click **New Maintenance Line Item**. See [Configuring a Maintenance Line Item](#).

Existing line items and maintenance line items can be linked:

- To link to an existing line item to one or more existing maintenance line items, click the **Line Items** tab, and select a line item. Then, click **Link Maintenance Line Items**. Select one or more maintenance line items and click **Save**.
- To link an existing maintenance line item to one or more existing line items, click the **Maintenance Line Items** tab, and select a maintenance line item. Then, click **Link Line Items**. Select one or more line items and click **Save**.

For each entitlement line item, it is possible to [show its fulfillment history](#) and transaction history.

See Also

- [Configuring an Entitlement Line Item](#)
- [Configuring a Maintenance Line Item](#)
- [Changing the State of a Line Item](#)
- [Deleting an Entitlement Line Item](#)

Configuring an Entitlement Line Item

When you click **New line item** on the **Create an Entitlement** page, FlexNet Operations opens the Configure Line Item wizard in a pop-up window. Continue configuring the settings for each entitlement line item.

See also the following subtopics:

- [Editing an Activation ID](#)
- [Automatic Renewal of Line Items](#)



Task

To configure an entitlement line item

1. **Select Product:** Select a product for the line item. You can select multiple products if they have a common license model assigned. Click **Next**.
2. **Select Part Number and License Model:** Enter values for the following, then click **Next**.
 - The entitlement's part number, if any.
 - Select a license model from the drop-down list, then specify any entitlement-time license model attributes. (Attributes from all license models are displayed.)
 - For FlexNet licensing technologies, an entitlement line item can contain, at most, 1 certificate, 1 trusted storage, and 1 embedded license model. The same line item can be activated using a certificate license, trusted storage activation request, or embedded activation request from a hardware device.
 - Optionally, set the Notice value (customer name and Purchase order number) and Serial Number of the license.
3. **Configure Product:** Enter values for the following, and then click **Next**.
 - **Quantity Per Copy:** Quantity per copy of each line item. This is a multiplier. So, for example, if one copy of the line item is fulfilled, the specified quantity of the product is shown in the license.
 - **Description:** enter a brief description of the product line item.
 - **Order ID:** enter the order ID. (This may be imported from your CRM/ERP application.)
 - **Order Line Number:** enter the order line number. (This may be imported from your CRM/ERP application.)
 - **Qty:** specify the number of copies for the entitlement.
 - **Start Date:** The start date of the entitlement line item is the start date of the licenses that are generated against the line item. Select a start date option from the drop-down list:
 - **Specify at each activation:** (not available for FlexNet Embedded licensing) the user is prompted to specify a start date each time the line item is activated. Each fulfillment record gets a new start date, and for duration-based entitlements, each fulfillment record's expiration date is set to start date specified + duration.

- **Specify value now:** select the start date value now. All fulfillment records of this line item get this start date. To specify a start date, click the **Calendar** next to the **Start Date** field and select a date.

If the year that you want to set is not currently available from the date picker, select the year that is closest to the desired year. This automatically increases the list by 10 years from the year you selected.
- **Use first activation date:** the date of the first activation is used as the start date. All fulfillment records for this line item get the same start date.
- **Specify at first activation:** (not available for FlexNet Embedded licensing) the user is prompted to specify a start date when first activating the line item. This start date is used for all fulfillment records.
- **Use each activation date:** every time the line item is activated, the activation date is used as the start date. Each fulfillment record gets a new start date. As a result, for duration-based entitlements, each fulfillment record's expiration date is set to activation date + duration.

- **Expiration:** Specify when the line item expires.

- **Permanent:** the line item never expires.
- **Specify Expiration Date:** the line item expires at midnight at the start of the indicated date.

Example: If the expiration date is set to 31-jan-2023, the assumed expiration time is 00:00:00. This means that the license is valid until **30-Jan-2023 23:59:59** (24-hour format).

Note: If you select this option, you **must** specify an expiration date. Otherwise, saving the entitlement fails.

If the year that you want to set is not currently available from the date picker, select the year that is closest to the desired year. This automatically increases the list by 10 years from the year you selected.

- **Specify Duration:** the line item is valid for this period of time after activation.

Note that if this entitlement line item is delivering usage, then setting or changing the expiration date to a date in the past does not propagate to the usage functionality. This means that the entitled count does not reflect in the usage report user interface. Usage does not allow changes to the past. In this case, the earliest you can set the expiration date to is today.

4. **Renewal:** Select the check box if the line item should be automatically renewed. The **Renewal Expiration** field is displayed, where you can select one of the following options:

- **Specify Expiration Date:** Use the date picker or type the date when the line item should expire after it's been renewed.
- **Specify Duration:** Set the duration after which the line item expires after it's been renewed.

The renewal expiration date is calculated based on the line item's expiration date. For example, if the line item is set to expire on **May 20, 2025**, and the renewal expiration is set to a duration of **1 month**, the line item's expiration will be extended by 1 month, with a renewal expiration date of **June 20, 2025**.



Important - For the line items to be automatically renewed, you must also activate the Line Item Auto Renewal job. For more information, see [Automatic Renewal of Line Items](#), below, and [FlexNet Operations Alert Types](#).

5. **Order Type:** select an order type from the drop-down list: Upsell, Upgrade, Renewal, or New. For Upsells, Upgrades and Renewals, if the parent line item is being upgraded, specify it here.
6. Click **Save** or **Complete** to save the entitlement line item.

An entitlement line item is created as a draft or a test that can be modified. After a draft entitlement is deployed to allow activation, existing line items cannot be modified. After an entitlement is saved, the history of its state change can be viewed by clicking **View History**.

Editing an Activation ID

You can edit a line item's activation ID as long as the line item is in Draft state. On the **Create an Entitlement** page, under **Line Items**, click in the **Activation ID** field to edit it. The activation ID must fulfill the following requirements:

- Maximum 255 characters
- Must not be empty
- Must be unique
- Invalid characters:

, " & % ^ () # @ ! ~ / < > ` } { = | .

Automatic Renewal of Line Items

Line items that are marked for auto-renewal can have their expiration date automatically renewed by the Line Item Auto Renewal job. This might be beneficial for producers who know in advance that a customer will renew their line items. On the day of expiration, the line item's expiration date is extended to the new end date or duration set for the line item. For a line item to be automatically renewed, you need to do the following:

- Select the line item's **Renewal** check box and set its renewal date. You do this in the Configure Line Item Wizard in the **Configure Product** section (see [Step 4](#), above).
- Activate the Line Item Auto Renewal job and configure its schedule. For more information about the job and how to configure it, see [FlexNet Operations Alert Types](#) and [Configuring Alert Behavior](#), respectively.

Considerations

- Permanent entitlement line items and permanent maintenance line items will not be automatically renewed.
- The Line Item Auto Renewal job renews line items that have already expired, line items that will expire on the same day and line items that expire on the next day that the job runs.
- A line item cannot have a renewal date that is earlier than its expiration date.
- The Line Item Auto Renewal job only renews deployed line items. Line items with any other status are not renewed.

See Also

[Changing the State of a Line Item](#)
[Creating an Entitlement](#)
[FlexNet Operations Alert Types](#)

Configuring a Maintenance Line Item

When you click **New maintenance line item** on the **Create an Entitlement** page, FlexNet Operations opens the Configure Line Item wizard in a pop-up window. Continue configuring the settings for maintenance line items. You configure maintenance line items using the Configure Line Item wizard.

A maintenance line item must be linked to one or more product line items for it to be effective during bulk operations.



Task **To configure a maintenance line item**

1. Select Maintenance: Select a maintenance product for the line item. Click **Next**.
2. Configure Maintenance: Enter values for the following, and then click **Next**.
 - Part Number, if any.
 - Description: enter a brief description of the product line item.
 - Order ID: enter the order ID. (This may be imported from your CRM/ERP application.)
 - Order Line Number: enter the order line number. (This may be imported from your CRM/ERP application.)
 - Number of Copies: specify the number of copies for the entitlement.
 - Start Date: The start date of the entitlement line item is the start date of the licenses that are generated against the line item.



Note ▪ If the year that you want to set is not currently available from the calendar, select the year that is closest to the desired year. This automatically increases the list by 10 years from the year you selected.

- Expiration: Specify when the line item expires.



Note ▪ If the year that you want to set is not currently available from the calendar, select the year that is closest to the desired year. This automatically increases the list by 10 years from the year you selected.

3. Click **Save** or **Complete** to save the maintenance line item.

See Also

[Changing the State of a Line Item](#)
[Creating an Entitlement](#)

Changing the State of a Line Item

You can change the state of entitlement line items and maintenance line items on an existing entitlement's **Create an Entitlement** page. (In the **Entitle Customers** view, click on an entitlement ID to see that entitlement's **Create an Entitlement** page.)

There are five possible states for a line item:

- **Draft:** An entitlement line item is created and can be edited in the draft state.

- **Deployed:** An entitlement line item must be deployed to be activated. Deploying a draft line item allows it to be activated, upgraded, upsold, or renewed.
- **Inactive:** Existing fulfillments against an inactive entitlement line item cannot be returned, repaired, or rehosted. Inactive line items can be changed back to a deployed state as necessary.
- **Test:** Test entitlement line items can be defined for draft products and license models. This helps the producer ensure that products and license models are defined correctly.
- **Obsolete:** An entitlement line item can be made obsolete if it is no longer required, or it was created and deployed in error. An obsolete entitlement line item cannot be fulfilled. Fulfillments of an obsolete entitlement line item cannot be rehosted. The obsolete state is permanent, but the inactive state is not. After you make a line item obsolete, you cannot change it back to a deployed state.



Note - An entitlement that has been activated on a device can have its state changed to Inactive or Obsolete only if the configuration option **Allow used entitlement/line item state change to Inactive or Obsolete** is selected.

When this configuration option is selected, an entitlement or line item that has been activated on a device can still be used until the license expires, even if the entitlement or line item has been deactivated or made obsolete.

For more information, see [General Options in Configuring System Settings](#).



Task **To change the state of one or more entitlements**

1. On the **Create an Entitlement** page, click the tab for the type of line items you want to change.
 - For entitlement line items, click the **Line Items** tab (default).
 - For maintenance line items, click the **Maintenance Line Items** tab.
2. Click check boxes to select line items.
3. Click **Change State**, and then click the state you want to assign to the selected line items.
4. Click **OK** to confirm the state change.

See Also

[Configuring an Entitlement Line Item](#)

[Configuring a Maintenance Line Item](#)

Deleting an Entitlement Line Item

You can delete an entitlement line item if the following conditions are met:

- The entitlement line item is not mapped to a device.

If you want to delete a line item that is mapped to a device, you need to first remove the line item from the device.

- The entitlement line item is in Test, Draft, or Obsolete state.



Task **To delete an entitlement line item**

1. Open the entitlement that contains the line item that you want to delete.
2. Under **Line Items**, select the check box(es) for the line item(s) that you want to delete.
3. Click **Delete**.

Creating a Bulk Entitlement

If you want to create an entitlement for a single product against which multiple end users can generate licenses, create a bulk entitlement. A bulk entitlement can be sold to a retailer that distributes Web register keys to customers.

No licenses can be generated using the entitlement ID of a bulk entitlement; licenses are generated using one of the Web register keys associated with the entitlement. When a Web register key is redeemed, a simple entitlement is created with a configurable entitlement ID (default value is web_register_keyENT). Subsequent lifecycle operations are performed on the simple entitlement line item.

Follow the instructions, below, to create a bulk entitlement. Then, continue with the instructions in [Configuring a Bulk Entitlement](#) to add a product. Then, add one or more Web register keys by following the steps in [Loading Web Register Keys](#) or [Adding a Web Register Key](#).



Task **To create a bulk entitlement**

1. Click **Entitlements > Create Bulk**. This link opens the Create a Bulk Entitlement page. (Click **Entitlements > Create Test Bulk** to create a test bulk entitlement.)
2. Required fields are indicated by a red asterisk. Provide values for the following fields:

Table 3-5 ■ Creating an Entitlement Fields

Field	Description
Entitlement ID	<p>The entitlement identifier uniquely identifies the entitlement. Select Auto Generate to let FlexNet Operations assign an entitlement ID, or select Specify to enter an entitlement ID of your choice.</p> <p>If the entitlement is in the draft or test state, you can regenerate the activation IDs of draft line items or the entitlement ID by clicking Regenerate IDs.</p> <p>If the IDs are based on characteristics of the entitlement that were not set when the entitlement was created, you can use Regenerate IDs to regenerate these IDs after you have set the characteristics.</p>
State	<p>An entitlement is created in a draft or test state. Entitlements in draft or test states can be modified or deleted.</p> <p>When the entitlement is ready for use, it can be changed to a deployed state. See Viewing Entitlements for more information about changing the state of an entitlement.</p>

Table 3-5 ▪ Creating an Entitlement Fields

Field	Description
Description	A brief, optional description of the entitlement.
Ship to email	Email address that FlexNet Operations sends the license to.
Ship to mail	Postal address that FlexNet Operations sends the license to.
Channel Partners	Under Channel Partners, <ol style="list-style-type: none"> 1. Click Add to assign a channel partner to the entitlement. 2. On the Channel Partner page, select a Partner Tier for the partner. (Bulk entitlements are typically sold to a distributor. Thus, the values for End Customer and Tier1 partner are set to the same account for bulk entitlements.) 3. Under Accounts, select the partner account. (If necessary, a new account can be created.) Click Next. 4. Under Contacts, select a contact to assign to the entitlement. (If necessary, a new contact can be created.) 5. Click Save.

3. To configure a bulk entitlement, click **Add Product**. (See [Configuring a Bulk Entitlement](#).)

Configuring a Bulk Entitlement

When you click **Add Product** on the **Create a Bulk Entitlement** page, FlexNet Operations opens the Configure Line Item wizard in a pop-up window. Continue configuring the settings for this entitlement line item. You configure entitlement line items using the wizard.




Task

To configure a bulk entitlement

1. Under **Select Product**, select one or more products from the list. You can search for a product, a suite, or search for all products. Click **Next**.
2. **Specify Quantities:** For each product, enter the quantity to be included in each line item. Click **Next**.
3. **Select License Model:** Select one of the license models that is associated with the selected product. Only deployed license models appear in the drop-down list. Specify any entitlement-time license model attributes. The existing model is displayed, if one was previously assigned. In addition, custom attributes specified at entitlement time are shown here.

4. **Configure Product:** For each product, specify the following values:

Table 3-6 ▪ Select Product Fields

Field	Description
Description	Describe the characteristics of this entitlement that make it unique.
Start Date	<p>The start date of the entitlement is the start date of the licenses that are generated against the line item. Select a start date option from the drop-down list:</p> <ul style="list-style-type: none"> ● Use each activation date as start date: (not recommended for use with FlexNet Embedded licensing) every time the line item is activated, the activation date is used as the start date. Each fulfillment record gets a new start date. As a result, for duration-based entitlements, each fulfillment record's expiration date is set to activation date + duration. ● Specify at first activation: the user is prompted to specify a start date when first activating the entitlement. This start date is used for all fulfillment records. ● Use first activation date: the date of the first activation is used as the start date. All fulfillment records for this entitlement get the same start date. ● Specify at each activation: (not recommended for use with FlexNet Embedded licensing) the user is prompted to specify a start date each time the entitlement is activated. Each fulfillment record gets a new start date, and for duration-based entitlements, each fulfillment record's expiration date is set to start date specified + duration.
Expiration	<p>Specify when the entitlement expires.</p> <p>Permanent: the entitlement never expires.</p> <p>Specify Expiration Date: the entitlement expires on the indicated date.</p>  <p>Note ▪ If the year that you want to set is not currently available from the calendar, select the year that is closest to the desired year. This automatically increases the list by 10 years from the year you selected.</p> <p>Specify Duration: the entitlement is valid for this period of time after activation.</p>

5. After the bulk entitlement is configured, you can save it in its current state, go to the **Load Web Register Keys** page to add Web register keys to the bulk entitlement, or deploy it:

- Click **Save** or **Complete** to save the entitlement. This saves the bulk entitlement in a draft state to allow further editing. After an entitlement is saved, the history of its state change can be viewed by clicking **View History**.
- Click **Next** to load Web register keys into the bulk entitlement.
- Click **Deploy** to deploy a draft bulk entitlement. Deploying a bulk entitlement allows activation but, after deploying, a bulk entitlement's existing line items cannot be modified.

See Also

[Loading Web Register Keys](#)
[Creating a Bulk Entitlement](#)
[What is a Bulk Entitlement?](#)

Loading Web Register Keys

Each bulk entitlement has a set of Web register keys that end users use to turn on license rights for their software. Web register keys can be added in more than one set and can be added after the bulk entitlement is deployed.

The total number of Web register keys that were added to the entitlement and the number that were already activated are displayed.

Select **Auto Generate** to let FlexNet Operations create Web register keys for the specified number of copies, or select **User Supplied** to specify a file that contains Web register keys. (Web register keys can also be imported using a FlexNet Operations Web service.)



Important - Whether using the **Auto Generate** or **User Supplied** option, you must configure the alert, **Importing Bulk Entitlement Web Register Keys**, before loading Web register keys. This alert runs a job that periodically checks whether there are any Web register keys to import, and it can be configured to send an email with the status of the import. See [Configuring Alert Behavior](#) for instructions.



Note - To show the **Load Web Register Keys** page, open the **Create Bulk Entitlement** page for the bulk entitlement to which you want to add Web register keys and click **Next**.



Task

To load Web register keys

1. On the **Load Web Register Keys** page, choose either **Auto Generate** or **User Supplied**:
 - Select **Auto Generate** to automatically generate Web register key values. Then enter the number of Web register keys to generate for this entitlement.
 - Select **User Supplied** to supply Web register key, yourself, from an XML file. Then use the on-page controls to choose the XML file that contains the Web register key values. (See [Specifying User-Supplied Web Register Keys](#) for details about the format and syntax of the XML file.)

2. Click **Save** to submit the request to load Web register keys.

If the **Importing Bulk Entitlement Web Register Keys** alert is configured, FlexNet Operations processes the import request and notifies you of the status of the import request.

3. Click **Complete** when you are done creating or editing the bulk entitlement. The bulk entitlement must be deployed before any activations can be done against it.



Tip - To manually add individual Web register keys, follow the instructions in [Adding a Web Register Key](#).

See Also

[Specifying User-Supplied Web Register Keys](#)
[Creating a Bulk Entitlement](#)
[What is a Bulk Entitlement?](#)

Adding a Web Register Key

You can manually add web register keys, one by one, to an existing bulk entitlement.



Note ▪ To show the **Load Web Register Keys** page, open the **Create Bulk Entitlement** page for the bulk entitlement to which you want to add Web register keys and click **Next**.



Task **To add a web register key**

1. On the **Load Web Register Keys** page, click **Add**.
2. Enter the web register key and click **OK**. The web register key is added.
3. Click **Save**.



Tip ▪ To load several Web register keys at the same time, either from a user-supplied file or by allowing FlexNet Operations to automatically generate the Web register key values, follow the instructions in [Loading Web Register Keys](#).

See Also

[Deleting a Web Register Key](#)
[Creating a Bulk Entitlement](#)
[What is a Bulk Entitlement?](#)

Deleting a Web Register Key

You can delete web register keys from bulk entitlements.



Note ▪ To show the **Load Web Register Keys** page, open the **Create Bulk Entitlement** page for the bulk entitlement from which you want to delete Web register keys and click **Next**.



Task **To delete a web register key**

1. On the **Load Web Register Keys** page, select the web register key you want to delete (or multiple keys) by selecting the corresponding check box.
2. Click **Delete**.
3. Click **Yes** to confirm deletion.

Specifying User-Supplied Web Register Keys

When loading Web register keys from a user-supplied file, you must provide the key values in an XML file. Enter Web register keys into a text file with the following format and save it on the machine on which you are running a browser.

```
<?xml version="1.0" encoding="UTF-8"?>
  <webregkeys>
    <webregkey>web_reg_1</webregkey>
    <webregkey>web_reg_2</webregkey>
    <webregkey>web_reg_3</webregkey>
    ...
  </webregkeys>
```

Use the controls on the **Load Web Register Keys** page to specify this file. (See [Loading Web Register Keys](#).)

Web register keys can also be imported using the Entitlement Order Web service. See the createWebRegKey operation in the *FlexNet Operations SOAP Web Services Guide* for instructions.

See Also

[Loading Web Register Keys](#)
[Creating a Bulk Entitlement](#)
[What is a Bulk Entitlement?](#)

Bulk Operations: Upgrade, Upsell, or Renew a Product

This wizard allows you to create new entitlements for a customer that has purchased either:

- An upgraded version of a product. This allows a customer to move from an older version of a product to a newer version.
- An upsold version of a product. This allows the customer to move from a product with fewer features to one with more features.
- A renewal of a product. This allows a customer to extend an existing entitlement for a licensed product.

The Bulk Operations process allows an Upgrade, Upsell, Renew, Test Upgrade, Test Upsell, or Test Renew of an entire set of entitlements. You are presented with a wizard that prompts you for information about the type of action that you want to perform. Many of the steps for completing each of these processes are identical and are outlined here. You can perform these operations in bulk, for multiple accounts, line items, and products all at once.



Note - Before performing an upgrade or upsell action, you must create the appropriate upgrade and upsell relationships between products. In addition, you can perform a Renew only when one of the following conditions is met:

- The entitlement line item has an Expiration Term that is temporary. (That is, the Expiration value is not set to Permanent.)
- If the Expiration Term for the entitlement line item is Permanent, it specifies a Product containing at least one Feature with the Version Format Type set to Date Based.



Important - FlexNet Operations does not evaluate the count of available copies when an upgrade is created. Therefore, it is possible to create an upgrade count that exceeds the number of available copies; however, the count is evaluated at fulfillment time. On fulfillment, upgrades that exceed the available count are rejected. To avoid errors at fulfillment time, users can invoke the method `getExactAvailableCount()`, which returns the exact number of copies available for upgrade fulfillment. This method is available as a web service call and also as part of public API.



Task **To use the Bulk Operations wizard**

1. Click **Entitlements > Bulk Operations**. This link opens the **Bulk Operations** page.
2. Select your operation by clicking the corresponding button: **Upgrade**, **Upsell**, **Renew**, **Test upgrade**, **Test upsell**, or **Test renew**. (The Test version of each operation only shows draft and deployed entitlements.)
3. Basic Information: Enter the basic information about the operation, and then click **Next**.
 - **Name**: The name of the upgrade, upsell, or renewal. You can use this for tracking purposes.
 - **Description**: A short description of the bulk operation you are performing.
 - (For Upgrades or Upsells Only) **Check Maintenance**: Select whether or not any maintenance line items are included in the upgrade or upsell. If **Yes**, select an expiration date for the maintenance using the calendar control. Line items linked to maintenances expiring after this date are displayed later.



Note - If the year that you want to set is not currently available from the date picker, select the year that is closest to the desired year. This automatically increases the list by 10 years from the year you selected.

- **Obsolete Line Items**: Indicate whether or not the parent line item of this item will be made obsolete.
 - (For Renewals Only) **Support Version Date Renewals**: For renewals, select whether or not to support version date renewals.
 - If yes, then permanent line items are shown during the renewal process. Only line items that have products with a date-based feature are shown.
 - If no, then you cannot renew permanent line items.
4. **Select Product**: For upgrades and upsells, a list of products is presented that can be upgraded or upsold. These are products that have been entitled to this account and that either have an Upgrade To relationship or an Upsell To relationship. Select the product you want to upgrade or upsell and then click **Next**.
 5. **Select Accounts**: If you want to perform the process for all accounts, select Yes. If not, select No and then select the accounts for which you want to perform the process. When complete, click **Next**.



Note - When performing a bulk upgrade for embedded licenses, all accounts must be upgraded.

6. **Select Line Items**: Select the entitlement line items you are upgrading, upselling, or renewing. These are entitlement line items that contain products entitled to the selected accounts. In Upgrade Count, type the

number of copies in the entitlement line item you want to upgrade, upsell, or renew. For Test operations, only Test line items are displayed. Then, click **Next**.

7. **Select Product:** For upgrades and upsells, a list of products is presented that can be upgraded or upsold. (The products being operated upon in Step 4 must have a common license model for you to select them in this step.) Select the products you want to upgrade, upsell, or renew and then click **Next**.



Note ▪ When performing a bulk upgrade for embedded licenses, only one product must be selected.

8. **Configure Product Quantities:** Enter the quantities of the products being upgraded, upsold, or renewed.
9. **Configure Part Number and License Model:** Select the part number and license model for the product being upgraded, upsold, or renewed.



Note ▪ When performing a bulk upgrade for embedded licenses, the license model cannot be changed.

10. **Line Item Attributes:** Specify the version date and auto fulfill option, and enter values for any additional entitlement line item attributes for which you are prompted.

Specify version date as follows:

- **Version Date:** Define how the version date is determined. In the drop-down menu, select either:
 - **Use Start Date to compute Version Date:** the Version Date is computed using the duration entered here and the Start Date. Enter a value for a duration of time that is added to the Start Date value. The Start Date Value can be defined on this page or can be defined at the time the Entitlement Line Item is activated.
 - **Specify Value Now:** specify a static date.

If the year that you want to set is not currently available from the calendar, select the year that is closest to the desired year. This automatically increases the list by 10 years from the year you selected.
 - **Specify the Version Start Date Later:** the Version Date is computed using the duration entered here and the Version Start Date. Enter a value for the duration that is added to the Version Start Date value. The Version Start Date value is defined at the time the entitlement line item is activated.
 - **Specify Version Date Later:** the Version Date is specified at the time the entitlement line item is activated.
 - **Use Activation Date to compute Version Date:** the Version Date is computed using the duration entered here and the Activation Date. Enter a value for the duration that is added to the Activation Date value. The Activation Date is the date when the entitlement line item is activated.
- **Permanent:** Specify whether this license is Permanent or Temporary.
- **Duration:** If the license is temporary, specify the duration that it is valid.
- **Date:** If the license is temporary, specify a static date when the license expires.



Note - If the year that you want to set is not currently available from the calendar, select the year that is closest to the desired year. This automatically increases the list by 10 years from the year you selected.

For **Auto Fulfill**, specify Yes or No:

- Click **Yes** to automatically fulfill the line items. All the line items in the bulk operation are automatically fulfilled after the operation is submitted. Example: For a bulk upgrade operation in which the parent line item is already fulfilled, FlexNet Operations creates the new, child (upgrade) line items and automatically activates them.
- Click **No** if you want to manually fulfill the line items. Line items in the bulk operation must subsequently be manually fulfilled as a support action.

For **Copy Custom Attribute**, specify Yes or No (only applicable for upgrades and test upgrades):

- Click **Yes** to copy any custom attribute values associated with the parent line item automatically to the new line item during the bulk upgrade process.
- Click **No** if custom attributes should not be copied to the new line item.

11. **Configure Policies:** Set policies for the following items, and then click **Save & Next**.

- **Number of Rehosts:** How many times and how often can your customers move (or rehost) licenses from one computer to another? Choose from **Ignore Policy** or **Specify Value Now**. If you choose **Specify Value Now**, the Producer Portal reveals controls for setting the number and frequency of rehosts.
- **Number of Returns:** How many times and how often can your customers return licenses to the pool of available licenses? Choose from **Ignore Policy** or **Specify Value Now**. If you choose **Specify Value Now**, the Producer Portal reveals controls for setting the number and frequency of returns.
- **Number of Repairs:** How many times and how often can your customers repair licenses? Choose from **Ignore Policy** or **Specify Value Now**. If you choose **Specify Value Now**, the Producer Portal reveals controls for setting the number and frequency of repairs.
- **Number of Extra Activations:** How many extra seats (or activations) do you want to enable for each entitlement? Choose from **Ignore Policy** or **Specify Value Now**. If you choose **Specify Value Now**, the Producer Portal reveals a field for the extra activations value.



Note - This option does not apply to FlexNet Embedded licensing models. It is only applicable for FlexNet Publisher-based trusted activations.



Note - For additional information about configuring license policies, see [Setting License Model Policies](#).

12. **Submit Job:** Select whether to submit the bulk operations job for processing now or later. You may want to select this time based on your system capabilities.

- Jobs submitted now are processed within 2 minutes.
- If submitted for later, specify the time FlexNet Operations should process the job. Typically, you should choose a time when demand for processing time is low.

When complete, click **Submit**. Your bulk operations job is submitted for processing at the specified time. You can check job status on the **Bulk Operations** page. Failed jobs are displayed on the page as well, along with any errors encountered. More information on failed jobs is contained in the application log.



Tip - FlexNet Operations can automatically create upgrade line items for qualifying products and line items with the Product Version Upgrade job. See [FlexNet Operations Alert Types](#).

Verifying the Status of a Bulk Operation

On the **Bulk Operations** page, the **Status** column shows the current status of each bulk operation.

For upgrade bulk operations using auto-fulfill for embedded licenses, you can open a dialog that displays the progress of mapping activation IDs from parents to children.



Task To see the status of a bulk operation

1. Click **Entitlements > Bulk Operations**. This link opens the **Bulk Operations** page.
The Status column shows the status for each bulk operation.
2. To see detailed status information for an upgrade bulk operations using auto-fulfill for embedded licenses, click the linked value in the Status column. This opens the **Bulk Upgrade Status** dialog.



Note - The link only appears once the upgrade has started. The link is not available for bulk operations in "Draft" status.

The **Bulk Upgrade Status** dialog shows the parent activation IDs, the child activation IDs that are generated by the batch upgrade operation, and—under Parent Count and Child Count—the number of devices that each activation ID is mapped to.

Emailing Bulk Operation Notifications

When a bulk operation processes an upgrade for entitlements, you can initiate that end users are sent an email for each upgraded line item.



Note - Email notifications can only be sent for completed bulk operations. In addition, ensure that the **Ship To Email** field on the **Create a Bulk Entitlement** page has been populated with the recipient email (see [Creating a Bulk Entitlement](#)).



Task To send an email notification for a bulk operation

1. Click **Entitlements > Bulk Operations**. This link opens the **Bulk Operations** page.
2. Select a completed operation (where the **Status** field shows **Completed**).

3. Click **Email**. This link opens the **Email Bulk Operations** page. The **Name** field shows the name of the upgrade operation.
4. Enter the following information:
 - **Email Type**: Select if you want to send emails for entitlements or fulfillment, or both.
 - **Language for email**: Select the language of the email that will be sent.
 - **Submit Job**: Select **Now** if the notification should be sent immediately, or select **Later** and provide the date and time to schedule the sending of the email.
5. Click **Submit**.

You can check the email bulk operation job status in the **Email Status** column on the **Bulk Operations** page. A submitted job can have the status Success, Failed, or Pending. The **Notes** column shows additional information.

If an email job for a bulk operation has already been submitted, emails will be sent for any records for which an email could not be sent earlier.



Note ▪ When entitlements are upgraded during a bulk operation and the same product exists on multiple line items of the upgraded entitlement, a customer will receive a single email notification instead of a notification for every upgraded line item.

Merging Entitlements

This capability allows you to reassign entitlements and users to another account. When you merge an entitlement, everything in the entitlement remains the same, except the Sold To value. This is changed to reflect the new account. When you merge users, all users and contacts that are associated with the source account are reassigned to the target account.

Any channel partners that are assigned to an account's entitlements are included in the merge.

The following selections are defined when merging entitlements from one account to another.

Table 3-7 ▪ Merge Wizard Selections

Field	Description
Source Account	The company that currently own the assets. This can be either a customer account or a self-registered account.
Target Account	The company that receives the assets. Only customer accounts can be specified.
Assets to be Transferred	Select either or both: <ul style="list-style-type: none">● Entitlements and Fulfillments: all entitlements, fulfillments, and host ID values are associated with the Target Account.● Users: all users and contacts that are associated with the Source Account are associated with the Target Account.

Transferring Entitlements

You can transfer the license rights in a single entitlement from one account to another. All entitlement line items for that entitlement are transferred. Transfer of entitlement is possible only if there are no fulfillments. The system provides an option to return all existing fulfillments automatically during the process of performing the transfer.

Bulk entitlements cannot be transferred. Also, entitlements with line items on an auto-provisioned license server cannot be transferred.

After the license rights are transferred, the status of the entitlement for the origin account changes to Obsolete and a new entitlement is created for the target account.

To transfer individual entitlement line items, see [Transferring Entitlement Line Items](#).



Task *To transfer activatable entitlements to accounts*

1. Click **Entitlements > List Entitlements**. This link opens the **List Entitlements** page.
2. Search for a line item by Activation ID and then select the item you want to transfer.
3. Click **Transfer**. The line item is displayed on the next page if it is transferable.
4. Fill in the number of copies of the line item you want to transfer. The total number sold and the number available for transfer is displayed, along with the source account.
5. Click **Search** to select the target account to which the copies are to be transferred, and click **OK**. Alternatively, type the account name in the **Target Account** field.
6. Select whether the target account is to use the original Activation ID. **Yes** causes the system to generate the Activation ID; **No** requires you to provide the Activation ID.
7. If you selected **No**, enter the new Activation ID, and select which parent entitlement the new line item is to belong to: **Existing** or **New**.
8. If you selected **No** in Step 7, select whether you want the system to auto generate the Entitlement ID. If you select **No**, you must provide the Entitlement ID, and you must fill in the new entitlement details.
9. If you selected **Yes** in Step 8, the system auto generates the Entitlement ID. You are prompted to provide the address where email is to be sent, and the address where mail is to be sent.
10. Click **Transfer** to transfer the line item to the target account.
11. If you selected **Yes** in Step 7, select which parent entitlement the new line item is to belong to: **Existing** or **New**. If no parent entitlements exist, select **New**.
12. Select whether you want the system to auto generate the Entitlement ID. If you select **No**, provide the Entitlement ID, and fill in the new entitlement details.
13. If you select **Yes** in Step 13, the system auto generates the Entitlement ID and you are prompted to provide the address where email is to be sent, and the address where mail is to be sent.
14. Click **Transfer** to transfer the line item to the target account.

Transfer Entitlements Wizard

Required fields are indicated by a red asterisk.

1. Click **Entitlements > List Entitlements by Order**. This link opens the **List Entitlements by Order** page.
2. Select the entitlement from the list. You can also search for entitlements based on specific criteria by
 - Specifying some particular values in the simple search, like **Entitlement ID Starts With**
 - Clicking **Advanced Search**, which lets you specify multiple search attributes.
3. Click **Transfer**.
4. **Target Account:** click **Search** to select the account that is to receive the entitlement, or directly type in the account name. If there are unreturned licenses, continue with [Step 5](#). If there are no activated licenses, continue with [Step 6](#).
5. **There are some active fulfillments for line items in this entitlement. Would you like the system to automatically return them?**
 - **Yes:** Operations returns all of the activated licenses. Continue with [Step 6](#).
 - **No:** The entitlement (or entitlement line item) cannot contain activated licenses. These existing fulfillments must be returned before transferring the entitlement (or entitlement line item). Click **Cancel** and go to [Supporting Licenses](#) to return the Fulfillments associated with this entitlement (or entitlement line item).
6. **Will the Target Account use the same entitlement ID and activation IDs that the source account used?**
 - **Yes:** If you select this option, the new entitlement retains the values defined for the entitlement ID and activation IDs. The entitlement ID and activation IDs values defined in the originating entitlement are changed to reflect the action taken.

Click **Transfer**. You are prompted that the entitlement is to be transferred to the new account. Continue with [Step 8](#).
 - **No:** You are provided the opportunity to change the information. Continue with [Step 7](#).
7. **Would you like the system to generate the entitlement ID and activation IDs?**
 - **Yes:** Operations generates a new entitlement ID and activation IDs. Click **Transfer** and then continue with [Step 8](#).
 - **No:** Operations generates a new entitlement ID and activation IDs, but gives you the ability to change these values. Click **Transfer** and then continue with [Step 8](#).
8. The [Creating an Entitlement](#) page is displayed with the Entitlement ID and Activation ID fields populated with values based on your selections. You can either accept the values as they are or you can change them. The account defined in the **Account** field contains the name of the new account. Click **Deploy** to complete this action.

Viewing Fulfillment History

The fulfillment history of an entitlement identified with an activation ID can be displayed when viewing an entitlement order.



Task **To see the fulfillment history of a line item:**

1. Click **Entitlements > List Entitlements by Order**. This link opens the **List Entitlements by Order** page.
2. Locate the entitlement. You can search for entitlements based on specific criteria by
 - Specifying some particular values in the simple search, like **Entitlement ID Starts With**
 - Clicking **Advanced Search**, which lets you specify multiple search attributes.
3. Click the entitlement ID to open it in the **Create an Entitlement** page.
4. Find the entitlement line item whose history you want to view and click its **Fulfill History** link. A pop-up window is displayed with the fulfillment history.
5. Click **OK** to close the pop-up window.

Viewing Custom Attributes

Custom attributes appear on the **Maintenance Entitlement Details** pop up.



Task **To view custom attributes**

- On the **List Entitlements** page, under the **Maintenance** tab, you can click the maintenance hypertext to view the custom attributes in the **Maintenance Entitlement Details** pop up.



Note - You can also view the custom attributes on the **List Entitlements By Order** page.

Viewing Entitlement History

The transaction history of an entitlement including a summary of what was changed and who changed it can be displayed when viewing an entitlement order.



Task **To see the change detail of an entitlement:**

1. Click **Entitlements > List Entitlements by Order**. This link opens the **List Entitlements by Order** page.
2. Search for an entitlement.
3. Click the entitlement ID to open it in the **Create an Entitlement** page.
4. Click **View Transaction** at the bottom of the page. The **Search Transactions: Results** page opens and list of updates is displayed. See [Viewing Transaction Histories](#) for more information.

Activating Licenses

An *activation* represents what the customer installed or redeemed against an entitlement. The activation process generates the actual license rights used by the software application you sell to customers, based on the license models you defined earlier.

When activating licenses, the software producer turns on license rights for a product or set of products for a customer account by performing the following tasks:

- Selecting an entitlement line item, identified by an activation ID, that refers to a specific product name and version
- Specifying values for license model attributes that are set at fulfillment time
- Generating a license

This section includes the following main topics.

Table 3-8 ■

Topic	Description
Activation Terms	Defines terms used to discuss activations.
Viewing Entitlements to Activate	Explains how to show all activatable line items.
Emailing an Entitlement Line Item	Shows how to email an entitlement line item.
Activating a License	Describes how to activate licenses with either the Activate Licenses wizard or Trusted Activate wizard.
Transferring Entitlement Line Items	Explains how to transfer entitlement line items and use the Transfer Entitlement Line Item Wizard.
Emailing a License	Shows how to email a license.
Manual Activations	Discusses manual activations and how to view a manual activation response.
Short Code Activations	Discusses short code activations and how to view a short code activation response.

See Also

- [Special Host ID Types](#)
- [Manual Activations](#)
- [Short Code Activations](#)

Activation Terms

The following topics define the terminology used for activations:

- [What is a License?](#)

- [What is Activation?](#)
- [What is the Activatable Line Item Type?](#)
- [What is an Activation ID?](#)
- [What is Batch Activation?](#)
- [What is License Consolidation?](#)

What is a License?

A license allows the use of software capability. FlexNet licenses are delivered as license certificates or delivered into trusted storage on a machine. License delivery for custom license technologies may vary.

See Also

[Activating a License](#)

[Emailing a License](#)

[What is License Consolidation?](#)

What is Activation?

Activation is the entire process of requesting, generating, delivering, and installing license rights. Generating a license certificate and activating a license in trusted storage using FlexNet Operations are different activation processes.

See Also

[Activating a License](#)

[Manual Activations](#)

[Short Code Activations](#)

[What is Batch Activation?](#)

What is the Activatable Line Item Type?

The *activatable line item type*, which is displayed in the Type column on the **List Entitlements** page, indicates whether an entitlement is certificate-based, trusted storage-based, or custom.

See Also

[Viewing Entitlements to Activate](#)

[Emailing an Entitlement Line Item](#)

What is an Activation ID?

The activation ID is the unique identifier of an activatable item. An activatable item is either an entitlement line item in a simple entitlement or a Web register key in a bulk entitlement.

Activation ID in FlexNet Operations corresponds to entitlement ID in FlexNet Publisher Licensing Toolkit. In trusted storage, Entitlement ID is the identifier of the entitlement that contains the activatable item.

The activation ID is listed in the **Activation ID** column on the **List Entitlements** page. A customer can log in to the End-User Portal with an activation ID.

See Also

[Viewing Entitlements to Activate](#)
[Emailing an Entitlement Line Item](#)

What is Batch Activation?

To simplify activation, FlexNet Operations supports simultaneous activation of multiple entitlement line items, provided the following are *all* true:

- All line items are sold to the same account.
- All line items pertain to the same certificate-based license model, that is, node-locked uncounted, node-locked counted, floating uncounted, or floating counted.

OR

- All line items pertain to the same custom license technology.

In other words, licenses for different customer accounts, trusted storage-based license models, or different certificate-based license models cannot be activated together. Products in the line items can vary. The line items need not share the same entitlement ID.

You can consolidate licenses generated during batch activation.

See Also

[Activating a License](#)

What is License Consolidation?

License consolidation is the process of combining multiple licenses into a single license file. Consolidating licenses can simplify subsequent rehosting tasks because it allows you to convert several separate licenses into a consolidated license.



Note - The license consolidation feature is not available by default. To enable this feature, the producer must select the **Show Consolidate Licenses Functionality** check box in **System > Configure > FlexNet Operations**.

License consolidation can take place during batch activation or post-activation.

License Consolidation Limitations

License consolidation is only possible for certificate licenses, and for custom (non-FlexNet) licenses when a custom consolidation class has been implemented. (See [Creating a License Technology](#) for more information.)

It is not possible to consolidate trusted storage licenses.

To be consolidated, licenses must belong to the same customer account. The licenses you consolidate can be based on different license models, use different license generator configurations, or even belong to different license technologies; however, when license technologies are different the consolidation process does not result in a single license. One consolidated license is created for each license technology.

License Consolidation Processing

For certificate licenses, a separate consolidated license is generated for each host. A separate consolidated license file is generated for floating or node-locked licenses on each license server. For example, floating counted and floating uncounted certificates can be consolidated on a single server. Also floating counted and node-locked counted certificates can be consolidated on a single server. (This is because the node-locked counted model requires a license server system.)



Note • For custom license technologies, the result of license consolidation depends on how the producer codes the consolidator class, where custom consolidation rules are defined.

See Also

[Consolidating Licenses](#)

[Administering License Technologies](#)

Viewing Entitlements to Activate

The **List Entitlements** page displays all activatable line items (entitlement line items and Web register keys), in order of modification date, most recently modified first. Line items using trusted license models are marked with an icon that looks like a letter T in a blue square.

By default, the following columns are included.

Table 3-9 • List Entitlements Page

Column	Description
Type	Identifies the license type—Certificate, Trusted, or Embedded—for the activatable line item.
Activation ID	The unique identifier of the activatable item. An activatable item is either an entitlement line item in a simple entitlement or a Web register key in a bulk entitlement. Activation ID in FlexNet Operations corresponds to entitlement ID in FlexNet Publisher Licensing Toolkit.
Entitlement ID	The identifier of the entitlement that contains the activatable item. Before a Web register key is activated, its entitlement ID identifies its bulk entitlement.
Parent Bulk	After the Web register key is activated, the ID of the bulk entitlement moves to the Parent Bulk column, and the entitlement ID of the simple entitlement created when the Web register key is redeemed replaces it. The ID of the new simple entitlement is <code>web_register_keyENT</code> . (Column is hidden by default.)
Sold to	The Sold to account has the right to receive licenses generated against this entitlement. The account information is presented in the format <i>Account ID (Account Name)</i> .
State	Activatable entitlements must be in the Deployed state. Other entitlement states are Test, Draft, Inactive. (Column is hidden by default.)

Table 3-9 - List Entitlements Page

Column	Description
Product	All products defined for the line item, including version numbers.
Available quantity	Number of activatable copies remaining in the line item: note that this number may be subject to policies.
Total quantity	Total number of activatable copies in the line item.
Expiration	Expiration date or duration of licenses issued from this line item, specified during entitlement creation
Order ID	The entitlement's order ID.
Maintenance	The entitlement's maintenance product.

To view all activatable line items, select **Entitlement ID**, **Parent bulk entitlement ID**, **Activation ID**, **Product**, **Part number**, **Sold-to Account name**, or **Sold-to Account ID** from the **Search for** drop-down, and click the **Simple Search** icon. You can also search for entitlement line items based on specific criteria. Line items in this page can be sorted by the following columns: **Activation ID**, **Entitlement ID**, **Sold to**, **Available quantity**, and **Maintenance**.

From this page, you can do the following:

Table 3-10 - Viewing Activatable Line Items

Action	Description
See the details of an activatable item	To see the details of a line item, click its activation ID.
Activate licenses for an entitlement line item or Web register key	To activate a license, select one or more activation IDs and click Activate or Trusted Activate , depending on the license type. Use Activate for certificate-based and custom activations. Use Trusted Activate for trusted-storage-based activations.
Print an entitlement	To print an entitlement line item, select one or more entitlement line items and click Print .
View an entitlement certificate	To view an entitlement certificate as it would appear when emailed to a customer, select the box next to a line item and click View certificate .
Email an entitlement	To email an entitlement line item, select the box next to it and click Email .
View fulfillment history	To view an entitlement's fulfillment history, select the box next to it and click Fulfill history . When complete, click OK .

Emailing an Entitlement Line Item

Use the **Email** button to send an entitlement to a specified email address or contact in a customer account.



Task *To email an entitlement line item to a customer*

1. Navigate to the **List Entitlements** page.
2. Select the box next to the line item you want to email; click **Email**.
3. Enter the email address you want the entitlement sent to. Use the search icon to look for contacts in the customer account. All contacts defined in the channel partners of the entitlement are automatically selected.
4. Click **Send**; click **Cancel** to cancel the operation and return to the **List Entitlements** page.

Activating a License

All activatable items are displayed in the **List Entitlements** page: items that generate certificate licenses and items that cause licenses to be written to trusted storage. By default, only line items that have any remaining copies are shown in this page. To see line items that do not have any copies remaining, perform an advanced search.

1. Click **Entitlements > List Entitlements**.
2. Search for an activation ID (entitlement or Web register key) against which to generate a license.
3. Select one or more activation IDs and click **Activate** or **Trusted Activate**, depending on the license type of the line item. You can select two entitlement line items that specify the same license model type (node-locked counted, floating counted, etc.) and activate licenses against them using the same wizard. You cannot do this with upgrade, upsell, or renewal entitlement line items.
4. Complete the steps in the Activate Licenses wizard (certificate) or Trusted Activate wizard (trusted storage).

The following topics provide more detailed instructions for activation wizard tasks.

Table 3-11 •

Topic	Description
Activate Licenses Wizard	Describes the fields that comprise the first page of the Activate Licenses wizard.
Trusted Activate Wizard	Describes the fields that comprise the first page of the Trusted Activate wizard.
Specifying Host IDs	Discusses the use of host IDs to provide tighter control over the environments in which the license can be legitimately used. (This is step 2 of the Activate Licenses wizard.)
Configuring Hosts in the Trusted Activate Wizard	Explains how to add a host for the activation. (This is step 2 of the Trusted Activate wizard.)

Table 3-11 ▪

Topic	Description
Special Host ID Types	Identifies the host ID types that can be differentiated by the Vendor Certificate Generator.
Configuring Counts	Explains how to configure counts for entitlement line items for certificate-based activation.
Configuring Counts for Trusted Activation	Explains how to configure counts for entitlement line items for trusted-storage activation.
Reviewing Activations and Generating Licenses	Describes how activations are presented for review and how to generate licenses for those activations.

Activate Licenses Wizard

Required fields are indicated by a red asterisk. Provide values for the following fields and any fulfillment-time license model attributes. Then click **Next** to specify [server or node-locked host IDs](#).

Table 3-12 ▪ License Generation - Required and Optional Fields

Field	Description
Sold to	This field is automatically populated unless the Activation ID was created using a bulk entitlement. When activating a Web register key of a bulk entitlement, the user must specify the Sold To field. This allows the producer to identify company that actually activated the Web register key.
Owner	Optional field. Shows the user who actually bought the web register key.
ActivationID	This field is automatically populated.
Product	Product name and version. This field is automatically populated.
Version	This field is automatically populated.
Expiration Date	This field is automatically populated.

Table 3-12 • License Generation - Required and Optional Fields

Field	Description
Version Date	<p>This field is displayed only in the following case:</p> <ul style="list-style-type: none"> the product defined in this entitlement line item contains a feature that specifies a date-based version format type, and you selected Specify Version Date Later when you created the entitlement for this product. <p>If Specify Version Start Date Later is set in a line item, a duration is specified in the line item. In this case, a version start date is set at activation time and the version date is computed as version start date + duration.</p>
Start Date	<p>After the entitlement is activated, the start date is the date that the license becomes valid and the user can begin using the software.</p> <ul style="list-style-type: none"> If the start date option was set in the entitlement line item, it is displayed. Whether it is editable depends on the Allow Editing of Deployed Entities configuration setting. If the start date was not set in the entitlement line item, it must be set when the first license is activated against the line item. This start date is written back to the line item. Whether it is editable depends on the Allow Editing of Deployed Entities configuration setting. (This bullet is true for Specify at First Activation or Use First Activation Date; Specify at Each Activation and Use Each Activation Date are not covered.) <p>When activating several line items together, you are prompted to specify the start date for those items without one. This date, once set at activation time, applies to all items that did not have a start date set during entitlement creation.</p>
Ship to email	<p>The email address to which a license generated against this entitlement is to be sent: It can be the email address of an account contact or an address already entered in the entitlement.</p> <ul style="list-style-type: none"> Click Search to select an email address for one of the contacts in the sold-to account. Additional email addresses can be entered in a comma-separated list that contains no spaces.
Ship to address	<p>The mailing address to which a license generated against this entitlement is to be sent: It can be the mailing address of an account contact or an address already entered in the entitlement.</p>
Vendor String	<p>Enter the producer-specific vendor string.</p>

Table 3-12 ▪ License Generation - Required and Optional Fields

Field	Description
Do you want to consolidate generated licenses?	<p>Select Yes (default setting) if you are activating two or more line items together, and would like to consolidate multiple licenses into a single license file. When activating a single license, this option does not appear.</p> <p>This is displayed if the Show Consolidate Licenses Functionality flag is enabled in System > Configure > FlexNet Operations.</p>

See Also

- [Specifying Host IDs](#)
- [Trusted Activate Wizard](#)
- [Activating a License](#)

Trusted Activate Wizard

Required fields are indicated by a red asterisk. Provide values for the following fields and any fulfillment-time license model attributes. Then click **Next** to configure a host. (See [Configuring Hosts in the Trusted Activate Wizard](#).)



Note ▪ This page also shows custom attributes (if any) defined and set at fulfillment time.

Table 3-13 ▪ License Generation - Required and Optional Fields

Field	Description
Sold to	This field is automatically populated unless the Activation ID was created using a bulk entitlement. When activating a Web register key of a bulk entitlement, the user must specify the Sold To field. This allows the producer to identify the company that actually activated the Web register key.
Owner	Optional field. Shows the user who actually bought the web register key.
ActivationID	This field is automatically populated.
Product	Product name and version. This field is automatically populated.
Version	This field is automatically populated.
Expiration Date	This field is automatically populated.

Table 3-13 ▪ License Generation - Required and Optional Fields

Field	Description
Ship to email	<p>The email address to which a license generated against this entitlement is to be sent: It can be the email address of an account contact or an address already entered in the entitlement.</p> <ul style="list-style-type: none"> ● Click Search to select an email address for one of the contacts in the sold-to account. ● Additional email addresses can be entered in a comma-separated list that contains no spaces.
Ship to address	<p>The mailing address to which a license generated against this entitlement is to be sent: It can be the mailing address of an account contact or an address already entered in the entitlement.</p>
Reinstall	<p>For server activation requests, select the check box for reinstalls. The effect of the Reinstall check box is that it prevents the activation from consuming the line item count. For retail (client) requests, the Reinstall check box is not shown. (Any repeat retail activation is automatically treated as a reinstall.)</p>
Vendor String	<p>Enter the producer-specific vendor string.</p>

See Also

[Configuring Hosts in the Trusted Activate Wizard](#)
[Activate Licenses Wizard](#)
[Activating a License](#)

Specifying Host IDs

When a license file (certificate) is issued to the customer, it can contain information to validate that it is being used on only a specific license server. In addition, it can be configured to allow only a specific client to check out the feature. Host IDs are used to define this information.



Note ▪ Depending on the license model defined for this product, you are prompted for one or more of the following attributes. If host IDs were implemented for this license model, you see a set of options:

- **Select Existing Host:** Select a host ID that has been already defined for this account.
- **Add New Host:** Create a host ID that has not been already defined for this account.
- **Remove:** This allows you remove a host ID value from this list.

Depending on how the license model is defined for this product, there are two types of hosts you can define. You are provided with the same selections for each host type you must define (Server or Nodelocked). The page displays a label indicating the type of host you are defining.

- **Server host:** this information is used to identify the license server that can serve these licenses.

For example, when you define the Server host to be HOSTNAME=dogma, the license can only be served from a system with the hostname 'dogma'. The license cannot be used on a system with a different hostname.

Each license server machine is identified by a host ID.

If you specify multiple server host IDs, then multiple license files are created: one for each host ID (that is, each license server system).

In the case of the nodelocked counted license model, you must define nodelocked host IDs for each server host ID (or three-server configuration) specified.

- **Nodelocked Host:** this information is used to identify the client that is checking out the feature. This creates a restriction that a product can only check out a feature if it is run on a specific client system.

Enter a host ID value identifying the machine to which the application is to be locked.

- To lock an application to more than one machine, click **Add Nodelocked Host** and enter multiple host ID values.

In the case of the nodelocked counted license model, you must define nodelocked host IDs for each server (or three-server configuration) specified.

The following table explains the type of host IDs that you are prompted for based on the license model type.

Table 3-14 - Definition of Hosts based on License Model

	If the license type is:			
	Nodelocked Counted	Nodelocked Uncounted	Floating Counted	Floating Uncounted
You are prompted to define the:	Server Host	Not Required	Server Host	Server Host
	Nodelocked Host	Nodelocked Host	Not Required	Not Required

1. In the **Generate Licenses** page, specify the necessary Host IDs (Nodelocked or Server) for the License and then click **Next**.
2. If the license model is counted (nodelocked or floating), you are prompted to specify a fulfill count for each server host ID, then click **Next**. If you are not required to specify a fulfill count (for example, for uncounted license models) do one of the following:
 - To check that the parameter values you have entered are valid, click **Verify**.
 - To generate a license certificate, click **Generate**.

After a license is generated, it can be saved to disk or sent by email. For unconsolidated licenses, a certificate is issued for each product on each server. For consolidated licenses, one file is issued per server. For more information about viewing a consolidated license, see [Consolidating Licenses](#). If you have selected more than one file to view, you can choose among license files by selecting the appropriate Consolidated License ID from the drop-down list provided.

See Also

- [Configuring Counts](#)
- [Activating a License](#)

Configuring Hosts in the Trusted Activate Wizard

After identifying the ship-to and specifying any fulfillment-time custom attributes for the activation, you must configure one or more hosts. In this step, you must upload one or more valid retail (client) or server request files (XML).



Task

To add a host

1. On the **Configure Host** page of the Trusted Activate wizard, click **Add host**. This opens the **Create Host** page in a pop-up window.
2. Click **Browse**, select a valid request file, and click **Save**. The **Create Host** page closes and the host identified by the request file is added to the **Host** list on the **Configure Host** page.

You can add multiple hosts in this step. Click **Next** to configure counts for the trusted activation.

See Also

[Configuring Counts for Trusted Activation](#)
[Trusted Activate Wizard](#)

Special Host ID Types

The following FlexNet Publisher host ID types can be differentiated by the Vendor Certificate Generator (VCG):

Table 3-15 • Host ID Types

Host ID Type	Description
ANY	Special FlexNet Publisher Licensing Toolkit host ID ANY. Allows the license to run on any machine.
DEMO	Special FlexNet Publisher Licensing Toolkit host ID DEMO: Can be used only for node-locked licenses, never for Server host IDs. Allows the license to run on any machine.
Ethernet	Ethernet address and also called MAC address. This is the hardware address from the Network Interface Card (NIC). This value consists of 12 hexadecimal digits (a 48-bit number).
TPM ID	The Trusted Platform Module host ID adds an additional layer of security for Windows platform certificate based licensing to minimize software piracy. This feature is available with VCG kit 16.2.2.0. The length of the TPM ID should be in the following format: xxxxx-xxxxx-xxxxx (4 sequences of 5 characters and 3 hyphens for a total of 23 characters). TPM ID can be used in conjunction with other host ID types in case of redundant servers.
Long	Used only with Solaris machines. It is the Solaris 32-bit hardware machine ID. This value consists of 8 hexadecimal digits (a 32-bit number).

Table 3-15 • Host ID Types



Host ID Type	Description
User	User name: Enter as USER=user_name in the Activate Licenses page. The FlexNet C/C++ Licensing toolkit uses the login name. FlexNet Publisher Licensing Toolkit for Java uses the username environment variable.
Host Name	This can a simple host name or a fully qualified DNS name. Host name: Enter as HOSTNAME=host_name in the Activate Licenses page.
Display	On Unix, this is the X display name. On Windows, it is the display adapter. Display name: Enter as DISPLAY=display_name in the Activate Licenses page.
Routable IP Address	<p>This setting allows you to define the host ID as a routable, public IP address. Use the format INTERNET=w.x.y.z, where each letter represents an octet with a decimal value between 0 and 255.</p> <p>FlexNet Operations validates that the address is not among the private, non-routable sets. The routable address cannot be an address in the primary three reserved, private network address ranges: 10.0.0.0-10.255.255.255, 172.16.0.0-172.31.255.255, and 192.168.0.0-192.168.255.255. In addition, the address cannot be 127.0.0.1 (localhost).</p> <p></p> <p>Note • FlexNet Operations IP address validation can be disabled by unselecting Enable Basic IP Address Host ID Validation in the system configuration settings. (See Configuring System Settings.)</p>
Routable IP Address with Wildcards	<p>This setting allows you to define the host ID as a routable, public IP address with a wildcard (*) as one or more octets. Use the format INTERNET=w.x.y.z, where each letter represents an octet with a decimal value between 0 and 255.</p> <p>FlexNet Operations validates that the address is not among the private, non-routable sets. The routable address cannot be an address in the primary three reserved, private network address ranges: 10.0.0.0-10.255.255.255, 172.16.0.0-172.31.255.255, and 192.168.0.0-192.168.255.255. In addition, the address cannot be 127.0.0.1 (localhost).</p> <p>The wildcard rules for routable IP addresses also apply. For an IP address of w.x.y.z</p> <ul style="list-style-type: none"> • If w is less than or equal to 127, then x, y, and z can be wildcards. • If w is between 127 and 192, then only y and z can be wildcards. • If w is greater than or equal to 192, then only z can be a wildcard. <p></p> <p>Note • FlexNet Operations IP address validation can be disabled by unselecting Enable Basic IP Address Host ID Validation in the system configuration settings. (See Configuring System Settings.)</p>

Table 3-15 • Host ID Types



Host ID Type	Description
Non-routable IP Address	<p>This setting allows you to define the host ID as a non-routable, private IP address. Use the format <code>INTERNET=w.x.y.z</code>, where each letter represents an octet with a decimal value between 0 and 255.</p> <p>The address you specify must be an address within the primary three reserved, private network address ranges: 10.0.0.0-10.255.255.255, 172.16.0.0-172.31.255.255, and 192.168.0.0-192.168.255.255.</p>  <p>Note • FlexNet Operations IP address validation can be disabled by unselecting Enable Basic IP Address Host ID Validation in the system configuration settings. (See Configuring System Settings.)</p>
Non-routable IP Address with Wildcards	<p>This setting allows you to define the host ID as a non-routable, private IP address with a wildcard (*) as one or more octets. Use the format <code>INTERNET=w.x.y.z</code>, where each letter represents an octet with a decimal value between 0 and 255.</p> <p>FlexNet Operations validates that the address is among the permitted, non-routable sets. The address you specify must be an address within the primary three reserved, private network address ranges: 10.0.0.0-10.255.255.255, 172.16.0.0-172.31.255.255, and 192.168.0.0-192.168.255.255.</p> <p>The wildcard rules for non-routable IP addresses also apply. For an IP address of w.x.y.z</p> <ul style="list-style-type: none"> • If w is less than or equal to 127, then x, y, and z can be wildcards. • If w is between 127 and 192, then only y and z can be wildcards. • If w is greater than or equal to 192, then only z can be a wildcard.  <p>Note • FlexNet Operations IP address validation can be disabled by unselecting Enable Basic IP Address Host ID Validation in the system configuration settings. (See Configuring System Settings.)</p>
Disk SN	<p>This is used with Windows systems only and is the disk serial number.</p> <p>Locks the software to a PC with this C:/ drive serial number. Enter as <code>DISK_SERIAL_NUM=sn</code> in the Activate Licenses page.</p>
FLEXid	<p>This is for Windows, Mac, and Linux systems only. Locks the software to a PC with a hardware dongle (hardware key) with serial number <code>id_string</code>. The format of this identifier depends on the brand of dongle used.</p> <p>Enter as <code>FLEXID=id_string</code> in the Activate Licenses page.</p>

Table 3-15 • Host ID Types





Host ID Type	Description
Composite	<p>A composite host ID combines multiple FlexNet Publisher Licensing Toolkit host IDs together to provide a more secure host ID. For instance, you can use USER and Disk SN to identify a host ID. A composite host ID is a hashed 12-character hexadecimal value formed by combining the values of multiple simple host IDs types.</p> <p>If you select the Composite format, you must provide your end user with a program to calculate the Composite host ID for the host machine. Enter as COMPOSITE=comp_id in the Activate Licenses page. For more information about using Composite host IDs, see the FlexNet Publisher Licensing Toolkit documentation.</p>
Vendor Defined	<p>The user must select the VENDOR_DEFINED item from the drop-down list and then enter the vendor-defined host as <name>=<string></p> <p></p> <p>Note ▪ If you specify a vendor-defined host ID, you must build your VCG to support your vendor-defined host ID type.</p> <p></p> <p>Note ▪ You can use a completely new entity to validate the host. The host ID for this entity is defined in Operations as <name> = <string>, where <name> is the entity name you want to use. You must define a list of allowable name values in the VCG. You must also create the code in the application or vendor daemon that obtains the string value.</p>

Table 3-15 • Host ID Types

Host ID Type	Description
Virtualization-Aware	<p>Virtualization-aware host ID prefixes define server host ID types that permit or restrict the kind of virtual environments, if any, on which a license server can run. These new host ID types begin with PHY_, VM_, VMW_, HPV_, or LMB_.</p> <ul style="list-style-type: none"> • Use the PHY_ prefix with ETHER, INTERNET, HOSTNAME, DISPLAY, USER, DISK_SERIAL_NUMBER, or FLEXID to restrict license operation to physical machines. • Use the VM_ prefix with UUID to restrict license server operation to any supported virtual environments: Xen, Hyper-V, and VMWare. VM_UUID supersedes VMW_UUID and HPV_UUID. • Use the VMW_ prefix with UUID, ETHER, INTERNET, and HOSTNAME to restrict license server operation to VMWare Workstation and ESX Server virtualizations. VMW_UUID is still supported, but has been superseded by VM_UUID. • Use the HPV_ prefix with UUID, ETHER, INTERNET, HOSTNAME, and VSN to restrict license server operation to Microsoft Hyper-V virtualizations. HPV_UUID is still supported, but has been superseded by VM_UUID. • Use the LMB_ prefix with ETHER, INTERNET, HOSTNAME, or FLEXID (9 or 10) to permit license server operation with bare metal binding. This permits operation in a virtualization but binds the license to the physical host machine. <p></p> <p>Note • VMW_HOSTNAME, HPV_HOSTNAME, and LMB_HOSTNAME host IDs cannot contain wildcards (asterisks).</p> <p></p> <p>Note • When used with three-server redundancy, virtualization-aware host ID types for all servers in the triad must use the same prefix: PHY_, VW_, VMW_, HPV_, or LMB_.</p>
Cloud-Specific	<p>Cloud-specific host ID types permit the kinds of cloud-hosted environments, if any, in which the product can operate. There are two server host ID type options and two nodelocked host ID type options:</p> <ul style="list-style-type: none"> • AMZN Routable EIP Address and AMZN Routable EIP Address with Wildcards—The AMZN_EIP host ID types permit license server operation in Amazon EC2 (public cloud) environments with binding to an elastic IP address. Routable and Routable with Wildcard addresses are supported. Non-routable addresses are not supported. This host ID type cannot be used with three-server redundancy. • AMZN AMI Template ID and AMZN IID Instance ID—The AMZN_AMI and AMZN_IID host ID types permit nodelocked licensing in Amazon EC2 environments with binding to the AMI template ID or AMI instance ID, respectively. Template ID binding is typically used in virtual appliance scenarios. Instance ID binding supports more generic cloud-based usage such as running software in the public cloud or in a virtual private cloud.

Configuring Counts

If the entitlement line item contains a certificate-based, counted license model (nodelocked or floating), you are prompted to specify a fulfill count for each server host ID. If the entitlement line item contains a

- nodelocked uncounted license and you define multiple node-locked host IDs, then:
 - multiple licenses files are created, one for each node-locked host ID.
 - the Copies value for the entitlement line item decrements by the number of node-locked hosts you define.
- nodelocked counted license and you define multiple server host IDs, each with multiple node-locked hosts, then:
 - multiple licenses files are created, one for each server host ID.
 - the Copies value for the entitlement line item decrements by the sum of the fulfillment counts for each server.
- floating counted license and you define multiple server host IDs, then:
 - multiple licenses files are created, one for each server host ID.
 - the Copies value for the entitlement line item decrements by the sum of the fulfillment counts for each server.
- floating uncounted license and you define multiple server host IDs, then:
 - multiple licenses files are created, one for each server host ID.
 - the Copies value for the entitlement line item decrements by the number of server hosts you define.

If this is an upgrade, upsell, or renewal entitlement line item, the available information and options in the **Configure Counts** page are different, depending on the product's license model.



Important - FlexNet Operations does not evaluate the count of available copies when an upgrade is created. Therefore, it is possible to create an upgrade count that exceeds the number of available copies; however, the count is evaluated at fulfillment time. On fulfillment, upgrades that exceed the available count are rejected. To avoid errors at fulfillment time, users can invoke the method `getExactAvailableCount()`, which returns the exact number of copies available for upgrade fulfillment. This method is available as a webservice call and also as part of public API.

1. Review the prepopulated fields on the **Configure Counts** page. The number of data fields that are displayed varies, depending on how the license model is defined. An important value in this list is:

Total Remaining Copies: The number of copies in the entitlement line item that can be activated. This is the maximum number of licenses that the customer can fulfill against this entitlement line item, regardless of whether the fulfillment is a new or is an upgrade, upsell, or renewal of another product.

2. **Copies Available to Activate Without Upgrading Previous Fulfillments:**

Use these fields to define the number of copies you to activate without upgrading an existing product.

Table 3-16 ▪ Configure Count Fields

Property	Description
Available Copies	The number of copies in the entitlement line item that can be fulfilled as a new activation. It does not include the number of copies that are available as an upgrade to another product. This does not include Extra Activations.
Extra Activations Available	This number is set when you define the license model. This is the number of extra copies of the product (beyond those purchased) that are available to be activated.
Pending Copies	If you have defined multiple server host IDs, this value is the number of copies that have already been assigned to the other Hosts IDs in this activation action.
Fulfill Count	The total number of licenses you want to fulfill for this server host ID. Specify a fulfill count for each of the fulfillments you are generating. In the case of the floating counted license model, you must specify a count for each server or three-server configuration on which you want licenses activated. In the case of the node-locked counted license model, you must provide counts for each server (or three-server configuration) specified, and the nodelocked hosts attached to that server.
Remaining Overdraft	The number of remaining unused Overdraft Licenses.
Overdraft	Enter the number of Overdraft licenses you want to allow for this server host ID.

3. Copies Available To Upgrade From Previous Fulfillments on host <Host ID>

Use these fields to define the number of copies you want to activate as part of upgrading an existing product. This question is displayed for each server host ID defined on the previous page.

Table 3-17 ▪ Configure Count Types

Property	Description
Available <Upgrade/Upsell/Renew> Count	This value is not editable and displays the total number of copies previously fulfilled for this server host ID that can be upgraded, upsold, or renewed to this new product.
Upgrade Count	<p>This field is displayed when you are activating licenses for an upgrade, upsell, or renewal entitlement line item.</p> <p>The number of copies of earlier products that have been activated for this server host ID. Define the number of copies that you want to upgrade/upsell/or renew for this to this new product.</p> <p>This entry allows the upgrade to occur on licenses that have already been fulfilled.</p>

4. What kind of Activation do you want to perform on this host?

This is displayed only when the license model is uncounted and is displayed for each server host ID defined on the previous page. When the license model is uncounted, you activate one copy at a time. The answer to this question tells the system how that single copy is to be activated.

- **<Upgrade/Upsell>**: you activate this copy by upgrading or upselling an existing product (that is, fulfillment). If you select this, you are presented with a list of entitlement line items that references fulfillments products previously activated for that server host ID and that can be upgraded or upsold to this new product. You can choose which product you want to be upgraded/upsold.
 - **Activate**: you activate this copy by creating a new fulfillment for this server host ID.
 - **None**: you do not activate any copies of this product for this server host ID.
5. Finish specifying the Configure Counts properties. Then click **Next** to go to the **Generate Licenses - Review** page.



Note - When the activation includes multiple host IDs, an arrow in the Hosts list indicates the current host ID. Clicking **Next** on the Configure Counts page advances to the next host ID. When counts are configured for the last host ID, clicking **Next** advances you to the Review step.

See Also

[Reviewing Activations and Generating Licenses](#)
[Specifying Host IDs](#)
[Activating a License](#)

Configuring Counts for Trusted Activation

If the entitlement line item contains a counted license model (trusted, server), you are prompted to define a fulfill count for each server host. If the entitlement line item contains a

- retail license (uncounted) and you define multiple host IDs, then:
 - multiple licenses files are created, one for each host ID.
 - the Copies value for the entitlement line item decrements by the number of hosts you define.
- server license (counted) and you define multiple host IDs, then:
 - multiple licenses files are created, one for each host ID.
 - the Copies value for the entitlement line item decrements by the sum of the fulfillment counts for each server.

Whether the entitlement line item is an upgrade, upsell, or renewal, the available information and options in the **Configure Counts** page are the same.



Important - FlexNet Operations does not evaluate the count of available copies when an upgrade is created. Therefore, it is possible to create an upgrade count that exceeds the number of available copies; however, the count is evaluated at fulfillment time. On fulfillment, upgrades that exceed the available count are rejected. To avoid errors at fulfillment time, users can invoke the method `getExactAvailableCount()`, which returns the exact

number of copies available for upgrade fulfillment. This method is available as a web service call and also as part of public API.

1. Review the prepopulated fields on the **Configure Counts** page. The number of data fields that are displayed varies depending on how the license model is defined. An important value in this list is:

Total Remaining Copies: The number of copies in the entitlement line item that can be activated. This is the maximum number of licenses that the customer can fulfill against this entitlement line item, regardless of whether the fulfillment is a new or is an upgrade, upsell, or renewal of another product.

Table 3-18 - Configure Count Fields

Property	Description
Available Copies	The number of copies in the entitlement line item that can be fulfilled as a new activation. It does not include the number of copies that are available as an upgrade to another product. This does not include Extra Activations.
Extra Activations Available	This number is set when you define the license model. This is the number of extra copies of the product (beyond what was purchased) that is available to be activated.
Pending Copies	If you have defined multiple server host IDs, this is the number of copies that have already been assigned to the other Hosts IDs in this activation action.
Fulfill Count	The total number of licenses you want to fulfill for this server host ID. Specify a fulfill count for each of the fulfillments you are generating.
Remaining Overdraft	The number of remaining unused Overdraft Licenses.
Overdraft	Enter the number of Overdraft licenses you want to allow for this server host ID.

2. Finish specifying the **Configure Counts** properties for the current host.
3. Click **Next** to go to the **Generate Licenses - Review** page.



Note - When the activation includes multiple hosts, an arrow in the **Hosts** list indicates the current host. Clicking **Next** on the **Configure Counts** page advances to the next host. When counts are configured for the last host, clicking **Next** advances you to the **Review** step.

See Also

- [Reviewing Activations and Generating Licenses](#)
- [Configuring Hosts in the Trusted Activate Wizard](#)
- [Activating a License](#)

Reviewing Activations and Generating Licenses

Prior to generating licenses, the Producer Portal allows you to review the activations. (This step is the same in both the Activate License wizard and the Trusted Activate wizard.)



Task **To review activations and generate licenses**

1. On the **Generate Licenses - Review** page, click either:
 - **Verify**: This option evaluates properties defined and determines whether the license is valid. (Not available for trusted activations.)
 - **Generate**: This option activates the license and opens the **Generated Licenses** page.
2. On the **Generated Licenses** page
 - a. For unconsolidated licenses, a certificate is issued for each product on each server.
 - b. For consolidated licenses, one file is issued per server.
 - c. For trusted licenses, there is one response/license per host.



Note - For more information about viewing a consolidated license, see [Consolidating Licenses](#). If you have selected more than one file to view, you can choose among license files by selecting the appropriate Consolidated License ID from the drop-down list provided.

On the **Generated Licenses** page, you can choose to **Save to File** or **Print** one or more licenses. (For certificate-based licenses, you can also choose to **Email License** or see **Shipment Records**.)

See Also

[Emailing an Entitlement Line Item](#)
[Certificate License Models](#)
[Trusted License Models](#)

Transferring Entitlement Line Items

You can transfer unfulfilled copies of an entitlement line item from one account to another.

To do this, the account that is to receive the entitlement must be defined in FlexNet Operations. This is done using the Producer Portal's account management capabilities. (See [Managing Accounts](#).)

As part of this transfer process, you can choose to either create a new entitlement for the transferred entitlement line item or to add it to an existing entitlement for that target account. You can also maintain the Activation ID or create a new one. The Transfer Entitlement Line Item Wizard walks you through each of these choices.

After the license rights are transferred, the Activation ID may change (depending on your wizard selections). A new entitlement line item is created for the target account.

To transfer an entire entitlement, see [Transferring Entitlements](#).

Transfer Entitlement Line Item Wizard

Required fields are indicated by a red asterisk. To proceed through the wizard:

1. Click **Entitlements > List Entitlements**. This link opens the **List Entitlements** page.
2. Select an entitlement line item from the list, and then click **Transfer**.

3. Enter the **Transfer Amount**.
4. **Target Account:** Search for and select the account that is to receive the line item.
5. **Do you want to transfer to a similar line item owned by the target account?**
 - **Yes:** The system searches for similar line items.
 - **No:** A new entitlement and line item is created for the target account.

Emailing a License

A new or previously generated license certificate or custom license can be sent as an email attachment to one or more email addresses. The email attachment is sent as a file, by default called `licensexxxxx.lic`, where `xxxxx` is a random number. The default subject line is `License`.

The **Ship to email** field contains the email address where the license is to be sent. This field contains email addresses that were specified in the entitlement or during license generation. Click **Search** to select an email address for one of the contacts in the sold-to account. Additional email addresses can be entered, and multiple email addresses are formatted in a comma-separated list with no spaces.

After the email is sent, a confirmation message is displayed on the page.

[Managing Email and Email Templates](#)

Manual Activations

Trusted activations are normally done programmatically as transactions between a client or server activation utility and the FlexNet Operations server. The activation utility generates a request that is submitted programmatically and the FlexNet Operations server generates a response that is used to complete the activation.

However, an activation request can also be generated and written to a file by a FlexNet Publisher Licensing Toolkit activation utility running on the machine where the license is to be activated. Such a manual activation is useful when there is no internet connectivity on the host.

- The file containing the request is sent to the producer and loaded into FlexNet Operations to generate a response.
- The response is saved to a file; the file is sent to the customer and is used by the FlexNet Publisher Licensing Toolkit activation utility to process the response. The response is processed differently, depending on whether a license has ever been generated on that machine using the transaction key associated with the product to be activated. If a license has never been activated on the target machine using this transaction key, the first response just configures trusted storage. A second request and response must be generated to actually activate the license. This two-step process is handled automatically by programmatic activation.
- If the first response is used to configure trusted storage, the activation utility prompts the customer to generate a second request to activate the license.



Task *To generate a response to an activation request submitted in a file*

1. Click **Licenses > Manual Activation**.
2. Browse to, and select the XML file that contains the activation request.
3. Click **Submit** to generate and [view the activation response](#).

Viewing a Manual Activation Response

Follow the instructions below to view a manual activation response.



Task *After an activation response is generated manually*

1. Verify the Activation ID, Product, Version, Fulfillment ID, and Sold To account.
2. Click **Save To File** to save this response to a file. The default file name is responseXML.xml.
3. Send the file to the customer with instructions for using the activation utility to process the response and activate the license.

Short Code Activations

Trusted activations are normally done programmatically as transactions between a client or server activation utility and the FlexNet Operations server. Usually, the activation utility generates a request that is submitted programmatically and the FlexNet Operations server generates a response that is used to complete the activation.

However, if a customer's environment does not support communication with the FlexNet Operations server, FlexNet Operations can generate a short code activation specification record (ASR) that can be used to generate an activation request. Short code activations are typically used in activations performed over the phone.

- A producer uses FlexNet Operations to generate a short code ASR and bundles it with the product.
- A FlexNet Publisher Licensing Toolkit activation utility running on the machine where the license is to be activated uses the short code ASR bundled with the product to generate a short request code.
- The short request code is sent to the producer and loaded into FlexNet Operations to generate a short response code.
- The response code is saved to a file; the file is sent to the customer and is used by the FlexNet Publisher Licensing Toolkit activation utility to process the activation response and activate the license.



Task *To allow a customer to activate a license using a short response code*

1. Create a short code ASR for a product.
2. Bundle the short code ASR with the product or send the customer the short code ASR in a file.

3. Instruct the customer to use the FlexNet Publisher Licensing Toolkit activation utility that you provide to generate a short request code from the short code ASR file.
4. Receive the generated short request code from the customer, along with the customer's activation ID.
5. In FlexNet Operations, click **Licenses > Short Code Activation**.
6. Enter values in the following fields.

Table 3-19 ▪ Short Code Activation Fields

Field	Description
Short Request Code	Short request code generated by the FlexNet Publisher Licensing Toolkit activation utility and sent by the customer.
Activation ID	Activation ID of the line item or web register key that you want to activate.

7. Click **Next** to generate and [view the short response code](#).

See Also

- [Creating a Short Code ASR](#)
- [Emailing a Short Code ASR](#)

Viewing a Short Code Activation Response

Follow the instructions below to view a short code activation response.



Task *After a short response code is generated manually*

1. Save the short response code to a file.
2. Send the file to the customer with instructions for using the activation utility to process the response and activate the license.

4

Supporting Licenses

Supporting licenses covers additional license lifecycle processes:

- [Support Licenses Terminology](#)
- [Viewing Fulfillment Records](#)
- [Returning a License](#)
- [Repairing a License](#)
- [Rehosting a License](#)
- [Generating an Emergency License](#)
- [Correcting a Publisher Error in a License](#)
- [Upgrade, Upsell, or Renew a Fulfillment](#)
- [Generating a Stop Gap License](#)
- [Consolidating Licenses](#)
- [Transferring Licenses](#)
- [Manual Return](#)
- [Manual Repair](#)
- [Short Code Return](#)
- [Short Code Repair](#)
- [Supporting Hosts](#)
- [Supporting Embedded Licenses](#)
- [Supporting Offline Device Activation](#)

For trusted licenses, these lifecycle processes are usually handled by FlexNet Operations without publisher intervention. However, [manual returns](#) and [manual repairs](#) can be performed on activations.

Support Licenses Terminology

The following terms are referred to when supporting licenses:

- [What is a Fulfillment?](#)
- [What is a License Return?](#)
- [What is a License Repair?](#)
- [What is a License Rehost?](#)
- [What is an Emergency License?](#)
- [What is a Stop Gap License?](#)
- [What is Support Type?](#)
- [What is License Consolidation?](#)

What is a Fulfillment?

A fulfillment is a transaction against an entitlement line item in which some portion of the entitlement is assigned to a specific license server system or to a specific FLEXenabled application's machine. A fulfillment can be generated in FlexNet Operations in one of the following ways:

- Through the FlexNet Operations Producer Portal on behalf of an end user
- Through the End-User Portal by an end user
- Using the License Web service

In addition, trusted activations can be performed programmatically.

See Also

[Viewing Fulfillment Records](#)

What is a License Return?

A license return involves removing the license rights from a system and transferring the license rights back to an entitlement line item, generally to allow a different license to be created. The number of allowed license returns per unit time per entitlement line item can be governed by a policy on the license model or entitlement line item.

Most trusted returns are done programmatically, but they can also be done through the FlexNet Operations Producer Portal or End-User Portal.

See Also

[Returning a License](#)

What is a License Repair?

A repair operation is used to repair a license that does not work for a customer. The meaning of a license repair is different for trusted and certificate licenses:

- For a **certificate license**, a repair is a customer-initiated change to a license to change a license parameter other than a host ID. A repair initiates a license return, then generates a modified license certificate.
- For a **trusted license**, a repair is necessary when a license becomes invalid because the machine hardware configuration has been changed enough that the anchor is broken.

Most trusted repairs are done programmatically, but they can also be done through the FlexNet Operations Producer Portal or the End-User Portal.

The number of allowed license repairs per unit time per entitlement line item can be governed by a policy on the license model or entitlement item.

See Also

[Repairing a License](#)

What is a License Rehost?

For a certificate license, a re-host operation is a customer-initiated change to a license to transfer a license from one host ID to another. No license properties other than the host ID are modified for a re-host operation. A rehost initiates a license return, then generates a modified license certificate.

The number of allowed license rehosts per unit time per entitlement line item can be governed by a policy on the license model or entitlement line item.

See Also

[Rehosting a License](#)

What is an Emergency License?

An emergency certificate license is a short-term license that a publisher can provide as a courtesy to a customer who has a license that has not expired, but is not functioning.

When generating an emergency license, you can change only the license duration and host ID relative to the original license. An emergency license is intended to be a short-term license, with a default expiration period of 30 days.

See Also

[Generating an Emergency License](#)

What is a Stop Gap License?

A stop gap certificate license is a short-term license that a publisher can provide as a courtesy a customer whose license has expired, but who has not yet completed the process of updating or renewing an entitlement.

This can occur, for example, during the contract-negotiation period for a license renewal. Similar to an emergency license, for a stop-gap license you can modify only the license duration or license expiration date.

See Also

[Generating a Stop Gap License](#)

What is Support Type?

The *support type* is listed on the **Support Licenses** page and identifies the type of fulfillment that is generated. The following support types are available:

- **EMERGENCY:** A fulfillment generated by the Emergency operation. An emergency license is a short-term license generated to cover an emergency situation when a customer's license has not expired, but isn't working.
- **PUBLISHER ERROR:** A fulfillment generated by the Publisher Error operation. If a publisher makes an error when generating a license for a customer, it can be corrected and does not count against a customer's return, repair, or rehost policy limits.
- **STOP GAP:** A fulfillment generated by the Stop Gap operation. If a customer's license has expired and the customer has not formally renewed its entitlement, the publisher can generate a short-term stop gap license.
- **MASTER:** A fulfillment record that is created when a license is activated. When any portion of that fulfillment is returned, repaired, upgraded, upsold, or rehosted, the MASTER record is marked as obsolete. In addition:



Note - For returns, if the entire fulfill count is returned, there is no additional fulfillment record created because the count goes back to the entitlement line item. If only a partial amount is returned, the partial return count is credited to the entitlement line item and the obsolete fulfillment record is marked as returned.

See Also

[Returning a License](#)
[Repairing a License](#)
[Rehosting a License](#)
[Generating an Emergency License](#)
[Correcting a Publisher Error in a License](#)
[Generating a Stop Gap License](#)

Viewing Fulfillment Records

The **Support Licenses and Maintenance** page displays all active fulfillments, certificate and trusted, in order of modification date, most recently modified first. Trusted fulfillments are marked with an icon with a blue key.

To view fulfillment records, select **Activation ID**, **Product**, **Sold To**, **Hostid**, or **Fulfill ID** from the **Search For** drop-down, and click **Simple Search**. You can also search for fulfillment records based on specific criteria.

From this page, you can:

Table 4-1 ▪ Fulfillment Capabilities

Action	Description
See the details of an fulfillment	To see the details of a fulfillment, click its fulfillment ID.

Table 4-1 ■ Fulfillment Capabilities

Action	Description
Return a license	A license is returned to allow it to be activated again at a later time. The number of returns against an entitlement line item can be limited by a return policy. To return a certificate license, select exactly one fulfillment record and click Support Actions > Return .
Repair a license	A certificate license is repaired to change license parameters other than a host ID. The number of repairs against an entitlement line item can be limited by a repair policy. Repairing a license in trusted storage means something different and is done differently. To repair a certificate license, select exactly one fulfillment record and click Support Actions > Repair .
Rehost a license	A license is rehosted to change one or more host IDs. The number of rehosts against an entitlement line item can be limited by a rehost policy. To rehost a certificate license, select exactly one fulfillment record and click Support Actions > Rehost .
Generate an emergency license	An emergency license is a short-term license generated to cover an emergency situation when a customer's license has not expired, but isn't working. To generate an emergency certificate license that is related to a non-working license, select the fulfillment record of the non-working license and click Support Actions > Emergency . Generating an emergency license does not return the original license.
Correct a publisher error	If a publisher makes an error when generating a license for a customer, it can be corrected and does not count against a customer's return, repair, or rehost policy limits. To correct an error the publisher made to a certificate license, select exactly one fulfillment record and click Support Actions > Publisher Error .
Generate a stop gap license	If a customer's license has expired and the customer has not formally renewed its entitlement, the publisher can generate a short-term stop gap license. To generate a stop gap certificate license that is related to an expired license, select the fulfillment record for the expired license and click Support Actions > Stop Gap .
Consolidate licenses	You can consolidate the license lines from different certificates into a single file, provided the certificates belong to the same licensing technology and customer account. For FlexNet technology, only certificate licenses can be consolidated.
Upgrade a license	A customer replaces an older version of a product with a newer version, such as moving from MyProgram Version 4.5 to MyProgram Version 5.0.
Upsell a license	A customer replaces a product with another product that provides a superset of the original's functionality, such as moving from the MyProgram Standard Edition to the MyProgram Professional Edition.

Table 4-1 • Fulfillment Capabilities

Action	Description
Renew a license	Extending the expiration date of a product's original entitlement, or its version date, to a date further in the future. It is not necessary to define a relationship for a renew operation because the product involved does not change.
Save To File	A certificate license can be saved to a file.
Email License	A certificate license can be sent as an email attachment.
View consolidated licenses	You can view a list of consolidated license files and also view the contents of individual files.
Print a fulfillment record	Select one or more fulfillment records on the Support Licenses page and click Print .

See Also

[What is a Fulfillment?](#)

Returning a License

The number of allowed license returns per unit time per entitlement line item can be governed by a policy on the license model or entitlement line item.

**Task****To return a license to regenerate it at a later time**

1. Click **Licenses > Licenses**. This link opens the Support Licenses and Maintenance page.
2. Search for a fulfillment for which a license is to be returned. Search by **Activation ID**, **Product**, **Sold To**, **Hostid**, or **Fulfill ID**.
3. Select one fulfillment ID. Click Support Actions, and then click **Return**.
4. Enter a **Ship to Email** or a **Ship To Mail** address, if applicable.
5. The **Return Count** shows the entire fulfill count of the returned fulfillment. If you want to return only part of the original fulfill count, specify the **Return Count** to return.
6. The **Return Overdraft Count** shows the entire overdraft count of the returned fulfillment. If you want to return only part of the original overdraft count, specify the **Return Overdraft Count** to return.
7. Click **Return** to return the specified fulfillment.

When the license has been successfully returned, if the cancel policy allows it, the entitlement line item against which the license was created is credited.

When a Web register key was redeemed, a simple entitlement was created with an entitlement ID and its fulfill count. Therefore, if a license generated against a Web register key is returned, its simple entitlement line item is credited, not the original bulk entitlement.

When the license has been successfully returned, the return count entered by the user is credited for the entitlement line item against which the license was created. Therefore, if a license generated against a Web register key is returned, the return count for its simple entitlement line item is credited.

The new fulfillment generated by the return operation is displayed with the Support Type MASTER. The original returned fulfillment record is displayed in the **Support Licenses** page as Obsolete with support action as RETURN.

See Also

[What is a License Return?](#)

Repairing a License

From time to time, customers may require support for license keys. Requests for support of certificate licenses are processed as *repairs* and involve the change of a license parameter other than a host ID.

A publisher can set policies on how many repairs are allowed on a particular line item in a given duration.



Task

To repair a license because a customer wants to change a license parameter other than a host ID

1. Click **Licenses > Licenses**. This link opens the Support Licenses and Maintenance page.
2. Search for a fulfillment for which a license is to be repaired. Search by **Activation ID**, **Product**, **Sold To**, **Hostid**, or **Fulfill ID**.
3. Select one fulfillment ID and click **Repair** from the Support Actions drop-down menu.
4. Enter a **Ship To Email** or a **Ship To Mail** address, if applicable.
5. Replace the original attribute value with the one to be used for the new license. Hostid values cannot be changed with a repair. The entire count of the fulfillment is repaired.
6. To check that the parameter values can be used to generate a valid license before actually generating a license, click **Verify**. To generate a license certificate, click **Repair**.
7. After a license is generated, the license text is displayed. The license text can be saved to a file on disk by clicking **Save to File** or it can be sent as an email attachment by clicking **Email License**.

For information about the file naming conventions, see FlexNet Operations system configuration settings. The license certificate can be saved to a file on disk by clicking **Save to File**.

The shipment history of this license can be displayed by clicking **Shipment Records**.

The new fulfillment generated by the repair operation is displayed with the Support Type MASTER. The original returned fulfillment record is displayed in the Support Licenses and Maintenance page as Obsolete with support action as REPAIR.

See Also

[Emailing a License](#)

Rehosting a License

Rehosting is defined as the process of moving a license from one machine to another. A publisher can define policies to control the number of rehosts in a given duration of time per line item. This policy can be defined on the license model or the entitlement line item.



Task *To rehost a license because a customer wants to change a host ID*

1. Click **Licenses > Licenses**. This link opens the Support Licenses and Maintenance page.
2. Search for a fulfillment for which a license is to be rehosted. Search by **Activation ID, Product, Sold To, Hostid, or Fulfill ID**.
3. Select one fulfillment ID and click **Rehost** from the Support Actions drop-down menu.
4. Enter a **Ship to Email** or a **Ship To Mail** address, if applicable.
5. Replace the original host ID with the one to be used for the new license. No other license model attributes can be changed.
6. The **Rehost Count** shows the entire fulfill count of the returned fulfillment. If you want to rehost only part of the original fulfill count, specify the **Rehost Count** to return.
7. The **Rehost Overdraft Count** shows the entire overdraft count of the returned fulfillment. If you want to rehost only part of the original overdraft count, specify the **Rehost Overdraft Count** to return.
8. To check that the parameter values can be used to generate a valid license before actually generating a license, click **Verify**. To generate a rehosted license certificate, click **Rehost**.
9. After a license is generated, the license text is displayed. The license text can be saved to a file on disk by clicking **Save to File** or it can be sent as an email attachment by clicking **Email License**. The shipment history of this license can be displayed by clicking **Shipment Records**.

For information about the file naming conventions, see [Configuring System Settings](#).

The new fulfillment generated by the rehost operation is displayed with the Support Type MASTER. The original returned fulfillment record is displayed in the Support Licenses and Maintenance page as Obsolete with support action as REHOST.

See Also

[Emailing a License](#)

Generating an Emergency License

An emergency license is a short-term license generated to cover an emergency situation when a customer's license has not expired, but isn't working. Generating an emergency license does not return the original license.

**Task****To generate an emergency license because a customer cannot use unexpired licenses**

1. Click **Licenses > Licenses**. This link opens the Support Licenses and Maintenance page.
2. Search for a fulfillment for which an emergency license is to be generated. Search by **Activation ID, Product, Sold To, Hostid, or Fulfill ID**.
3. Select one fulfillment ID and click **Support Actions > Emergency**. Generating an emergency license does not cause the original fulfillment to be returned.
4. Enter a **Ship to Email** or a **Ship To Mail** address, if applicable.
5. By default, the **Start Date** of an emergency license is the **Fulfill Date** of the original fulfillment. You can set a different **Start Date** and can set the expiration to be after a set **Duration** or to a specific **Expiration Date**.



Note - If the year that you want to set is not currently available from the calendar, select the year that is closest to the desired year. This automatically increases the list by 10 years from the year you selected.

6. Replace license parameters for the emergency license. The entire count of the fulfillment is used for the emergency license.
7. To check that the parameter values can be used to generate a valid license before actually generating a license, click **Verify**. To generate an emergency license certificate, click **Emergency**.
8. After a license is generated, the license text is displayed. The license text can be saved to a file on disk by clicking **Save to File** or it can be sent as an email attachment by clicking **Email License**. The shipment history of this license can be displayed by clicking **Shipment Records**.

For information about the file naming conventions, see [Configuring System Settings](#).

Emergency fulfillments appear in the **Support Licenses and Maintenance** page as Support Type **EMERGENCY**.

See Also

[Emailing a License](#)

Correcting a Publisher Error in a License

If a publisher makes an error when generating a license for a customer, it can be corrected and does not count against a customer's return, repair, or rehost policy limits.

**Task****To regenerate a license because the publisher made an error generating the original license**

1. Click **Licenses > Licenses**. This link opens the Support Licenses and Maintenance page.
2. Search for a fulfillment for which a license is to be repaired. Search by **Activation ID, Product, Sold To, Hostid, or Fulfill ID**.
3. Select one fulfillment ID and click **Publisher Error** in the Support Actions drop-down menu.
4. Verify that you want to return the license to correct it.

5. Enter a **Ship to Email** and a **Ship To Mail** address, if applicable.
6. By default, the **Start Date** is the **Fulfill Date** of the original fulfillment. You can set a different **Start Date** and can set the expiration to be after a set **Duration** or to a specific **Expiration Date**.



Note - If the year that you want to set is not currently available from the calendar, select the year that is closest to the desired year. This automatically increases the list by 10 years from the year you selected.

7. Replace the incorrect values with those to be used for the new license. You can choose to correct a publisher-generated error for the entire fulfill count, or a partial amount.
8. To check that the parameter values can be used to generate a valid license before actually generating a license, click Verify. To generate a license certificate, click **Generate New License**.
9. After a license is generated, the license text is displayed. The license text can be saved to a file on disk by clicking Save to File or it can be sent as an email attachment by clicking **Email License**. The shipment history of this license can be displayed by clicking **Shipment Records**.

For information about the file naming conventions, see [Configuring System Settings](#).

Corrected fulfillments appear in the Support Licenses and Maintenance page as Support Type MASTER and the Original fulfillment record is marked as Obsolete with a support Type PUBLISHER ERROR.

See Also

[Emailing a License](#)

Upgrade, Upsell, or Renew a Fulfillment

You can upgrade, upsell, or renew one or more seats in a fulfillment. The new license is created for the currently defined server host.

This process is similar to activation of an upgrade, upsell, or renewal entitlement line item. The difference is that this process allows you to control which fulfillments are upgraded, upsold, or renewed.



Important - Before upgrading or upselling a fulfillment, you must upgrade, upsell, or renew the customer's entitlement line item for the product that this fulfillment references.



Important - Some conflicts can prevent the successful activation of upgrade line items. See [Avoiding the Creation of Upgrade Line Items with Incompatible License Models](#) for details.



Tip - FlexNet Operations can automatically upgrade line items for qualifying products and line items with the Product Version Upgrade job. See [FlexNet Operations Alert Types](#).

When you upgrade, upsell, or renew a fulfillment, the status of the original fulfillment is changed to **Obsolete** and the **Support Type** is changed to either UPGRADE, UPSELL, or RENEW accordingly. A new fulfillment is created and the **Support Type** is MASTER. If you upgrade or upsell only a portion of the total **Count** in a fulfillment, then two fulfillments are created. The status of the original fulfillment is changed to **Obsolete** and the **Support Type** is changed to either UPGRADE, UPSELL, or RENEW accordingly.

For example, F1-P1 is a fulfillment for ten seats of product P1 (the **Count** property equals 10). You upgrade only two seats from that fulfillment to product P2. The status of fulfillment F1-P1 is changed to **Obsolete** and the **Support Type** is changed to UPGRADE. Two new fulfillments are created:

- F2-P1 is a fulfillment for the remaining eight seats of product P1.
- F3-P2 is a fulfillment for the two seats of product P2.

If you are upgrading or upselling a product with a floating counted, floating uncounted, and nodelocked counted license model and the entitlement line item for the new product specifies a nodelocked uncounted license model, the user is prompted to define either the server host ID or the nodelocked host ID (see the following table for details).

For example, in case 3 of the following table, the license model changes from floating counted to nodelocked counted, the new fulfillment record requires that nodelocked host IDs be defined. The server host ID is obtained from the original fulfillment record, but the user is prompted to define the nodelocked host IDs. If there is no change in the license model type, then all the information is retained from the original entitlement line item.

Table 4-2 ■






	Original License Model	Upgrade or Upsell License Model	User is prompted to define the following host IDs (Server or Nodelocked):
1	FC	FC	None
2	FC	FU	None
3	FC	NC	Nodelocked host ID
4	FC	NU	Nodelocked host ID1
5	FU	FC	None
6	FU	FU	None
7	FU	NC	Nodelocked host ID
8	FU	NU	Nodelocked host ID  Note ■ In this case, the <i>SUPERSEDE</i> keyword is not used in the upgraded license, even if you enabled the Use SUPERSEDE Keyword for Upgrade and Renewal Licenses property in the System > Configure > FlexNet Operations page.
9	NC	FC	None

Table 4-2 •

	Original License Model	Upgrade or Upsell License Model	User is prompted to define the following host IDs (Server or Nodelocked):
10	NC	FU	None
11	NC	NC	None
12	NC	NU	<p>Nodelocked host ID</p>  <hr/> <p>Note ▪ In this case, the SUPERSEDE keyword is not used in the upgraded license, even if you enabled the Use SUPERSEDE Keyword for Upgrade and Renewal Licenses property in the System > Configure > FlexNet Operations page.</p>
13	NU	FC	<p>Server host ID</p>  <hr/> <p>Note ▪ In this case, the SUPERSEDE keyword is not used in the upgraded license, even if you enabled the Use SUPERSEDE Keyword for Upgrade and Renewal Licenses property in the System > Configure > FlexNet Operations page.</p>
14	NU	FU	<p>Server host ID</p>  <hr/> <p>Note ▪ In this case, the SUPERSEDE keyword is not used in the upgraded license, even if you enabled the Use SUPERSEDE Keyword for Upgrade and Renewal Licenses property in the System > Configure > FlexNet Operations page.</p>
15	NU	NC	<p>Server and nodelocked host ID</p>  <hr/> <p>Note ▪ In this case, the SUPERSEDE keyword is not used in the upgraded license, even if you enabled the Use SUPERSEDE Keyword for Upgrade and Renewal Licenses property in the System > Configure > FlexNet Operations page.</p>
16	NU	NU	None

FC=floating counted; FU=floating uncouncted; NC=node-locked counted; NU=node-locked uncouncted.

Upgrade Process

The following steps describe the upgrade process:

1. **Upgrade Products for the Activation ID...** page.

If there are multiple products (or entitlement line items) that this product can be upgraded or upsold to, you are presented with a list of entitlement line items that you can choose from. If there is only one entitlement line item that meets this requirement, you are not prompted to select anything.

2. In the **<Upgrade/Upsell/Renew> Fulfillment...** page, define the required properties.

3. Click:

- **Verify** to check whether the values entered generate a valid license.
- **Generate <Upgrade/Upsell/Renew> License** to create the new license and complete the process.



Important - FlexNet Operations does not evaluate the count of available copies when an upgrade is created. Therefore, it is possible to create an upgrade count that exceeds the number of available copies; however, the count is evaluated at fulfillment time. On fulfillment, upgrades that exceed the available count are rejected. To avoid errors at fulfillment time, users can invoke the method `getExactAvailableCount()`, which returns the exact number of copies available for upgrade fulfillment. This method is available as a web service call and also as part of public API.

Avoiding the Creation of Upgrade Line Items with Incompatible License Models

Some license technology and license model conflicts can prevent the successful activation of upgrade line items. (FlexNet Operations does not prevent the creation of these upgrade line items, but the resulting line items cannot be successfully activated.) The following upgrade paths result in upgrade line items that cannot be activated:

Table 4-3 -

Upgrading From	Upgrading To	Notes
Custom licensing	FlexNet Publisher Trusted Licensing	Sharing counts between a license model from a custom license technology and retail activation license model is not supported.
FlexNet Publisher Certificate Licensing	FlexNet Publisher Trusted Licensing	Sharing counts between a floating, counted license model and a retail activation license model is not supported.
FlexNet Embedded Licensing	FlexNet Publisher Certificate Licensing	Sharing counts between an embedded counted license model and a node-locked, uncounted license model is not supported.
FlexNet Embedded Licensing	FlexNet Publisher Trusted Licensing	Sharing counts between an embedded, counted license model and a retail activation license model is not supported.

Using the SUPERSEDE and SUPERSEDE_SIGN Keywords

The SUPERSEDE keyword, available in FlexNet Operations 8.2 and later, is an optional attribute of an INCREMENT line. Normally, INCREMENT lines in certificate licenses are additive: each INCREMENT line adds to the total number of licenses. However, if SUPERSEDE appears in a line, all licenses issued for the listed features earlier than the date specified in ISSUED= or START= are superseded by the contents of the line.

If f1, f2, and f3 are features of a product, an example of the use of SUPERSEDE would be:

```
INCREMENT f1 ... 1 ... ISSUED=1-jan-2008
INCREMENT f1 ... 4 ... SUPERSEDE ISSUED=1-jan-2009
```

The second line supersedes the first, and the first line is ignored.

```
FEATURE f1 ... 1 ... ISSUED=1-jan-2008
FEATURE f2 ... 1 ... ISSUED=1-jan-2008
FEATURE f3 ... 4 ... SUPERSEDE="f1 f2" ISSUED=2-jan-2009
```

In this example, f3 supersedes f1 and f2 and causes the license file to support only f3.

Specifying a start date with the ISSUED= keyword makes this date explicit (such as ISSUED=1-jan-2009). If the ISSUED date is not set, then SUPERSEDE uses the START= date.

Multiple INCREMENT lines for the same feature, specifying SUPERSEDE with the same ISSUED= date, are pooled together rather than superseding one another. The resulting license pool collectively SUPERSEDES the older feature. For example:

```
INCREMENT f1 ... 1 ... ISSUED=1-jan-2008
INCREMENT f1 ... 4 ... SUPERSEDE ISSUED=1-jan-2009
INCREMENT f1 ... 3 ... SUPERSEDE ISSUED=1-jan-2009
```

results in a license pool containing seven licenses for f1, collectively superseding the first INCREMENT line.

SUPERSEDE_SIGN works similarly to SUPERSEDE, but the supersede is based on signatures available in FlexNet Operations 11.5 or later.



Note - You cannot use both the SUPERSEDE and SUPERSEDE_SIGN keywords on the same feature definition line (or package line). Do not use both the SUPERSEDE keyword and the SUPERSEDE_SIGN to override the license model for the same feature name or package name. This may produce unexpected results. SUPERSEDE_SIGN is explained in the FlexNet Publishing Licensing Toolkit documentation.

Considerations When Using SUPERSEDE or SUPERSEDE_SIGN

This section explores issues to consider when using the SUPERSEDE keyword.

Server-based License Model to a Client-based License Model

An upgraded entitlement line item may refer to a different type of license model than the original line item; that is, server-based or client-based. For example, one line item could refer to a floating counted license model and a second line item could refer to a nodelocked uncounted model. As a result, the hosts necessarily are different. This operation is almost like rehosting the license from a server to a client.

Even if FlexNet Operations used the SUPERSEDE keyword in this case, it is not effective if the user chooses not to install the superseded license on the server. As a result, the SUPERSEDE keyword is not generated.

The same problem exists for upgrading from a client-based license model to a server-based license model.

Because SUPERSEDE overrides all features in that server ISSUED prior to the ISSUED date of the SUPERSEDE line, caution must be exercised when using it. Consider these situations before implementing SUPERSEDE.

Different Identifiers for the Same Host

A host can be identified using an IP address or a DNS name in FlexNet Operations, but there is no way to confirm that this is the same host. As a result, FlexNet Operations may not regenerate the licenses for certain fulfillments on that host, causing some features to be superseded inadvertently.

Using host ID policies can help mitigate this problem. Most publishers restrict how a host can be defined. For example, some of them may allow their users to use only DNS names.

Trusted Storage Licensing

Trusted storage licensing currently supports both returns and repairs. Currently, an upgrade operation is implemented as returning the previous license and activating a new one. As a result, FlexNet Operations cannot track that a new fulfillment was created due to upgrading another fulfillment and the SUPERSEDE keyword is not generated for trusted storage licenses.

Also, the SUPERSEDE solution depends on the fact that FlexNet Operations records all the licenses ISSUED for a particular host. If there is a trusted activation on that host, FlexNet Operations only has the Machine Identifier of that host (which is not the same as the host name). As a result, FlexNet Operations does not regenerate the trusted storage license and it can be superseded. Mixing trusted storage and certificate licenses on the same host can cause problems if the SUPERSEDE keyword is used.

Start Date of the Upgraded License

Note that the upgraded license is generated from a new entitlement line item. As a result, that entitlement line item can have a different start date than the original line item.

Original and Upgraded Fulfillment on the Same Day

If a user fulfills a license for a product and gets the upgraded license on the same day, the SUPERSEDE keyword does not override the original product license, as both license lines have the same ISSUED date.

If the host contains any fulfillments ISSUED on the same day with similar features, SUPERSEDE licenses need not be generated for these fulfillments.

HOSTID as ANY

If ANY (or DEMO) is used as the hostname, the license works on any machine. If such a license is upgraded, then regenerating all ANY licenses with the SUPERSEDE keyword is problematic. As a result, FlexNet Operations does not generate the SUPERSEDE keyword for ANY (or DEMO) host ids.

Multiple VCGs

If the publisher supports multiple VCGs, SUPERSEDE does not supersede feature lines from another vendor daemon. As a result, FlexNet Operations does not regenerate licenses belonging to another vendor daemon.

Different Organization Units (Accounts) Using the Same Host

A host is identified by its name and the organization unit (account) in FlexNet Operations. When a license is generated for the first time on a host, the organization unit of the logged-in user is set as the organization unit of the host.

Consider two users who belong to the same company and use the same machine to host their licenses, but identify themselves to FlexNet Operations using two different organization units. (This case is common with the channel sales model, when end customers buy from resellers and come to the publisher separately.) In this case, FlexNet Operations treats the host names defined by these two users as different hosts, but in reality, they may be the same machine. Licenses of one or the other user may become ineffective.

Self-Registered Users

Self-registered users are FlexNet Operations Portal users who do not belong to an organization unit (account). Internally, all self-registered users belong to a dummy organization unit called PORTAL_ORG_UNIT. Because a self-registered user name is not used to identify the host, the SUPERSEDE keyword cannot be used if self-registered users are supported. Licenses may be accidentally inactivated if two self-registered users use the same hostname.

Signature Length

SUPERSEDE_SIGN supersedes previous increment lines on a host based on their signatures. As signatures are quite long, sometimes, when a number of signatures are included in the SUPERSEDE_SIGN setting, the limit of the license line length can be equaled or exceeded.

If this occurs, the VCG returns the following error: Feature <name> has count zero. Increase count for the feature or decrease superseded sign list, where <name> is the feature for which the license line length is reached.

To resolve this issue, click **System > Configuration > FlexNet Operations > Override older fulfillments on the host using SUPERSEDE_SIGN keyword**. This decreases the number of signatures being added to the increment line.

Example of Using SUPERSEDE

The following is an illustration of the use of the SUPERSEDE keyword.

Consider a product, P1, with 3 features (f1, f2, and f3), and these attributes:

Product Name: P1 (F1, version 1.0) (F2, version 1.0) (F3, version 1.0)

Activation ID: Activation1

Entitlement ID: EL1

Account Name: Org1

Hostname: Mymachine

A user activates 5 out of 10 counts of the product, resulting in this license key:

```
SERVER this_host HOSTNAME=mymachine
VENDOR demo
USE_SERVER
INCREMENT F1 demo 1.0 26-dec-2008 5 ISSUER="My Corporation" \
  ISSUED=3-oct-2008 START=2-oct-2008 SIGN="002A 20C2 A452 8B82 \
```

```

7CF9 0A2D 1003 CB00 2BFC AC9B B59E D0C9 6CE6 5813 566A"
INCREMENT F2 demo 1.0 26-dec-2008 5 ISSUER="My Corporation" \
ISSUED=3-oct-2008 START=2-oct-2008 SIGN="00F0 9DFD 1320 33D9 \
63B1 FF49 3A87 9400 4A69 C389 E117 9D40 96D2 7578 0E97"
INCREMENT F3 demo 1.0 26-dec-2008 5 ISSUER="My Corporation" \
ISSUED=3-oct-2008 START=2-oct-2008 SIGN="005F 56FB 63A7 A359 \
C40B 5C7B C3BA 2D00 DE42 3BCA FF74 D606 6208 25F1 EB2D"

```

Now consider product P2, with 3 features, which is an upgrade of product P1. Product P2 has these attributes:

Product Name: P2 (F1, version 2.0) (F2, version 1.0) (F4, version 1.0)

Activation ID: upgraded-Act

Entitlement ID: upgraded-EL

Account Name: Org1

Hostname: Mymachine

Now, if the user upgrades 3 copies of P1 to P2, FlexNet Operations would generate the following licenses using the SUPERSEDE keyword:

Fulfillment license text for P2 (the upgraded product):

```

SERVER this_host HOSTNAME=mymachine
VENDOR demo
USE_SERVER
INCREMENT F2 demo 1.0 8-feb-2009 3 ISSUER="My Corporation" \
ISSUED=3-oct-2008 START=31-oct-2008 SIGN="0025 879F C7B4 798B \
66B5 262B 9D90 AE00 E62F FF09 2F83 2FBF E75C BA1A 2EC0"
INCREMENT F4 demo 1.0 8-feb-2009 3 ISSUER="My Corporation" \
ISSUED=3-oct-2008 START=31-oct-2008 SIGN="0069 4F14 9B2A 94F4 \
DB26 B912 801C 4400 CA61 4D94 78D6 1D1C A080 C8DB B744"
INCREMENT F1 demo 2.0 8-feb-2009 3 ISSUER="My Corporation" \
ISSUED=3-oct-2008 START=31-oct-2008 SIGN="00C6 6180 7299 E091 \
8DFD CFB1 497D D400 A1C0 D22F 18C4 54DE 9F45 34DA 4D1C"

```

Fulfillment license text for P1 (the old product):

Note the SUPERSEDE keyword in the license key.

```

SERVER this_host HOSTNAME=mymachine
VENDOR demo
USE_SERVER
INCREMENT F1 demo 1.0 26-dec-2008 2 SUPERSEDE="F3 F1 F2" ISSUER="My \
Corporation" ISSUED=3-oct-2008 START=2-oct-2008 SIGN="009F \
996A EA12 7504 32FE 3C14 5910 8300 5B4E 8600 57E1 EB1C A774 \
AC01 22A3"
INCREMENT F2 demo 1.0 26-dec-2008 2 SUPERSEDE="F3 F1 F2" ISSUER="My \
Corporation" ISSUED=3-oct-2008 START=2-oct-2008 SIGN="002F \
1350 4898 5A94 223E 93E2 A2AA 5400 4487 DD7A F305 9D94 87D2 \
6172 821B"
INCREMENT F3 demo 1.0 26-dec-2008 2 SUPERSEDE="F3 F1 F2" ISSUER="My \
Corporation" ISSUED=3-oct-2008 START=2-oct-2008 SIGN="0069 \
210A 84EA 4DD1 1C87 3999 88EB 2000 8D03 A3C4 ACC1 B783 6CD0 \
816F 0E7C"

```

As can be seen from these license files, the user would receive:

- 5 copies of F1 (2 copies of the F1, 1.0 feature and 3 copies of the F1, 2.0 feature)
- 5 copies of F2
- 2 copies of F3
- 3 copies of F4

If users later activate 2 copies of an upgradable line item from the Activate License page on the same host, FlexNet Operations generates the following license without using the SUPERSEDE keyword:

```
SERVER this_host HOSTNAME=mymachine
VENDOR demo
USE_SERVER
INCREMENT F2 demo 1.0 8-feb-2009 2 ISSUER="My Corporation" \
  ISSUED=3-oct-2008 START=31-oct-2008 SIGN="001D 82E1 DAA5 E0FD \
  88A9 F261 AD14 8900 AB02 9BCC F774 E196 12EF DD5B 20CD"
INCREMENT F4 demo 1.0 8-feb-2009 2 ISSUER="My Corporation" \
  ISSUED=3-oct-2008 START=31-oct-2008 SIGN="00B0 26BD FD33 FBC4 \
  68FE C9B5 C38E 3300 33F3 521F 2588 B763 9470 E2EA C1AE"
INCREMENT F1 demo 2.0 8-feb-2009 2 ISSUER="My Corporation" \
  ISSUED=3-oct-2008 START=31-oct-2008 SIGN="0080 1869 FA9D 2B87 \
  920B 16DF 0636 E200 30FE D8E8 954A 2D16 3685 7722 E64C"
```

Example of Using SUPERSEDE_SIGN

The following is an illustration of the use of the SUPERSEDE_SIGN keyword.

Product Name: P1 (F1, version 1.0) (F2, version 1.0) (F3, version 1.0)

Activation ID: Activation1

Entitlement ID: EL1

Account Name: Org1

Hostname: Mymachine

A user activates 5 out of 10 counts of the product, resulting in these license keys:

License Key for Product P1:

```
SERVER this_host HOSTNAME=Mymachine
VENDOR opsqa
USE_SERVER
INCREMENT F1 opsqa 1.0 permanent 5 2575363D2F8A ISSUER="My \
  Corporation" ISSUED=7-oct-2008 START=6-oct-2008 SIGN="004E \
  5318 9887 61FF 6F2F 9039 210E 2D00 29C0 41D9 5B9A ADBE F33E \
  1FF2 CB16" SIGN2="0099 75D7 B158 0059 9AE5 650C 977C AE00 AE32 \
  56A9 FC6C 6831 23C8 951E 7489"
INCREMENT F2 opsqa 1.0 permanent 5 25AE6544D8E1 ISSUER="My \
  Corporation" ISSUED=7-oct-2008 START=6-oct-2008 SIGN="0061 \
  68BC 9E59 962F 36AD 014B 0A52 A500 220C F2A2 50F8 B7FB C06D \
  4007 6615" SIGN2="001F E152 80F2 1858 053B D75B 3710 5500 9B82 \
  BADA 4D5C D39D 50A2 B2D3 4E56"
INCREMENT F3 opsqa 1.0 permanent 5 2DFA5C27ED28 ISSUER="My \
```



```
Corporation" ISSUED=7-oct-2008 START=6-oct-2008 SIGN="0013 \
8996 1A1D 84EF D0E1 C0EC 7B32 0600 1B07 3E12 7413 36FE 585E \
E9C0 580E" SIGN2="00B2 4E2B 4C49 DABC 2EFC 503E A6A0 9F00 D931 \
106C 0E1E 4605 489B 2410 C638"
```

Product Name: P2 (F1, 2.0) (F2, 1.0) (F4, 1.0)

Activation ID: upgraded-Act

Entitlement ID: upgraded-EL

Account Name: Org1

Hostname: Mymachine

Now, if the user upgrades 3 copies of P1 to P2, then the old license of Product P1 become obsolete, and FlexNet Operations generates the following license using the SUPERSEDE_SIGN keyword:

Fulfillment license text for Product P2 (Upgraded Product)

```
SERVER this_host HOSTNAME=Mymachine
VENDOR opsqqa
USE_SERVER
INCREMENT F2 opsqqa 1.0 7-feb-2009 3 B16BDF658A55 ISSUER="My \
Corporation" ISSUED=7-oct-2008 START=30-oct-2008 SIGN="008F \
8BE8 4D9E 5EF5 B5F7 1037 F882 8B00 CA90 C2C3 DE1F B29F 5D71 \
CEF8 4C05" SIGN2="0016 6763 55B6 CF4C 3659 02BA BE89 8300 DF02 \
36FE EB6B 133F CE15 F849 B22D"
INCREMENT F4 opsqqa 1.0 7-feb-2009 3 4072393334B7 ISSUER="My \
Corporation" ISSUED=7-oct-2008 START=30-oct-2008 SIGN="00DC \
10B8 CBAE 2B32 8EE5 7ECF 8744 7C00 9E54 0C40 7621 0697 36B4 \
EF21 555A" SIGN2="0005 84B2 3B51 D9C7 6D20 3CA0 1B47 9C00 DE53 \
C962 CC1B 745A B4E0 C962 6854"
INCREMENT F1 opsqqa 2.0 7-feb-2009 3 43026EA5EC87 ISSUER="My \
Corporation" ISSUED=7-oct-2008 START=30-oct-2008 SIGN="00A5 \
CF1B E66A 3D04 5679 B3F4 E4C6 2D00 DE42 95B4 DC62 E752 B5AC \
04AC 77AB" SIGN2="0056 719E D96A D643 51C9 3EF5 65DE E100 00E2 \
5C55 16E5 8415 EFB5 6AE5 47C5"
```

Fulfillment license text for P1 (the old product). Note the SUPERSEDE SIGN keyword in the license key.

```
SERVER this_host HOSTNAME=Mymachine
VENDOR opsqqa
USE_SERVER
INCREMENT F1 opsqqa 1.0 permanent 2 6BD0062092EC ISSUER="My \
Corporation" ISSUED=7-oct-2008 START=6-oct-2008 \
SUPERSEDE_SIGN={"F1:004E 5318 9887 61FF 6F2F 9039 210E 2D00 \
29C0 41D9 5B9A ADBE F33E 1FF2 CB16" "F2:0061 68BC 9E59 962F \
36AD 014B 0A52 A500 220C F2A2 50F8 B7FB C06D 4007 6615" \
"F3:0013 8996 1A1D 84EF D0E1 C0EC 7B32 0600 1B07 3E12 7413 \
36FE 585E E9C0 580E"} SIGN="0029 3648 50D1 9BD1 EE19 1182 6B1D \
6800 CB0E FFD6 A951 0378 518D B381 A59D" SIGN2="00DC 766F A4CB \
7FCD D1DA CB78 9C1F A400 CC6B 3060 2AC8 6823 FADF E653 21CF"
INCREMENT F2 opsqqa 1.0 permanent 2 C2B2737DA117 ISSUER="My \
Corporation" ISSUED=7-oct-2008 START=6-oct-2008 \
SUPERSEDE_SIGN={"F1:004E 5318 9887 61FF 6F2F 9039 210E 2D00 \
29C0 41D9 5B9A ADBE F33E 1FF2 CB16" "F2:0061 68BC 9E59 962F \
36AD 014B 0A52 A500 220C F2A2 50F8 B7FB C06D 4007 6615" \
"F3:0013 8996 1A1D 84EF D0E1 C0EC 7B32 0600 1B07 3E12 7413 \
```

```

36FE 585E E9C0 580E"} SIGN="0000 937B A809 AF06 5AB3 883A AEA2 \
9600 79F5 432B AF02 5722 6B16 F093 43E9" SIGN2="0046 C582 FBB5 \
E97A 8B4B D48B 6720 FE00 7BC3 AFA1 5D6D 5DCC CB1F 8561 CF2A"
INCREMENT F3 opsqa 1.0 permanent 2 8FB794EE24AA ISSUER="My \
Corporation" ISSUED=7-oct-2008 START=6-oct-2008 \
SUPERSEDE_SIGN={"F1:004E 5318 9887 61FF 6F2F 9039 210E 2D00 \
29C0 41D9 5B9A ADBE F33E 1FF2 CB16" "F2:0061 68BC 9E59 962F \
36AD 014B 0A52 A500 220C F2A2 50F8 B7FB C06D 4007 6615" \
"F3:0013 8996 1A1D 84EF D0E1 C0EC 7B32 0600 1B07 3E12 7413 \
36FE 585E E9C0 580E"} SIGN="002A EEEB AFE4 2002 D145 4082 0FAA \
7A00 CF17 2073 B7A8 BC70 EA1F 664E CB04" SIGN2="00B9 91E6 C380 \
4CF9 F1A1 660E 7C8C AB00 E511 994F 3CBE 2E71 5A1D F687 A65D"

```

A user can consolidate both of the above licenses into a single license file for convenience.

Consolidated License: CID_33c0d5d6_11cd97c2d8e__7fff

Sold To: Account

Consolidation Criteria: Server HOSTNAME=Mymachine

Consolidated License

```

SERVER this_host HOSTNAME=Mymachine
VENDOR opsqa
USE_SERVER
INCREMENT F1 opsqa 1.0 permanent 2 6BD0062092EC ISSUER="My \
Corporation" ISSUED=7-oct-2008 START=6-oct-2008 \
SUPERSEDE_SIGN={"F1:004E 5318 9887 61FF 6F2F 9039 210E 2D00 \
29C0 41D9 5B9A ADBE F33E 1FF2 CB16" "F2:0061 68BC 9E59 962F \
36AD 014B 0A52 A500 220C F2A2 50F8 B7FB C06D 4007 6615" \
"F3:0013 8996 1A1D 84EF D0E1 C0EC 7B32 0600 1B07 3E12 7413 \
36FE 585E E9C0 580E"} SIGN="0029 3648 50D1 9BD1 EE19 1182 6B1D \
6800 CB0E FFD6 A951 0378 518D B381 A59D" SIGN2="00DC 766F A4CB \
7FCD D1DA CB78 9C1F A400 CC6B 3060 2AC8 6823 FADF E653 21CF"
INCREMENT F2 opsqa 1.0 permanent 2 C2B2737DA117 ISSUER="My \
Corporation" ISSUED=7-oct-2008 START=6-oct-2008 \
SUPERSEDE_SIGN={"F1:004E 5318 9887 61FF 6F2F 9039 210E 2D00 \
29C0 41D9 5B9A ADBE F33E 1FF2 CB16" "F2:0061 68BC 9E59 962F \
36AD 014B 0A52 A500 220C F2A2 50F8 B7FB C06D 4007 6615" \
"F3:0013 8996 1A1D 84EF D0E1 C0EC 7B32 0600 1B07 3E12 7413 \
36FE 585E E9C0 580E"} SIGN="0000 937B A809 AF06 5AB3 883A AEA2 \
9600 79F5 432B AF02 5722 6B16 F093 43E9" SIGN2="0046 C582 FBB5 \
E97A 8B4B D48B 6720 FE00 7BC3 AFA1 5D6D 5DCC CB1F 8561 CF2A"
INCREMENT F3 opsqa 1.0 permanent 2 8FB794EE24AA ISSUER="My \
Corporation" ISSUED=7-oct-2008 START=6-oct-2008 \
SUPERSEDE_SIGN={"F1:004E 5318 9887 61FF 6F2F 9039 210E 2D00 \
29C0 41D9 5B9A ADBE F33E 1FF2 CB16" "F2:0061 68BC 9E59 962F \
36AD 014B 0A52 A500 220C F2A2 50F8 B7FB C06D 4007 6615" \
"F3:0013 8996 1A1D 84EF D0E1 C0EC 7B32 0600 1B07 3E12 7413 \
36FE 585E E9C0 580E"} SIGN="002A EEEB AFE4 2002 D145 4082 0FAA \
7A00 CF17 2073 B7A8 BC70 EA1F 664E CB04" SIGN2="00B9 91E6 C380 \
4CF9 F1A1 660E 7C8C AB00 E511 994F 3CBE 2E71 5A1D F687 A65D"
INCREMENT F2 opsqa 1.0 7-feb-2009 3 B16BDF658A55 ISSUER="My \
Corporation" ISSUED=7-oct-2008 START=30-oct-2008 SIGN="008F \
8BE8 4D9E 5EF5 B5F7 1037 F882 8B00 CA90 C2C3 DE1F B29F 5D71 \
CEF8 4C05" SIGN2="0016 6763 55B6 CF4C 3659 02BA BE89 8300 DF02 \
36FE EB6B 133F CE15 F849 B22D"

```

```
INCREMENT F4 opsqa 1.0 7-feb-2009 3 4072393334B7 ISSUER="My \
Corporation" ISSUED=7-oct-2008 START=30-oct-2008 SIGN="00DC \
10B8 CBAB 2B32 8EE5 7ECF 8744 7C00 9E54 0C40 7621 0697 36B4 \
EF21 555A" SIGN2="0005 84B2 3B51 D9C7 6D20 3CA0 1B47 9C00 DE53 \
C962 CC1B 745A B4E0 C962 6854"
INCREMENT F1 opsqa 2.0 7-feb-2009 3 43026EA5EC87 ISSUER="My \
Corporation" ISSUED=7-oct-2008 START=30-oct-2008 SIGN="00A5 \
CF1B E66A 3D04 5679 B3F4 E4C6 2D00 DE42 95B4 DC62 E752 B5AC \
04AC 77AB" SIGN2="0056 719E D96A D643 51C9 3EF5 65DE E100 00E2 \
5C55 16E5 8415 EFB5 6AE5 47C5"
```

As can be seen from the above license files, the user receives:

- 5 copies of F1 (2 copies of the F1, 1.0 feature and 3 copies of the F1, 2.0 feature)
- 5 copies of F2
- 2 copies of F3
- 3 copies of F4

Note that if a user activates 2 copies of an upgradable line item on the same host, FlexNet Operations generates the following license without using the SUPERSEDE SIGN keyword:

```
SERVER this_host HOSTNAME=Mymachine
VENDOR opsqa
USE_SERVER
INCREMENT F2 opsqa 1.0 7-feb-2009 2 882127379F59 ISSUER="My \
Corporation" ISSUED=7-oct-2008 START=30-oct-2008 SIGN="008A \
0A65 CAD8 DDC4 85AA 48A7 A9CA BD00 17AB 7BF8 9F2E 666A 7A53 \
E700 5375" SIGN2="0068 A545 B631 9773 9017 24BC C1C9 8D00 F062 \
1ACE 8C33 BE7C 4995 C091 2478"
INCREMENT F4 opsqa 1.0 7-feb-2009 2 09B95D118D97 ISSUER="My \
Corporation" ISSUED=7-oct-2008 START=30-oct-2008 SIGN="00F5 \
C68F 4978 FC24 ECC6 9A2D 4BAB 8300 A09B 3332 4CF3 E00C 4D9F \
4C95 2719" SIGN2="004C 09FF 27E8 B631 9320 C85E 329C 4F00 6E38 \
CCC7 81D7 9D22 1EE0 48EC 51E8"
INCREMENT F1 opsqa 2.0 7-feb-2009 2 AACDA415B7B9 ISSUER="My \
Corporation" ISSUED=7-oct-2008 START=30-oct-2008 SIGN="0041 \
7961 1A8F A373 767F B5AC BBA7 4400 18AE 38B7 296D 8038 0D16 \
4DA3 36CE" SIGN2="0013 FA4B FBA6 1CF2 39A6 D8D4 5D6D 7A00 FEED \
80E8 6765 8E56 3044 B52B F6CE"
```

Configuring the SUPERSEDE or SUPERSEDE_SIGN Keyword

The option for configuring the SUPERSEDE or SUPERSEDE_SIGN keyword is hidden. Contact Revenera support if you want to change this value.

You can use either keyword for upgrades, renewals, or both. You can use SUPERSEDE or SUPERSEDE_SIGN, but not both at the same time. By default, no keyword is used.

Generating a Stop Gap License

If a customer's license has expired and the customer has not formally renewed its entitlement, the publisher can generate a short-term stop gap license.



Task **To generate a stop gap license because a customer has not yet renewed an expired license**

1. Click **Licenses > Licenses**. This link opens the Support Licenses and Maintenance page.
2. Search for a fulfillment for which a stop gap license is to be generated. Search by **Activation ID, Product, Sold To, Hostid, or Fulfill ID**.
3. Select exactly one fulfillment ID and click **Stop Gap**. Generating a stop gap license does not cause the original fulfillment to be returned.
4. Enter a **Ship to Email** or a **Ship To Mail** address, if applicable.
5. By default, the **Start Date** of a stop gap license is the **Fulfill Date** of the original fulfillment. You can set a different **Start Date** and can set the expiration to be after a set **Duration** or to a specific **Expiration Date**.



Note - If the year that you want to set is not currently available from the calendar, select the year that is closest to the desired year. This automatically increases the list by 10 years from the year you selected.

6. No license parameters can be modified for the stop gap license. The entire count of the fulfillment is used for the stop gap license.
7. To check that the parameter values can be used to generate a valid license before actually generating a license, click **Verify**.
8. To generate an stop gap license certificate, click **Stop Gap**.
9. After a license is generated, the license text is displayed. The license text can be saved to a file on disk by clicking Save to File, or it can be sent as an email attachment by clicking **Email License**. The shipment history of this license can be displayed by clicking **Shipment Records**.

For information about the file naming conventions, see [Configuring System Settings](#).

Stop gap fulfillments appear in the **Support Licenses and Maintenance** page as Support Type **STOP GAP**.

See Also

[Emailing a License](#)

[Configuring System Settings](#)

Consolidating Licenses

License consolidation, or the generation of a single license file for several certificate-based or custom licenses, can be done during batch activation, or post-activation, from the **Support Licenses** page.

To enable this capability, the **Show Consolidate Licenses Functionality** flag must be enabled. This is configured under **System > Configure > FlexNet Operations**.



Task **To consolidate a license**

1. Click **Licenses > Licenses**. This link opens the Support Licenses and Maintenance page.
2. Select the boxes next to the fulfillments you want to consolidate. Ensure that these records meet the consolidation criteria.
3. Click **Consolidate** to view the consolidated license file. One file is generated for each group of floating or nodelocked licenses on each server.

See Also

[What is License Consolidation?](#)

Consolidated Licenses Page

The **Consolidated Licenses** lists all consolidated license files. The files are listed with the following information:

Table 4-4 • Consolidated License File Information

Information	Description
Type	Shows if the license is active or not.
Consolidated License ID	Machine-generated unique identifier for each consolidated license file.
Consolidation Criteria	Mostly lists the host ID of the machine on which node-locked or floating licenses have been consolidated.
Sold To	Name of the customer account that owns the consolidated licenses.
Consolidation Date	Date on which licenses were consolidated: not necessarily the same as activation date.

From this page you can do the following:

- Click a consolidated license ID.
- View **Shipment History** for the license.
- **View Fulfillments** contained with the consolidated license.
- Click Rehost to rehost a consolidated license.
- Save or email the license.
- If you have selected more than one file to view, you can choose among license files by selecting the appropriate **Consolidated License ID** from the drop-down list provided.
- The license text can be saved to a file on disk by clicking Save to File or it can be sent as an email attachment by clicking **Email**.

For information about the file naming conventions, see [FlexNet Operations system configuration](#) settings.

Rehosting a Consolidated License

Rehosting a consolidated license reassigns it from one host ID to another.



Task

To rehost a consolidated license

1. Click **Licenses > Consolidated Licenses**.
2. On the Consolidated Licenses page, search for the fulfillment for the license by, for example, **Consolidated License ID** or **Consolidation Criteria** (usually, a server host ID).
3. Select the box next to the fulfillment ID you want to rehost.
4. Select a new Host ID for the consolidated license. Alternatively, add a new host ID to rehost this license by creating a new host on the Create License Host page.
5. Click **Rehost**. The license is assigned to the new Host ID.

Batch Rehosting

Using the Batch Rehost feature, you can use redistribute licenses for a group of products among various license servers and change the license count of products on different servers. For example, you can change 20 licenses for Product 1 on Server A, to 10 licenses on Server A and 10 on Server B. Batch rehosting only works for counted licenses – that is, floating counted or node-locked counted models.



Task

To batch rehost a group of products

1. Click **Licenses > Batch Rehost**. This link opens the Batch Rehost - Select Customer Account Unit and Hosts page.
2. In Account, select the account for which you want to redistribute licenses.
3. Select the products whose licenses you want to redistribute, and click Next.
4. If desired, enter the common attributes you want to assign to each of the redistributed licenses, and click Next.
5. Add new hosts as needed.
6. In Final Count, enter the number of copies to assign to each selected host. (The green arrow indicates the current host assignment. The green check mark indicates that the count has been changed.) Click Next.
7. Review the summary page for your redistribution. If necessary, click Back to correct any incorrect entries. If correct, click Generate. The licenses are redistributed.

Transferring Licenses

When you transfer licenses, you move all licenses for one account from one host to another. This is typically used when a host crashes and licenses on it must be moved to a new machine.



Task **To transfer licenses from one account to another**

1. Click **Licenses > Transfer Licenses**. This link opens the Transfer Licenses page.
2. In Account, select the account from which you want to transfer licenses.
3. In Source Host, select the host of the source licenses.
4. In Target Host, select the host that you will transfer licenses to.
5. Select whether or not you want to consolidate the licenses into a single file.
6. Click **Next**.
7. On the summary page, review the details of your transfer. If necessary, click Back to correct any incorrect entries. If correct, click Transfer. The licenses are transferred to the specified host.

Manual Return

Trusted returns are normally done programmatically as transactions between a client or server activation utility and the FlexNet Operations server. The activation utility generates a request that is submitted programmatically and the FlexNet Operations server generates a response that is used to complete the return.

However, when there is no internet connection, a return request can also be generated and written to a file by a FlexNet Publisher Licensing Toolkit activation utility running on the machine from which the license will be returned.

- The file containing the request is sent to the publisher and loaded into FlexNet Operations to generate a response.
- The response is saved to a file; the file is sent to the customer and is used by the FlexNet Publisher Licensing Toolkit activation utility to process the response and return the license.



Task **To generate a response to a return request submitted in a file**

1. Instruct the customer to use the FlexNet Publisher Licensing Toolkit activation utility that you provide to generate and save to a file a return request. The activation utility requires the fulfillment ID of the license.
2. Click **Licenses > Manual Return**. This link opens the Manual Return page.
3. Browse to the XML file that contains the return request.
4. Click **Submit** to generate and [view the return response](#).

Viewing a Manual Return

Follow this procedure to view a return after you manually generate a return response.

**Task** *After a return response is generated manually*

1. Verify the Activation ID, Product, Version, Fulfillment ID, and Sold To.
2. Click **Save to File** to save this response to a file. The default file name is responseXML.xml.
3. Send the file to the customer with instructions for using the activation utility to process the response and return the license.

Manual Repair

Trusted repairs are normally done programmatically as transactions between a client or server activation utility and the FlexNet Operations server. The activation utility generates a request that is submitted programmatically and the FlexNet Operations server generates a response that is used to complete the repair.

However, a repair request can also be generated and written to a file by a FlexNet Publisher Licensing Toolkit activation utility running on the machine on which the license will be repaired.

- The file containing the request is sent to the publisher and loaded into FlexNet Operations to generate a response.
- The response is saved to a file; the file is sent to the customer and is used by the FlexNet Publisher Licensing Toolkit activation utility to process the response and repair the license.

**Task** *To generate a response to a repair request submitted in a file*

1. Instruct the customer to use the FlexNet Publisher Licensing Toolkit activation utility that you provide to generate and save to a file a repair request. The activation utility requires the fulfillment ID of the license.
2. Click **Licenses > Manual Repair**.
3. Browse to the XML file that contains the repair request.
4. Click **Submit** to generate and [view the repair response](#).

Viewing a Manual Repair

Follow this procedure to view a repair after you manually generate a repair response.

**Task** *After a repair response is generated manually*

1. Verify the Activation ID, Product, Version, Fulfillment ID, and Sold To.
2. Click **Save to File** to save this response to a file. The default file name is responseXML.xml.
3. Send the file to the customer with instructions for using the activation utility to process the response and repair the license.

Short Code Return

Trusted returns are normally done programmatically as transactions between a client or server activation utility and the FlexNet Operations server. The activation utility generates a request that is submitted programmatically and the FlexNet Operations server generates a response that is used to complete the return.

However, some customer environments do not support communication with the FlexNet Operations server. If the publisher created a short code ASR that was packaged with the software, whether the license was activated with short code or programmatically, it can be repaired using a short code.

A FlexNet Publisher Licensing Toolkit activation utility, running on the machine from which the license is to be returned, uses the short code ASR to generate a short request code.

- The short request code is sent to the publisher, who loads it into FlexNet Operations to generate a short response code.
- The response code is saved to a file and sent to the customer, who uses the FlexNet Publisher Licensing Toolkit activation utility to process the response and return the license.



Task *To allow a customer to return a license with a short response code*

1. The customer's license must have been activated with a short code ASR, the short code ASR must have been packaged with the product, and the activation utility must be able to generate a short code return request and process a short code return response. The license to be returned may have been originally activated online or with a short code request.
2. Instruct the customer to use the FlexNet Publisher Licensing Toolkit activation utility, which you provide, to generate a short code return request using the short code ASR file.
3. Receive the generated short code from the customer, along with the activation ID (or web register key) used to activate the original license.
4. Click **Licenses > Short Code Return**.
5. Enter values in the following fields.

Table 4-5 ▪ Short Code Return Fields

Field	Description
Short Request Code	Short code return request generated by the FlexNet Publisher Licensing Toolkit activation utility and sent by the customer.
Activation ID	Activation ID or a Web register key associated with the short code ASR's bulk entitlement.
Reason for Return	Reason for the short code return, if any: REHOST, UPGRADE, UPSELL, UPGRADE, RENEW.

6. Click Generate to generate and [view the short response code](#).

Viewing a Short Code Return

Follow this procedure to view a short code return after you manually generate a short code return response.



Task *After a short code return response is generated manually*

1. Save the response code to a file.
2. Send the file to the customer with instructions for using the activation utility to process the response and return the license.

Short Code Repair

Trusted storage repairs are normally done programmatically as transactions between a client or server activation utility and the FlexNet Operations server. The activation utility generates a request that is submitted programmatically and the FlexNet Operations server generates a response that is used to complete the repair.

However, some customer environments do not support communication with the FlexNet Operations server. If the publisher created a short code ASR that was packaged with the software, the customer who originally activated the license with that short code ASR can use the short code ASR file to generate a short code request to repair the license.

A FlexNet Publisher Licensing Toolkit activation utility, running on the machine on which the license is to be repaired, uses the short code ASR to generate a short request code.

- The short request code is sent to the publisher, who loads it into FlexNet Operations to generate a short response code.
- The response code is saved to a file and sent to the customer, who uses the FlexNet Publisher Licensing Toolkit activation utility to process the response and repair the license.



Task *To allow a customer to repair a license with a short response code*

1. The customer's license must have been activated with a **short code ASR**, the short code ASR must have been packaged with the product, and the activation utility must be able to generate a short code repair request and process a short code repair response. The license to be repaired may have been originally activated online or with a short code request.
2. Instruct the customer to use the FlexNet Publisher Licensing Toolkit activation utility, which you provide, to generate a short code repair request using the short code ASR file.
3. Receive the generated short code from the customer, along with the activation ID (or Web register key) used to activate the original license.
4. Click **Licenses > Short Code Repair**.

- Enter values in the following fields.

Table 4-6 ▪ Short Code Repair Fields

Field	Description
Short Request Code	Short code repair request generated by the FlexNet Publisher Licensing Toolkit activation utility and sent by the customer.
Activation ID	Activation ID or a Web register key associated with the short code ASR's bulk entitlement.

- Click Generate to generate and [view the short response code](#).

Viewing a Short Code Repair

Follow this procedure to view a short code repair after you manually generate a short code repair response.



Task *After a short code repair response is generated manually*

- Save the response code to a file.
- Send the file to the customer with instructions for using the activation utility to process the response and repair the license.

Supporting Hosts

You can view fulfillment or license information associated with previously-defined hosts.



Task *To manage host information*

- Click **Licenses > Hosts**.
- Select the host you want to view or manage information for.
- Do one of the following:
 - Click **View Fulfillments** to view fulfillments associated with the host.
 - Click **Download License** to download license files associated with the host. Choose a location to save the license file to, then click **OK**.
 - For a manual, replacement license technology, click **Set License** to set the license file information for the host. Then complete the requested information for your license file.
 - Click **Delete** to delete the host from FlexNet Operations.
 - Click **Transfer** to move the selected hosts (and their entitlements) to a different account. (See [Transferring Hosts](#).)

Transferring Hosts

Transfer Hosts allows you to transfer fulfillments from one or more hosts to a related account.



Note - When a host is moved, entitlements that belong to devices assigned to that host are moved as well. The result of the move is to either create new entitlements for the target account or to pool the line items—incrementing the counts of the target account's existing (and matching) entitlements by the counts on the hosts' entitlements that were moved.



Task

To transfer hosts

1. In the Producer Portal, click **Licenses > Hosts**. On the Hosts page you can select hosts to transfer.
2. On the Hosts page, select the hosts you want to transfer and click **Transfer**. This button opens the Transfer Hosts page.
3. On the Transfer Hosts page, set the **Target Account**:
 - a. Click the **Search Account** button to open the Select Account page in a pop-up window.
 - b. Select the customer account to which you want to move the selected hosts.
 - c. Click **OK**. This button closes the Select Account window and returns you to the Transfer Hosts page. Note that the Target Account is now set to the account you selected.
4. Next, choose a setting for **Pool Line Items**:
 - **Yes**—If matching entitlements exist in the target account, those entitlements are incremented by the counts in the hosts' entitlements. Otherwise, if no matching entitlements exist, new entitlements are created at the target account.
 - **No**—FlexNet Operations creates new entitlements at the target account, even if matching entitlements already exist.
5. Click **Transfer**. FlexNet Operations queues the transfer for processing.
6. Click **Complete**.



Note - You can check the status of the host transfer job by its Job ID on the **Host Transfer Jobs** page. To go to the Host Transfer Jobs page, click **Licenses > Host Transfer Jobs**.

Supporting Embedded Licenses

To support embedded licenses, you can easily add or delete additional licenses, or re-allocate them between devices, in response to customer demands, maintenance, or market conditions. Some of the operations you can perform include:

- RMAs: Return material authorization
- Upgrades

- Transfers
- Temporary (emergency or stop-gap, for example) licenses



Task **To edit additional licenses for a particular device**

1. Click **Devices > Search Devices**. The Producer Portal opens the Search Devices page.
2. Specify search criteria to locate the device you want to change and click **Search**.
3. From the list of devices, select a device to manage.
4. Under Entitlements, edit the entitlements for the selected device.

Changes to additional licenses are not performed in real time, but take effect on each device the next time the affected devices connect to FlexNet Operations, or the next time the license is copied by a user to a given device.

Pre-installed licenses are not transferable between devices.

Return Material Authorizations (RMAs)

A customer might be required to return a malfunctioning device to a manufacturer or reseller, and get a new device. The existing license is transferred to the new device. This process is known as a return material authorization (RMA).

After you have determined that a device must be replaced, you can process the RMA in FlexNet Operations.



Task **To process an RMA**

1. Click **Devices > Search Devices**. The Producer Portal opens the Search Devices page.
2. Specify search criteria to locate the device you want to change and click **Search**.
3. From the list of devices, click the ID for the old device. This link opens the View Device page.
4. Click **Edit > Make Obsolete**.
5. Click **Devices > Create Device** and create a new device with the same characteristics as the old, but a new Device ID.
6. Click **Licenses > Map Entitlements**. The Producer Portal opens the Map Entitlements page where you select the entitlement line items for the new device (which is the same as the old device).
7. Under **Entitlements Available**, specify the amount to add in **Qty to Add** for the entitlements you want to map, and click **Save**.

A newly authorized device has been created in FlexNet Operations.

Upgrades, Renewals, and Upsells

upgrade — Transferring a customer from a specified version of a product to a more recent version of the same product, with potentially new features.

renewal — Extending the expiration date of a license to a later date.

upsell — Transferring a customer to an expanded version of the same product that provides more functionality.

These three processes are supported for FlexNet Embedded licenses and work the same way.



Task *To process an upgrade, renewal, or upsell manually*

1. Create an entitlement representing the upgraded/renewed/upsold product. For example, if the regular entitlement gives access to a feature, the upgrade entitlement would represent the new or expanded feature.
2. Click **Devices > Search Devices**. The Producer Portal opens the **Search Devices** page.
3. Specify search criteria to locate the device you want to change and click **Search**.
4. From the list of devices, click the ID for device to upgrade/renew/upsell. This link opens the **View Device** page.
5. Click **Licenses > Remove Licenses**.



Important • Note the following limitations:

- On a CLS instance, licenses for counted features that are currently in use cannot be removed. You must unmap used licenses first before deleting them. At any one time, you can remove licenses from a total of five activation IDs.
 - On a local license server, only concurrent licenses that are not in use can be removed. To remove used licenses, you must unmap the licenses before deleting them. Licenses that are currently in use cannot be removed.
 - Only unused licenses for metered features can be removed from an auto-provisioned license server (using **Licenses > Remove Licenses**).
6. Under **Licenses Currently Mapped**, specify the amount to remove in **Qty to Remove**, and click **Save**. The previously assigned counts are added back to the entitlement. The entitlements can now be assigned to new devices.
 7. Click **Licenses > Map Entitlements**. The Producer Portal opens the **Map Entitlements** page, where you select the upgraded/renewed/upsold entitlement line items for the device.
 8. Under **Entitlements Available**, specify the amount to add in **Qty to Add** for the entitlements you want to map, and click **Save**.

About Automatic Version Upgrades, Renewals, and Upsells for Devices and Servers

For FlexNet Operations to apply the automatic upgrade, renewal, or upsell process, you must create relationships between the two product versions and between the two entitlement line items for those product versions.

When mapping an upgrade entitlement to a device that already has copies of the related pre-installed entitlement, FlexNet Operations automatically reduces the copies of the pre-installed entitlement by the number of copies of the upgrade entitlement being mapped. This is particularly helpful as the copies are shared between the pre-installed entitlement and the upgrade entitlement, and frequently the upgrade entitlement cannot be mapped until copies of the pre-installed entitlement are unmapped (to free up available copies).

The return of the pre-installed copies skips the normal confirmation process, as the returned copies are immediately consumed by the upgrade being mapped. Also, for the same reason, potential limitations for duration based entitlements do not apply.

Limitations:

- You are not permitted to mix the different relationship types within a single parent-child chain of product relationships.
- The type of relationship—upgrade, renewal, or upsell—you use in the product relationship must be the same as the type of relationship between the entitlement line items.
- The application does not support multiple upgraded products that have the same parent.
- The application does not support a child entitlement having a higher license quantity than its parent. In this case, you must create two entitlement lines: one that is for the same quantity as the parent and one that is for the remaining extra quantity.
- If there are no copies currently available for an upgrade entitlement, the **Map Entitlements** page does not show the upgrade entitlement as an option to map, even if there are copies of the pre-installed entitlement mapped to the device being acted on (that could be automatically returned to enable the operation to succeed). Activation via capability request does not have this limitation.
- If both pre-installed and upgrade entitlements are specified in a capability request, the order in which they are listed matters. If the pre-installed entitlement is listed first, the mapped copies are unmapped by the upgrade item listed second (if the upgrade copies requested are greater or the same; some are left if the pre-installed request is for more copies). If the pre-installed entitlement is listed second, it is successfully mapped in addition to the upgrade listed first. When the same is done from the user interface, the result is not well defined.
- If a device has a device series limiting the copies of a feature in the upgrade/pre-installed entitlement, the feature-limiting logic does not properly take into account the copies being returned in the pre-installed entitlement and may prevent mapping via the user interface.



Tip ▪ FlexNet Operations can automatically upgrade line items for qualifying products and line items with the Product Version Upgrade job. See [FlexNet Operations Alert Types](#).

Transfers

Transferring licenses is defined as the process of moving licenses from one device to another. A publisher can define policies to control the number of rehosts in a given duration of time per line item. This policy can be defined on license model or the entitlement line item.



Task

To process a transfer

1. Click **Devices** > **Search Devices**. The Producer Portal opens the Search Devices page.
2. Specify search criteria to locate the device you want to change and click **Search**.
3. From the list of devices, click the ID for the old device. This link opens the View Device page.
4. Click **Licenses** > **Remove License**.

5. Under Licenses Currently Mapped, specify the amount to remove in **Qty to Remove**, and click **Save**. The previously assigned counts are added back to the entitlement. The entitlements can now be assigned to new devices.
6. Click **Devices > Create Device** and create a new device with the same characteristics as the old, but a new Device ID.
7. Click **Licenses > Map Entitlements**. The Producer Portal opens the Map Entitlements page where you select the entitlement line items for the new device (which is the same as the old device).
8. Under **Entitlements Available**, specify the amount to add in **Qty to Add** for the entitlements you want to map, and click **Save**.

A newly authorized device has been created in FlexNet Operations.

Temporary (Emergency and Stop-Gap) Licenses

Temporary licenses are limited in duration for a specific purpose. A temporary license can be issued in the following circumstances:

- An emergency license allows a customer to temporarily move features from an old device to a new device.
- A stop-gap license allows a customer to temporarily use an expiring license until another license can be issued.
- A temporary license allows a customer to demonstrate a product for trial purposes, and expires after a short trial period.



Task **To issue a temporary license**

1. Create a limited-duration entitlement representing the upgraded product.
2. Click **Devices > Search Devices**. The Producer Portal opens the Search Devices page.
3. Specify search criteria to locate the device you want to change and click **Search**.
4. From the list of devices, click the ID for device to change. This link opens the View Device page.
5. Click **Licenses > Map Entitlements**. The Producer Portal opens the Map Entitlements page where you select the temporary entitlement line items for the device.
6. Under **Entitlements Available**, specify the amount to add in **Qty to Add** for the entitlements you want to map, and click **Save**.

The Producer Portal maps the entitlement line items to the current device and shows its View Device page.

Supporting Offline Device Activation

If necessary, FlexNet Operations can be used to upload license requests (Generate License) and download both pre-installed and additional licenses.

Table 4-7 •

Topics	Description
Offline Activation: Generating a License	Steps through the process of uploading a binary license request file.
Offline Activation: Downloading a Pre-Installed License	Describes how to download a previously generated, pre-installed license.
Offline Activation: Downloading an Additional License	Describes how to download a previously generated, additional license.

Offline Activation: Generating a License

Some devices may follow an offline activation model in which the device generates a binary license request file (for an additional license) that can be manually uploaded on the FlexNet Operations Producer Portal or the End-User Portal. FlexNet Operations processes the request file to generate a license appropriate for the request.

If the license request is made for an existing device, FlexNet Operations generates a regenerative license. If the request is made for a new device, FlexNet Operations enters the device into the system, adds the corresponding entitlement, and generates a license for it.



Task

To upload a license request file for an existing device

1. Click **Devices > Search Devices**. The Producer Portal opens the Search Devices page.
2. Specify search criteria to locate the device you want to change and click **Search**.
3. From the list of devices, click the ID of the device for which you want to upload a license request. This link opens the View Device page.
4. Click **Browse** and locate the license request file on your local system. (Button names vary depending on the web browser you are using.)
5. Click **Upload Capability Request**.

The Producer Portal uploads the request file. FlexNet Operations generates a regenerative license.



Task **To upload a license request file for an existing license server**

1. Click **Devices > Search License Servers**. The Producer Portal opens the Search License Servers page.
2. Specify search criteria to locate the server you want to change and click **Search**.
3. From the list of devices, click the ID of the server for which you want to upload a license request. This link opens the View Server page.
4. Click **Browse** and locate the license request file on your local system. (Button names vary depending on the web browser you are using.)
5. Click **Upload Request**.

The Producer Portal uploads the request file. FlexNet Operations generates a regenerative license.



Task **To upload a license request file for a new device**

1. Click **Licenses > Offline Device Activation**. The Producer Portal opens the Generate License page.
2. On the Generate License page, click **Browse**. (Button names vary depending on the web browser you are using.)
3. Click **Upload Request**.

The Producer Portal uploads the request file. FlexNet Operations enters the device into the system, adds the corresponding entitlement, and generates a license for it.

Offline Activation: Downloading a Pre-Installed License

You can download a license response file for a pre-installed license after the pre-installed license has been generated.



Task **To download a pre-installed license**

1. Click **Devices > Search Devices**. The Producer Portal opens the Search Devices page.
2. Specify search criteria to locate the device you want to change and click **Search**.
3. From the list of devices, click the ID of the device for which you want to download a license. This link opens the View Device page.
4. Click **View > Download License File**.

The Producer Portal downloads the license response file (license.bin) to your local machine.

Offline Activation: Downloading an Additional License

You can download a license response file for an additional license after the license has been generated.



Task

To download an additional license

1. Click **Devices > Search Devices**. The Producer Portal opens the Search Devices page.
2. Specify search criteria to locate the device you want to change and click **Search**.
3. From the list of devices, click the ID of the device for which you want to download a response. This link opens the View Device page.
4. Click **View > Download Response**.

The Producer Portal downloads the license response file as a binary (typically <device ID>.bin) to your local machine.

Managing Devices

Producers who use FlexNet Embedded licensing can manage their devices from the **Devices** menu.

Use the topics in this section to learn more about managing FlexNet Embedded devices.

Table 5-1 -

Topic	Description
About Device Management	Introduces FlexNet Embedded licensing concepts and discusses device and server attributes, management, and support.
Listing Devices	Shows how to list existing devices.
Filtering the Devices List	Explains how to filter the devices list by device type and activation status.
Previewing Licenses on a Device	Explains how to quickly view which licenses are on a device.
Searching for Devices	Shows how to search for devices.

Table 5-1 •

Topic	Description
Viewing Devices	<p>Explains how to view a device, its device history, and so on. The tasks described here explain how to use the commands in the View menu on the default view for a device or server page.</p> <ul style="list-style-type: none"> ● Viewing this Device ● Viewing a Server's Binding-Break Status ● Viewing a Server's Served Devices ● Viewing Device History ● Viewing Device Requests ● Viewing a Vendor Dictionary for a Device ● Downloading a License File for a Device ● Viewing a License File for a Device ● Downloading a Response for a Device Request ● Viewing a Response for a Device Request ● Viewing Standalone Device Updates
Creating Devices	<p>Explains how to create a device.</p>
Editing Devices	<p>Explains how to edit a device's attributes, assign it to an account, and so on. The tasks described here explain how to use the commands in the Edit menu on the default view for a device or server page.</p> <ul style="list-style-type: none"> ● Editing Device Attributes ● Adding a Pre-installed Product to a Device ● Assigning an Account to a Device ● Associating a Device with a Device User ● Returning a Device ● Moving a Device ● Making a Device Obsolete
Working with Licenses on a Device	<p>Describes how to add entitlements to, and remove licenses from devices.</p> <ul style="list-style-type: none"> ● Mapping an Entitlement ● Mapping Entitlements by Activation IDs ● Removing Licenses

Table 5-1 ▪

Topic	Description
Supporting Devices	Shows how to generate license files and capability responses, and how to manually upload capability requests for devices. <ul style="list-style-type: none"> ● Generating a License File ● Generating a Capability Response ● Uploading a Capability Request from the Device Page
Offline Device Management	Describes offline device management activities. <ul style="list-style-type: none"> ● Uploading a Capability Request from the Offline Device Management Page ● Uploading Synchronization History

See Also

[Administering Device and License Server Setup](#)
[Configuring Embedded Devices Settings](#)

About Device Management

The following topics discuss FlexNet Embedded licensing concepts.

Table 5-2 ▪

Topic	Description
About Standalone Devices, Servers, and Served Devices	Introduces the concepts of FlexNet Embedded devices, servers, and served devices.
About Device Ownership	Discusses how ownership originates and flows with transactions in FlexNet Operations.
About Device Attributes	Describes the attributes of standalone and served devices. These attributes are important when creating or editing devices, as well as for device searches.
About Server Attributes	Describes attributes of servers. These attributes are important when creating or editing servers, as well as for server searches.
About Device Status	Discusses the possible states for devices.
About Overriding the Expiration Date of an Entitlement	Discusses the conditions under which a license expiration date can be overridden on a device and the limitations of doing so.
About the Device–Device User Association	Describes what a device user is, the system configuration options, and the user permissions required to view and edit device users.

See Also

[Administering Device and License Server Setup](#)
[Managing Devices](#)

About Standalone Devices, Servers, and Served Devices

A device is a hardware component that has its features licensed using FlexNet Embedded (FNE). Examples of devices include high-end medical equipment, routers, and microchip ID scanners.

A device is identified by a device ID and its type. Device types are:

- **Standalone Device**—FlexNet Embedded device that connects to FlexNet Operations, which manages device ownership, state, features, and more. See [Creating Devices](#) for more information.
- **Anonymous Device**—A type of standalone device that connects to FlexNet Operations but that is not assigned to an account. Anonymous devices are typically devices that are sold to a single end user, or those running software that is not licensed.
- **Server Device**—FlexNet Embedded server that communicates with FlexNet Operations to manage device ownership, state, and features for a collection of served devices. (When a FlexNet Embedded server is used, its served devices connect with the FlexNet Embedded server rather than connecting directly to FlexNet Operations.)
- **Served Device**—FlexNet Embedded device that is managed via a FlexNet Embedded server. In FlexNet Operations, served devices are essentially read-only entities.

For more information about FlexNet Embedded licensing, see your FlexNet Embedded documentation.

See Also

[Administering Device and License Server Setup](#)
[About Device Management](#)
[Managing Devices](#)

About Device Ownership

For any device that exists in the Producer Portal, producers can perform all device management actions that are possible for a user with their roles and permissions. Typically, producers can create devices, view a device, map entitlements, remove licenses, and so forth. However, by default, mapping entitlements to a device involves an ownership check.

In the End-User Portal, the device owner always retains full control over the device and the licenses on it. But for users in other accounts, the visibility and control of devices depends upon multiple factors, mainly related to the end user's accounts, the accounts that are on entitlements, and the accounts that own the device.

These factors, along with expected behavior in both the Producer Portal and End-User Portal, are discussed in detail in the following subsections:

- [Ownership Account Check](#)
- [Skip Account Check](#)
- [Assignment of Ownership for Unowned Devices](#)
- [Device Visibility in the End-User Portal](#)



Note ▪ In all cases, users working with devices must have the appropriate permissions to interact with them. For example, users who do not have roles with the **Manage Devices** permission cannot make changes to FlexNet Embedded devices.



Tip ▪ In the Producer Portal, producers can directly assign device ownership to an end user or partner account from the default view for a device or server page. For instructions, see [Assigning an Account to a Device](#).

Ownership Account Check

By default, FlexNet Operations performs an account check when entitlements are mapped to a device. Different factors are considered for this account check, depending on whether entitlements are being mapped in the Producer Portal or the End-User Portal.

In the Producer Portal, producers can map entitlements from the device owner's account or its sub-accounts to any device that account owns (or any unowned device). Entitlements that belong to other accounts outside the device owner's sub-account hierarchy cannot be mapped.

In the End-User Portal, the account check compares the user's accounts, entitlement accounts, and device owner accounts when entitlements are mapped to a device. Specifically, in the End-User Portal,

- Users can map any entitlement owned by their accounts to any device they can see in the End-User Portal. (See [Device Visibility in the End-User Portal](#), below, to learn about which devices a user can see in the End-User Portal.)
- Users with roles that include the **View Child Devices** permission can also map entitlements owned by sub-accounts of their accounts.
- Users with roles that include the **Claim Device and Activate** permission can also map their entitlements to unowned devices if they can identify the device by its device ID.

Producers can configure FlexNet Operations to permit mapping of entitlements from unrelated accounts on the same device by enabling the **Skip Account Check** system configuration setting.

Skip Account Check

The ownership check that FlexNet Operations performs by default can be ignored by enabling the **Skip Account Check** system configuration setting. This setting removes the account check ordinarily performed when an entitlement is mapped to a device. Because the account check is not performed, FlexNet Operations permits entitlements that belong to accounts unrelated to the device owner to be mapped.



Note ▪ The **Skip Account Check** system configuration setting applies to certain activations (End-User Portal, Web Service activations, and capability requests) that map new activation IDs or increase quantities.

In the Producer Portal, skipping the account check allows producers to map any entitlement to a device regardless of which account owns the device. The account check is not used.

In the End-User Portal, skipping the account check permits users to map entitlements to devices that are owned by unrelated accounts. With **Skip Account Check** turned on, End-User Portal users can perform all the operations permitted when the account check is run. But they can also map any of their entitlements to any device as long as they know its device ID and the activation IDs of the entitlements. (Standard permission requirements apply.)

End users with entitlements on a device owned by an unrelated account can only manage their own entitlements (removing licenses or reducing quantities) on that device.

Channel partner users can only manage entitlements for which they are a distribution partner.



Important - Channel partners cannot map entitlements to devices unless the **Skip Account Check** system configuration setting is enabled.



Note - In the End-User Portal, skipping the account check applies only to mapping methods for which the user is free to specify device IDs and activation IDs: capability requests, mapping by activation ID, and claiming and activating. It does not apply for methods in which the system pre-determines the list of available entitlements (based on account check rules), such as mapping an entitlement to a device.



Tip - To enable this system configuration setting, click **System > Configure > FlexNet Operations** and, in the **Embedded Device Settings** group, select the check box for **Skip Account Check**.

Assignment of Ownership for Unowned Devices

As new devices are created, the account that owns the device is determined by a number of different factors. Devices can be created in FlexNet Operations manually or programmatically. For example, producers can manually create a device via the Producer Portal, as described in the instructions in [Creating Devices](#).

In some cases, such as when a device is manually created in the End-User Portal, ownership is assigned when the device is created. In other cases, devices are created without an owner.

Unowned devices can be claimed by end users in the End-User Portal or can be assigned an owner by the producer in the Producer Portal.

- For producers, the process of assigning an owner account to an unowned device is relatively simple and direct. (See [Assigning an Account to a Device](#) for instructions.) The specified account becomes the device owner.
- In the End-User Portal, the process of claiming and activating a device can also assign an owner to an unowned device. When an end user clicks **Devices > Claim and Activate**, the End-User Portal shows the **Claim and Activate** page. On this page, the user identifies the device—typically by specifying its device ID—and then lists one or more activation IDs for licenses to activate on that device. In this process, for an unowned device, the account to which the first activation ID belongs becomes the owner of the device.



Tip - **Claim and Activate** only appears in the **Devices** menu of the End-User Portal for users with roles specifically granted the End-User Portal permissions, **Claim Device and Activate** and **Generate Licenses**. (By default, only the Producer Portal system administrator role has this permission; no End-User Portal roles have this permission.) See [FlexNet Operations Permissions](#) for more information about these permissions.

Device Visibility in the End-User Portal

A user's ability to see a device in the End-User Portal depends on the accounts he or she belongs to and the user's relationship (if any) with the account that owns the device. The visibility of devices to End-User Portal users also depends on whether or not one of the user's accounts (or sub-accounts thereof) has an entitlement mapped to the device.

Device Visibility Guidelines

The following organizational and entitlement factors determine which devices are visible to an end user:

- Devices that are owned by an account to which a user belongs are visible.
- Devices that are owned by a sub-account of the accounts to which a user belongs are also visible, if the user has a role with **View Child Devices** permission.
- Devices with an entitlement that belongs to one of the user's accounts are visible to that user.
- Devices with an entitlement that belongs to a sub-account of the user's accounts are also visible, if the user has a role with **View Child Devices** permission. (This is true even if the device itself is not owned by any of the user's related accounts.)
- For channel partner users, devices with an entitlement for which the channel partner account is a distribution partner are visible.
- For channel partner users, devices with an entitlement for which one of the sub-accounts to the user's account is a distribution partner are also visible, if the user has a role with the **View Child Devices** permission.

Devices that are visible to an end user appear in search results for devices.

Restricted Information on the View Device and View Server Pages

The end user can see these devices, but not all details about the device are shown in cases where none of the end user's related accounts is the device owner. In particular, while the activation IDs of licenses owned by an end user's accounts (or their sub-accounts) are shown, the activation IDs of unrelated accounts are masked—all but the last three characters of the activation ID are replaced with asterisks.

Similarly, channel partner users can see all the entitlements on a visible device, but the End-User Portal masks the activation IDs of the entitlements for which the channel partner is not a distribution partner. And, for greater privacy among producers, distributors, resellers, and end customers, entitlements that belong to accounts other than the channel partner account or its sub-accounts do not show the account that owns the entitlement. In these cases, instead of the owner account, they see Name Withheld.

(For more information about channel partner accounts, see [Account Types](#) and [Partners and Distribution Tiers](#) in the [About Accounts](#) section.)

See Also

[Assigning an Account to a Device](#)
[Managing Accounts and Users](#)

About Device Attributes

The following attributes are used when creating, editing, and searching for standalone and served devices. Some of the attributes do not apply to anonymous devices (devices that are not assigned to an account), as indicated in the table below.

Table 5-3 -

Attribute	Description
Activation ID	An activation ID associated with the device. Exception: Anonymous devices are not associated with an activation ID.
Device ID	The device's unique identity.
Device ID Type	One of several possible device host ID types. <ul style="list-style-type: none">● Ethernet● Internet● Internet IPV6● FlexID 9● FlexID 10● String● User● VM UUID● Container Id● Extended● Publisher defined
Device Model	The device's model. When creating a device, you can choose from existing device models or keep the default setting: Use Default Device Model . See Managing Device Models for more information about models.
Device Name	A short, alternate name for the device.
Entitlement ID	An entitlement ID associated with the device. Exception: Anonymous devices are not associated with an entitlement ID.
Identity	The publisher identity to use for the current device. When creating a device, you can choose from existing identities or keep the default setting: As Defined by Device Model . See Managing Publisher Identities for more information about identities.
Last Modified	The last date that the device was changed, or had entitlements mapped or licenses removed. For served devices, the date is updated when a sync record is processed.

Table 5-3 •

Attribute	Description
Notes	Additional information about the device for internal use by the producer's account.
Account ID	The ID of the customer or partner account that owns the device. Exception: Anonymous devices are not associated with an account.
Account Name	The name of the customer or partner account that owns the device. Exception: Anonymous devices are not associated with an account.
Part Number	The part number of the device.
Pre-installed Product	The product that determines the features included in the pre-installed license for the device. Pre-installed product settings also determine the license model, license model attributes, and expiration terms used for the pre-installed product on the device. If no pre-installed product is specified, the device inherits the pre-installed product that was added to its device model. If no pre-installed product is specified in the device model, the device includes no built-in features in its pre-installed license. Exception: Preinstalled products cannot not specified for anonymous devices.
Product, Product Name	The name of a product on the device. Exception: Products cannot not specified for anonymous devices.
Served by Server ID	The ID of the server for a device whose type is SERVED_CLIENT.
Site Name	The device's site name.
Status	The status of the device. See About Device Status for information about possible status values.
Type	CLIENT for standalone devices (including anonymous devices), SERVED_CLIENT for served devices.
User	The device user associated with the device. See About the Device-Device User Association for more information about device users.
Updates	The update activity for a device. In the Devices grid view, the Updates column displays either Updates with a link to the Updates tab for that device or No updates . Hovering over the Updates link triggers a pop-up that contains the update name, update ID, the status of the update and the date of the last activity. See Creating Devices for more information.

See Also

[About Server Attributes](#)
[About Device Management](#)
[Managing Devices](#)

About Server Attributes

The following attributes are used when creating, editing, and searching for servers.

Table 5-4 •

Attribute	Description
Backup License Server ID	The ID of the server's backup server.
Deployment	The deployment type for the server. Choose from Local License Server and Cloud Licensing Service .
Device Name	A short, alternate name for the server.
Host ID Type	<p>One of several possible device host ID types.</p> <ul style="list-style-type: none">● Ethernet● Internet● Internet IPV6● FlexID 9● FlexID 10● String● User● VM UUID● Container ID● Tolerant● Extended● Publisher defined <p>Host ID Type is not shown for servers with the Cloud Licensing Service deployment type. In this case, the host ID type is set by the Server Host Type.</p>
Identity	The publisher identity to use for the current server. When creating a server, you can choose from existing identities or keep the default setting: As Defined by Server Host Type . See Managing Publisher Identities for more information about identities.
Last Modified	The last date that the server was changed, had entitlements mapped, or had licenses removed.

Table 5-4 •

Attribute	Description
License Server ID	<p>A unique identity for the server.</p> <p>License Server ID is not shown for servers with the Cloud Licensing Service deployment type. In this case, FlexNet Operations automatically generates a License Server ID. (The License Server ID serves as the instance ID to identify this server in endpoint URLs.)</p>
Notes	Additional information about the device for internal use by the producer's account.
Account	The name of the account specified in Account ID .
Account ID	The account ID for the owner, enterprise, or other account that currently holds the device.
Pre-installed Product	<p>The product that determines the features included in the pre-installed license for the server. Pre-installed Product settings also determine the license model, license model attributes, and expiration terms used for the pre-installed product on the server.</p> <p>If no pre-installed product is specified, the server inherits the pre-installed product that was added to its server host type. If no pre-installed product is specified in the server host type, the server includes no built-in features in its pre-installed license.</p>
Server Host Type	The server host type for the device. When creating a server, you can choose from existing server host types or keep the default setting: Use Default Server Host Type . See Managing Server Host Types for more information about server host types.
Site Name	Site Name is optional for local license servers but required for servers that use the Cloud Licensing Service deployment type. The Site Name is a label used to distinguish between different servers when a customer account is given multiple Cloud Licensing Service servers.
Status	The status of the server. See About Device Status for information about possible status values.
Type	SERVER for a license server.
User	The device user associated with the server. See About the Device-Device User Association for more information about device users.

See Also

[About Device Attributes](#)
[About Device Management](#)
[Managing Devices](#)

About Device Status

FlexNet Embedded device status is indicated on various pages of the Producer Portal.

Device Status for Standalone Devices and Servers

The state of a device or server is indicated by its status in the devices list of the search results, and its default view for a device or server page. A device or server's status can be **ACTIVE**, **RETURNED**, or **OBSOLETE**.

The status of a device affects the types of operations you can perform on that device.

- **Active**—An active device can be the target for any normal operation (like activation, download, and return).
- **Returned**—When a device is returned, its licenses can be moved to a designated device or, if no target device is provided, those licenses are returned to the pool. The returned state is permanent; returned devices cannot be made active again.
- **Obsolete**—When a device is made obsolete, its licenses are unmapped and returned to the pool, and the device is unable to acquire licenses. The device ID of a device that is made obsolete also changes to reflect its status. FlexNet Operations appends **-OBSOLETE-`<datetime>`** to the end of the device ID value. The obsolete state is permanent; obsolete devices cannot be made active again.

Device Status for Served Devices

The status of served devices appears in the same locations on the Producer Portal, but it is not managed on the Producer Portal. (You cannot manually make a served device obsolete.) The possible status values for a served device include normal, returned, dropped, and expired.

- **Normal**—Served device is operating and currently managed by its parent FlexNet Embedded server.
- **Returned**—Served device still belongs to the FlexNet Embedded server, but has returned all its licenses to the entitlement pool.
- **Dropped**—Served device has been manually dropped by a user on the FlexNet Embedded server. (Dropped device licenses return to the entitlement pool.)
- **Expired**—Served device's features have expired and the device has not checked in with its parent FlexNet Embedded server.

See Also

[About Device Management](#)
[Managing Devices](#)

About Overriding the Expiration Date of an Entitlement

FlexNet Operations enables End-User and Producer Portal users to override an entitlement's configured expiration date with an earlier, user-specified expiration date when the entitlement is mapped to a device as an additional product. This feature allows finer control of license expiration, and makes licenses available for other hosts in a more planned and automated way.

To enable this capability in the End-User and Producer Portals, select the **Override license expiration date** setting (in the Producer Portal, click **System > Configure > FlexNet Operations > Embedded Devices Settings**). When it is enabled, both portals display the **License expiration date** field—in which the user can enter a short-term expiration date—on their **Map Entitlements** page.

The user-specified expiration date must be later than the current date and earlier than the configured license expiration date. For example:

- If the license is configured to be a permanent license, the user can set the expiration to any date later than the current date.
- If the license is configured with an expiration date such as 31 December 2025, the user can set the expiration to any date later than the current date and before 31 December 2025.
- If the license is configured with a duration-based expiration and a “Use Each Activation Date” start, the start date (license generation date) is the current date.
- If the license is configured with a duration-based expiration and a “Use First Activation Date” start, the start date is the first license generation date. In other words, the current date is the start date if no licenses have been generated for the entitlement on that device yet. However, after licenses have been generated, the actual activation date is the start date.

A user-specified expiration date can be set for each entitlement (however, additional copies of an entitlement are assigned the same user-specified expiration date) and can be different for each host with the same entitlement. After it is set, the date is displayed in the **Expiration Date** column of the default view for a device or server page of both portals.

Licenses with user-specified expiration dates are automatically removed from a host when that date has passed. An automated process removes licenses with a user-specified expiration date when they expire,

- regardless of other rules about license removal,
- once a day at 10 AM Coordinated Universal Time (UTC)
- and does not require confirmation from the host (in other words, the licenses are returned directly to the pool and are available for other hosts).

Limitations

A user-specified expiration date can be set only in the End-User or Producer Portal interface; it cannot be set in capability requests or Web Services.

Because of the risk for license abuse, the user-specified expiration date cannot be changed. If the wrong user-specified expiration date is entered, it can be changed using standard license removal and entitlement mapping procedures.

See Also

[Mapping an Entitlement](#)

[Configuring System Settings](#)

About the Device–Device User Association

A FlexNet Operations device can be associated with an end user or a contact called the **Device User**. Associating a device with a device user allows an End-User Portal administrator to communicate with someone regarding the licenses on that device. For example, if the End-User Portal administrator needs a license for a new device but there are no licenses available, the administrator can search for all existing devices using that license and request that one of those device users return their license so it can be used on the new device.

With the proper combination of system configuration and user permission settings, a device user can be added, edited, or deleted via capability request, sync request, the End-User Portal, the Producer Portal, or Web Services. The same device user can be associated with multiple devices, but a device can only be associated with one device user.

System Configuration

Use the Device User Option (click **System > Configure > FlexNet Operations > Embedded Device Settings**) to enable and configure this capability. Values are:

- Off – The **User** field is not visible in either portal, and device user data sent in a capability request, sync request, or Web Service is ignored.
- On with no validation – The **User** field is shown in both portals, and with the correct permission (refer to [User Permissions](#)) can be edited by the user. The value entered is not validated, so it can be anything. For example, it can be an email address or a phone number.
- On with validation – The **User** field is shown in both portals, and with the correct permission (refer to [User Permissions](#)) can be edited by the user. The value can only be set to an active user or a contact chosen from the **Select User** window.



Important - When the device is a license server, the device **User** field is not validated.

When the Device User Option is set, the **User** field appears on the default view for a device or server page in the End-User and Producer Portals. A validated device user is displayed as an email address that links to the **Users** page. Device user is also returned in Web Services and capability responses. Device users who are not active FlexNet Operations users are identified as inactive.

User Permissions

An End-User Portal user with Edit user on device permission can edit the **User** field of a device.

A Producer Portal user with Manage devices permission can view and edit the **User** field (Edit user on device permission is not required).

When Device User Option is ON with validation, an End-User Portal user with Manage User permission can click the user name link—located below the **User** name—to display the **View/Edit Device User** page. Similar functionality is available in the Producer Portal.

See Also

[Creating Devices](#)
[About Device Management](#)
[Managing Devices](#)

Listing Devices

Use the following instructions to list existing standalone devices, servers, and served devices on the Producer Portal.



Task **To list devices**

1. Click **Devices > Devices**. The **Devices** page opens.
2. On the **Devices** page, you can filter the device list by device type and status.
3. To view a particular device, click its **Name**. On the default view for a device or server page, you can perform device editing and support activities.

See Also


[Filtering the Devices List](#)
[Editing Devices](#)
[Supporting Devices](#)
[Managing Devices](#)

Filtering the Devices List

To quickly reduce the size of the devices list displayed on the **Devices** page, filter it by device type and activation status.



Task **To filter the devices list**

1. On the **Devices** page, hover the cursor over the  filter icon to display the filter selection list.
2. On the selection list, select the device **Type** (or types) and **Status** you want to view.
3. Click **Apply** to filter the devices according to your selection(s). The number in the red bubble indicates how many filters are active.
4. You can also search a filtered devices list.

See Also

[Searching for Devices](#)

Previewing Licenses on a Device

In the **Devices** page list, the **Licenses** column enables you to quickly view the licenses on a device and decide whether to view that device in more detail. A preview pane shows up to ten of the licenses on the device, and includes a link to view the rest of the licenses if there are more than ten on that device. Served devices have features only; their licenses reside on a server, so no license information is available for them. If there are no licenses on a device, that is also indicated.



Task **To preview licenses on a device**

- In the **Devices** page list, hover the cursor over the **License info** link in the **Licenses** column cell for the device whose licenses you want to preview.

Searching for Devices


Existing devices can be easily located by performing a search of the **Devices** page list based on an attribute of the device you want to see. You can perform a simple search on a single attribute, or an advanced search on multiple attributes. For both searches, you can use the * wild card to match zero or more characters in the text string.



Task

To search for a device

1. Optionally, to reduce the size of your devices list, you can filter it by device type and activation status before you search:

- a. On the **Devices** page, hover the cursor over the  filter icon to display the filter selection list.
- b. On the selection list, select the device **Type** (or types) and **Status** you want to view.
- c. Click **Apply** to filter the devices according to your selection(s). The number in the red bubble indicates how many filters are active.

2. Perform a simple search or an advanced search for a device:

Simple Search

- a. On the **Devices** page, click the drop-down list next to the filter icon and select the search criterion.
- b. Type the search string in the text field next to the drop-down list.
- c. Click **Search**.

Advanced Search

- a. On the **Devices** page, click the + icon (next to the **Search** button) to open the **Advanced Search** window.
- b. Type search criteria in the attribute text fields.
- c. Click **Search**.

The Producer Portal shows a list of the devices that match your search criteria on the **Devices** page.



Note - FlexNet Operations tenants configured with a Device user option setting other than Off, listed below, can enter these User search criteria with wildcards:

- On with no validation - free-form string
- On with validation - email address

The Producer Portal shows a list of the devices that match your search criteria on the **Device Search Results** page. See [About Device Attributes](#) or [About Server Attributes](#) for more information about attributes available in the search criteria.

You can also locate served devices from the **View Server** page of their server. See [Viewing a Server's Served Devices](#) for instructions.



Note ▪ Searches that include **Account** as a search criterion may return devices that are not owned by an account that matches the search criteria. When **Account** is part of the search criteria, search results include

- Devices owned by an account that matches the search criteria
- Devices with licenses that belong to an account that matches the search criteria



Tip ▪ To view a particular device, click on its device **Name**. On the default view for a device or server page, you can perform device editing and support activities—such as changing device or server attributes, or moving a device—that are permitted by your user account permissions. See [Viewing Devices](#).

See Also

- [Editing Devices](#)
- [Supporting Devices](#)
- [Managing Devices](#)
- [About the Device–Device User Association](#)
- [Filtering the Devices List](#)
- [Viewing Devices](#)
- [About Standalone Devices, Servers, and Served Devices](#)

Viewing Devices

Users typically search for a device they want to view and then click that device’s **Name** to open the default view for a device or server page. The **View** menu on the device’s page includes several commands to get more details about the device, the device history, device requests, and so on. For standalone devices, the default view includes the Overview and Update tabs for users with the Updates and Insights module. With the commands in the **View** menu, you can perform the following tasks.

Table 5-5 ▪

Topic	Description
Viewing this Device	Explains how to return to the default view for a device or server page when performing other device-related operations.
Viewing a Server’s Binding-Break Status	Explains how to track how many times a license server’s trusted storage has been reset to repair broken binding.
Viewing a Server’s Served Devices	Shows how to see devices that are served by a license server.
Viewing Device History	Explains how to view the device history for a selected device.
Viewing Device Requests	Explains how to view requests made by a device.
Viewing a Vendor Dictionary for a Device	Shows how to see vendor dictionary entries for a device.

Table 5-5 •

Topic	Description
Downloading a License File for a Device	Describes how to download a license file for a device.
Viewing a License File for a Device	Shows how to see a license file for a device.
Downloading a Response for a Device Request	Describes how to download a response for a capability request.
Viewing a Response for a Device Request	Shows how to see a response generated for a capability request.
Viewing Standalone Device Updates	Displays the update(s) for a given device.

See Also

- [Editing Devices](#)
- [Supporting Devices](#)
- [Managing Devices](#)

Viewing this Device

When working with a device, you can return to the default view for a device or server page by clicking **View this Device/Server/Served Device**. Device-related operations are downloading a capability response, viewing device requests, assigning an account to the device, mapping entitlements, and so forth. On these device-related pages, **View this Device/Server/Served Device** is a command in the **View** menu.

The Producer Portal also shows the default view for a device or server page after you create a device on the **Create Device/Server** page.



Task *To return to the default view for a device or server page*

- Click **View** > **View this Device/Server/Served Device**.

The default view for a device or server page opens. For standalone devices, the Overview tab is selected.



Note • When viewing served devices, the information displayed under **Features** depends on your system configuration settings. If the configuration option **Support Multiple License Servers** is selected, the view shows the latest record of features that the device acquired across multiple license servers (see [Configuring Embedded Devices Settings](#)).

Viewing a Server's Binding-Break Status



Important - A server's binding break status is displayed only if the configuration option **Limit Binding Break Repairs for License Server** is selected (see [Configuring Embedded Devices Settings](#)).

The **Binding Break** section on the **View Server** page enables you to track how many times a license server's trusted storage has been reset to repair broken binding. You can also click the **Reset** button to restart the count and allow further binding-break repairs.

The **Binding Break** section shows the following:

- **Repairs Done**—The number of binding-break repairs since the count was last reset.
- **Maximum Number of Repairs Allowed**—The number of times the local license server is allowed to repair a binding break. The local license server will cease to serve licenses if the number of binding break repairs (field **Repairs Done**) reaches the maximum number of allowed repairs, and no further repairs are allowed.
- **Reset Binding Break Repair Count**—Click the **Reset** button to restart the count of binding-break repairs. After the count has been reset, the local license server can serve licenses again.

See Also

[Viewing Devices](#)

[Editing Devices](#)

[Supporting Devices](#)

Viewing a Server's Served Devices

Producers can view the devices served by a particular server from the server's **View Server** page.



Task *To view the served devices of a server*

- Click **View > View Served Devices**.

The **Served Devices Search Results** page opens.

See Also

[Editing Devices](#)

[Viewing Devices](#)

Viewing Device History

You can view a device's history from its default view for a device or server page. The **Host History** page shows a history of device management events such as device creation, ownership changes, transfers, and device status changes.



Task *To view the history of a device*

- Click **View > View Device/Server/Served Device History**.

The **Host History** page opens.

See Also[Viewing Devices](#)[Editing Devices](#)[Supporting Devices](#)

Viewing Device Requests

You can view the history of all device activation requests, as well as the sync message records (for servers and served devices), from a device's default view page.

**Task****To view device request history**

- Click **View > View Device/Server Requests**.

The **View Host Requests** page opens.

See Also[Viewing Devices](#)[Editing Devices](#)[Supporting Devices](#)

Viewing a Vendor Dictionary for a Device

You can view vendor dictionary entries for a device from its default view page.

**Task****To view vendor dictionary entries**

- Click **View > View Vendor Dictionary**.

The **View Vendor Dictionary** page opens.

See Also[Viewing Devices](#)[Editing Devices](#)[Supporting Devices](#)

Downloading a License File for a Device

If a license has been generated for a device, you can download its license file from the default view for a device or server page.

**Task****To download a license file**

- Click **View > Download License File**.

The Producer Portal sends the license file (typically, license.bin). The download experience depends on the web browser you are using.



Tip • A device's license format settings determine which, if any, of its features are included in a license file. Devices inherit their license format settings from their device model. You can download a license file for a device that stores either its pre-installed license or its pre-installed license plus additional licenses in a license file. (Devices that store both the pre-installed license and additional licenses in trusted storage use capability requests and responses rather than license files.)

See Also

[Generating a License File](#)
[Viewing a License File for a Device](#)
[Viewing Devices](#)

Viewing a License File for a Device

If a license has been generated for a device, you can view its license file from the default view page.



Task

To view a license file

- Click **View** > **View License File**.

The **View License File** page opens. This page shows the text of the license file that was generated for the device.



Tip • A device's license format settings determine which, if any, of its features are included in a license file. Devices inherit their license format settings from their device model. You can view a license file for a device that stores either its pre-installed license or its pre-installed license plus additional licenses in a license file. (Devices that store both the pre-installed license and additional licenses in trusted storage use capability requests and responses rather than license files.)

See Also

[Generating a License File](#)
[Downloading a License File for a Device](#)
[Viewing Devices](#)

Downloading a Response for a Device Request

If a capability response has been generated for a device, you can download that response from the default view for a device or server page.



Task

To download a capability response

- Click **View** > **Download Response**.

The Producer Portal sends the capability response (typically <device ID>.bin for a device, <license server ID>.bin for a server). The download experience depends on the web browser you are using.



Tip ▪ A device's license format settings determine which, if any, of its features are described in capability responses. Devices inherit their license format settings from their device model. You can download a response for a device that stores either its pre-installed license or its pre-installed license plus additional licenses in trusted storage. (Devices that store both the pre-installed license and additional licenses in a license file do not have response files to download.)

See Also

[Viewing a Response for a Device Request](#)
[Generating a Capability Response](#)
[Viewing Devices](#)

Viewing a Response for a Device Request

If a capability response has been generated for a device, you can view the response from the default view for a device or server page.



Task **To view a capability response**

- Click **View** > **View Response**.

The **View Response** page opens. This page shows the a human-readable representation of the capability response that was generated for the device.



Tip ▪ A device's license format settings determine which, if any, of its features are described in capability responses. Devices inherit their license format settings from their device model. You can view a response for a device that stores either its pre-installed license or its pre-installed license plus additional licenses in trusted storage. (Devices that store both the pre-installed license and additional licenses in a license file do not have response files to view.)

See Also

[Downloading a Response for a Device Request](#)
[Generating a Capability Response](#)
[Viewing Devices](#)


Viewing Standalone Device Updates

When an update has been generated for a standalone device, you can view it from the Updates tab.



Version ▪ This tab is only visible to producers who use the Software Delivery module.

**Task** *To view updates for a standalone device*

1. From the default view of a standalone device, click the **Updates** tab. If the Updates tab is not visible, select **View > View this Device**.
2. On the **Updates** page, hover the cursor over the  filter icon to display the filter selection list. By default, the **Updates** page is set to display all updates.
3. You can sort the update list by any column in ascending or descending order.
4. Click the link in the **Status** column to see additional information about the update's status. Note that this information is available only if the device provided a status reason.
5. You can also search a filtered update list. Use the drop-down menu to narrow your search to either **Update ID** or **Update Name**.

The updates for a device are displayed in a grid with the **Update name**, **Update ID**, **Status** and date/time of **Last activity**. You can sort the list by any of the grid columns.

See Also

[Viewing Devices](#)

Creating Devices

You can create new devices in the Producer Portal. Each device is identified by a device ID (typically, a serial number) and its host type. You can create a set of devices for which licenses can be generated, as well as generate pre-installed licenses for the device. Entitlements can be linked to devices.

A new server can submit its own capability requests to FlexNet Operations and serve its own licenses to separate FlexNet Embedded served devices.

Producers who use FlexNet Cloud Licensing Service can choose from two **Server deployment** options to create a server as a **Local** (default) or as a **Cloud** license server. If auto provisioning is permitted by the license model, Cloud Licensing Service servers can be automatically created when the entitlement is deployed.



Note - You are permitted to create a server and a nodelocked device with the same **Device ID** and **ID Type**.

**Task** *To create a device*

1. Click **Devices > Create Device**. The **Device | New Device** page opens.
2. On the **Device | New Device** page, type a device **Name** (required).
3. Select an **ID Type** from the drop-down menu; below it, type the device's **ID** (required).
4. Select an **Account** to specify which account owns the device (skip this step if you are creating an anonymous device):
 - a. Click the search icon next to **Account**. The **Assign Device Owner** window appears.

- b. In the **Assign Device Owner** window, click the **Customers** or **Partners** tab, as appropriate.
 - c. Choose an account and click **Select**. The **Assign Device Owner** window closes and the **Account** field on the **Device | New Device** page is populated.
5. Optionally, specify values for **Model**, **Identity**, **Site name**, and **Notes**. (See [About Device Attributes](#) for details about these attributes.)



Important - Be aware that the device model you specify may include a default pre-installed product. In this case, adding a pre-installed product to the device overrides the device model's pre-installed product.

6. Click **Save**.

The Producer Portal creates the new device and opens its default view page.



Task **To create a local license server**

1. Click **Devices > Create Device**. The **Device | New Device** page opens.
2. On the **Device | New Device** page, type a device **Name** (required).
3. Select the **Runs license server?** check box. For **Server deployment**, choose **Local**.
4. Select an **ID Type** from the drop-down menu; below it, type the server's **ID** (required).
5. Select an **Account** to specify which account owns the device (required):
 - a. Click the search icon next to **Account**. The **Assign Device Owner** window appears.
 - b. In the **Assign Device Owner** window, click the **Customers** or **Partners** tab, as appropriate.
 - c. Choose an account and click **Select**. The **Assign Device Owner** window closes and the **Account** field on the **Device | New Device** page is populated.
6. Optionally, specify values for **Model**, **Identity**, **Site name**, and **Notes**. (See [About Server Attributes](#) for details about these attributes.)



Important - Be aware that the device model you specify may include a default pre-installed product. In this case, adding a pre-installed product to the device overrides the default pre-installed product in the device model.

7. Click **Save**.

The Producer Portal creates the new server and opens its **View Server** page.



Task **To create a Cloud Licensing Service license server**

1. Click **Devices > Create Device**. The **Device | New Device** page opens.
2. On the **Device | New Device** page, type a device **Name** (required).
3. Select the **Runs license server?** check box. For **Server deployment**, choose **Cloud**.

4. Select an **Account** to specify which account owns the device (required):
 - a. Click the search icon next to **Account**. The **Assign Device Owner** window appears.
 - b. In the **Assign Device Owner** window, click the **Customers** or **Partners** tab, as appropriate.
 - c. Choose an account and click **Select**. The **Assign Device Owner** window closes and the **Account** field on the **Device | New Device** page is populated.
5. Optionally, specify values for **Model**, **Identity**, **Site name**, and **Notes**. (See [About Server Attributes](#) for details about these attributes.)



Important - Be aware that the device model you specify may include a default pre-installed product. In this case, adding a pre-installed product to the device overrides the default pre-installed product in the device model.

6. Click **Save**.

The Producer Portal creates the new server and opens its **View Server** page.

See Also

- [Supporting Devices](#)
- [Managing Devices](#)
- [Editing Devices](#)

Editing Devices

Users typically search for a device they want to edit and then click its device **Name** to open its default view for a device or server page. The **Edit** menu on the default view for a device or server page includes several commands for actions—like editing device attributes, assigning an account, or making a device obsolete—for an existing device. With the commands in the **Edit** menu, you can perform the following tasks.

Table 5-6 -

Topic	Description
Editing Device Attributes	Explains how to edit a device's changeable attributes. (Some attributes are read-only after a device has been created.)
Adding a Pre-installed Product to a Device	Explains how to add a pre-installed product to a device to define a set of built-in features.
Assigning an Account to a Device	Describes how to change the current account that holds a device.
Associating a Device with a Device User	Explains how to associate a device with a device user.
Returning a Device	Explains how to return a device.

Table 5-6

Topic	Description
Moving a Device	Shows how to change the account of a device that has not yet been assigned to a customer account.
Making a Device Obsolete	Describes how to make a device obsolete.

Some device changes are made as part of support activities. These are described in [Supporting Devices](#).

See Also

- [About the Device–Device User Association](#)
- [Supporting Devices](#)
- [Managing Devices](#)
- [Working with Licenses on a Device](#)

Editing Device Attributes

You can edit a device’s details from the default view for a device or server page. Most of the device information that you enter when you create a device can be edited on the **Edit Device /Server/Served Device** page.



Note - A device’s editable attributes may also include the values for any custom device attributes you have defined. To learn more about custom attributes, including custom device attributes, see [Administering Custom Attributes](#).

For more information about device attributes, see [About Device Attributes](#). For more information about server attributes, see [About Server Attributes](#).



Task *To edit device attributes*

1. On the default view for a device or server page, click **Edit > Edit this Device/Server/Served Device**. The default edit page for a server or device page opens for the current device.
2. Make changes to one or more device attributes.
3. Click **Save**.

The Producer Portal saves your changes and returns to the default view for a device or server page for the current device.

See Also

- [Viewing Devices](#)
- [Supporting Devices](#)
- [Editing Devices](#)

Adding a Pre-installed Product to a Device

You can add pre-installed products to a device from the default view for a device or server page. A pre-installed product defines a set of built-in features for a device. A device with no pre-installed products is a device with no built-in features; all features would be additional features.




Important - Be aware that a device model may include a default pre-installed product. In this case, adding another pre-installed product to the device overrides the device model's pre-installed product.



Task To add a pre-installed product

1. On the **default view for a device or server** page, click **Edit > Edit this Device/Server**. The default Edit page for a device or server appears.
2. In the **Pre-installed Licenses** section of the page, click **Add**. The **Add Pre-installed Product** window opens.
3. In the **Add Pre-installed Product** window, click **By product**. The **Select Product** window opens. The **Select Product** window lists products with features permitted by the restrictions imposed (if any) by the device model's device series.
4. In the **Select Product** window, select the pre-installed product and then click **OK**. The **Select Product** window closes, and the product name and product version of the selected product are shown on the **Add Pre-installed Product** page.
5. In the **Add Pre-installed Product** window, specify a license model, license model attributes (optional), and expiration terms.

Setting	Description
License Model	Choose a License Model for the pre-installed product. The license models that are available are determined by the license models that are linked to the selected pre-installed product.
License Model Attributes	Optionally, provide settings for license model attributes (such as Notice and Vendor String).
Expiration Terms	Set the Start Date and Expiration for the pre-installed product.  Note - If the year that you want to set is not currently available from the calendar, select the year that is closest to the desired year. This automatically increases the list by 10 years from the year you selected.

6. Click **Add**. The **Add Pre-installed Product** window closes and the default edit page for a device or server is displayed. Notice that the **Pre-installed Licenses** settings show the product you selected, as well as its expiration terms.
7. Click **Save**.

The Producer Portal saves your changes and returns to the default view for a device or server page for the current device.

See Also

[Viewing Devices](#)

[Supporting Devices](#)

[Editing Devices](#)

Assigning an Account to a Device

You can assign a customer or partner account to an existing device from the device's default view for a device or server page. (See [About Accounts](#) for more information about customer and partner accounts.)



Note - Auto-provisioned license servers that have entitlements mapped for metered features cannot be moved to another account. Refer to [Auto-Provisioning](#) for more information.



Task

To assign an account to a device

1. Click **Edit > Assign Account**. The **Assign Account** page opens.
2. For **Account ID**, click the search icon. The **End Customer and Channel Partners** window opens.
 - a. Choose an account.
 - b. Click **Save**.

The **End Customer and Channel Partners** window closes, the **Account ID** is set to the ID of the account you chose, and the **Account Name** is populated.

3. Click **Assign account**.

The Producer Portal changes the account of the device and opens its default view for a device or server page.

Devices that do not have a customer account assigned to them can also be moved to a partner account. (See [Moving a Device](#).)

See Also

[Supporting Devices](#)

[Managing Accounts](#)

[Editing Devices](#)

Associating a Device with a Device User

When the Device User Option is enabled, the **User** field is visible and a device can be associated with an end user or contact called the **Device User**. Associating a device with a device user allows an End-User Portal administrator to communicate with someone regarding licenses on the device.



Note - When the Device user option is enabled (not set to Off), device user is in one of these formats:

- *Free-form string for On* with no validation – see [To associate a device with a device user—no user validation](#)
- *Email address link for On* with validation – see [To associate a device with a device user—validated user](#)

You can associate a device with a device user from the default view for a device or server page.



Task **To associate a device with a device user—no user validation**

1. Click **Edit > Edit this Device/Server**. The default edit page for a device or server opens.
2. In the **User** field, type the device user information for the device.

To remove an associated user, clear the **User** field.
3. Click **Save** to save the change. The default view for a device or server page opens, showing the updated **User**.



Task **To associate a device with a device user—validated user**

1. Click **Edit > Edit this Device/Server**. The default edit page for a device or server opens.
2. In the **User** field, click the search icon to display a list of available users.

To remove an associated user, clear the **User** field.
3. Select one user, then click **Select** to close the list and set the device user.
4. Click **Save** to save the change. The default view for a device or server page opens, showing the updated **User**.

See Also

[About the Device–Device User Association](#)

Returning a Device



Important - *Returning a device is an irreversible action. It is intended for devices that no longer receive capability responses or license files, or servers that no longer serve devices or communicate with the FlexNet Operations back office.*

A customer may be required to return a malfunctioning device to a manufacturer or reseller. During the return process, you have the option to move all of the malfunctioning device's licenses to a replacement device. In this case, you might want to create the new device before returning the existing device, so that it is ready to receive the existing device's licenses (for more information, see [Creating Devices](#)). If you do not move a license, the license is returned to the pool of unused licenses and you can allocate it to another device.

You can return a device from the default view for a device or server page.



Task **To return a device**

1. Click **Edit > Return Device/Server**. The default return page for a device or server opens.
2. Optionally, identify the device to receive the current device's licenses in **Destination Device/License Server ID**.
 - Type the **ID** of the device to receive the current device's licenses.
 - Click the search icon to open the **Find Device** or **Search License Servers** window.
 - a. Choose a device.
 - b. Click **Submit**.

The **Find Device/License Servers** window closes and the default destination ID page for a device or license server value is set to the device you chose.

3. Optionally, type an RMA number for **Return Material Authorization (RMA) Number**. RMA number values are recorded by the Producer Portal but are not required by FlexNet Operations.
4. Click **Confirm**.

The Producer Portal returns the device and shows its default view for a device or server page. The status of a returned device is RETURNED.

See Also

[Supporting Devices](#)

[Editing Devices](#)

[Working with Licenses on a Device](#)

Moving a Device

A device that does not have a customer account assigned to it can be moved from one account to a related account. For example, the parent account can move the device from one of its child accounts (a regional division, for example) to another child account.

When a device is moved, any entitlements that belong to that device are moved as well. The result of such a move is to either create new entitlements for the receiving account, or to increment the count of that account's existing (and matching) entitlements by the count on the device that was moved.



Note - *Auto-provisioned license servers that have entitlements mapped for metered features cannot be moved to another account. Refer to [Auto-Provisioning](#) for more information.*

You can move a device from the default view for a device or server page.

**Task** *To move a device*

1. Click **Edit > Move Device/Server**. The **Move Host** page opens.
2. In the **Target Account** section, click the **System Account ID** search icon. The **End Customer and Channel Partners** window opens.
 - a. Choose an account.
 - b. Click **Save**.

The **End Customer and Channel Partners** window closes, the **System Account ID** is set to the ID of the account you chose, and the **Account ID** and **Account Name** fields are populated.

3. Click **Move Device/Server**.

The Producer Portal changes the account of the device and opens its default view for a device or server page.

See Also

[Assigning an Account to a Device](#)
[Supporting Devices](#)
[Editing Devices](#)

Making a Device Obsolete

You can make an active device obsolete from its default view for a device or server page. When a device is made obsolete, its licenses are unmapped and returned to the pool, and it becomes unable to acquire new licenses.



Important - *Obsolete status is permanent. Obsolete devices cannot be re-activated.*



Note - *Making an auto-provisioned license server that has entitlements mapped for metered features obsolete will remove all licenses mapped to the server. However, this is not recommended, because future line items will not be mapped automatically to the auto-provisioned license server. Refer to [Auto-Provisioning](#) for more information.*

**Task** *To make a device obsolete*

1. Click **Edit > Make Obsolete**. The Producer Portal warns that this process is irreversible and asks you to confirm before changing the current device's status to OBSOLETE.
2. Click **OK**.

The Producer Portal changes the status of the device to OBSOLETE and shows its default view for a device or server page.

See Also

[About Device Status](#)
[Supporting Devices](#)
[Editing Devices](#)

Working with Licenses on a Device

Additional features are capabilities that can be mapped (added) to or removed from a device. (Pre-installed capabilities, on the other hand, are features included with a device or server.) The following topics describe how to manage additional capabilities in the Producer Portal.

Table 5-7 ▪

Topic	Description
Mapping an Entitlement	Shows how to map additional entitlements to a device.
Mapping Entitlements by Activation IDs	Shows how to map additional entitlements by activation ID (for users who know the activation IDs of the capabilities they want to add).
Removing Licenses	Shows how to remove previously mapped licenses from a device.

For more information about creating additional capabilities as features for your FlexNet Embedded devices, see [Working with Features](#).

See Also

[About Overriding the Expiration Date of an Entitlement](#)
[Managing Devices](#)

Mapping an Entitlement

Devices often include pre-installed licenses but also permit the addition of new features or more capacity via additional entitlements.

When the current account of a device is entitled to additional capabilities, you can manually map those entitlements to it via the Producer Portal. (Entitlements can also be mapped programmatically from the device using an activation ID.)

You can map entitlements from the default view for a device or server page.



Task

To map an entitlement

1. Click **Licenses > Map Entitlements**. The **Map Entitlements** page opens. The table lists entitlements that can be mapped to the current device.



Tip ▪ *When an entitlement has been upgraded, upsold, or renewed, the Map Entitlements page shows only the most recent entitlement in its lifecycle chain. Earlier entitlements are grouped under the most recent*

entitlement but initially hidden. These entitlement groups have a **Show Upgrades** button to reveal earlier entitlements in the list.

2. In the table, type values into **Qty to add** for the entitlements you want to map.
3. (Optional) If the capability is enabled, you can override an entitlement's configured **Expiration**, as shown in the **Licenses** table, with a shorter-term expiration. (Refer to [About Overriding the Expiration Date of an Entitlement](#) for details.)

To override an entitlement's expiration,

- a. Click the pencil icon next to its expiration. The Producer Portal opens a calendar control.
- b. In the calendar control, select the shorter-term expiration.



Note ▪ If the year that you want to set is not currently available from the date picker, select the year that is closest to the desired year. This automatically increases the list by 10 years from the year you selected.

After the change is saved, the new expiration appears in the **Licenses** table of the default view for a device or server page, and is denoted by an asterisk in the table on the device's **Map Entitlements** page.

4. Click **Save**.

The entitlement is mapped to the current device and its default view for a device or server page is shown.

See Also

[About Overriding the Expiration Date of an Entitlement](#)
[Removing Licenses](#)
[Working with Licenses on a Device](#)

Mapping Entitlements by Activation IDs

Devices often include pre-installed capabilities, but also permit the addition of new features or more capacity via additional entitlements.

When the current account of a device is entitled to additional capabilities, and you know the activation IDs for those entitlements, you can manually map those entitlements to the device via the Producer Portal, as shown below. (Entitlements can also be mapped programmatically from the device or server using an activation ID.)

First locate the device or server to which you want to map new activation IDs. (See [Searching for Devices](#) or [Viewing Devices](#) for instructions.) Then you can map entitlements by activation ID from the default view for a device or server page.

On the **Map by Activation IDs** page, you can type the activation IDs to map to the current device.



Note ▪ This operation is for producers who know the activation IDs for the entitlements they want to map.



Task **To map an entitlement by activation ID**

1. Click **Licenses > Map by Activation IDs**. The **Map by Activation IDs** page opens.
2. In the **Activation IDs** field, type one or more activation IDs (one activation ID per line) to map to the current device.
3. Click **Validate**. The Producer Portal evaluates the activation IDs you provided and shows whether they can be mapped to the current device.
 - If all activation IDs provided can be mapped to the device, proceed to [Step 4](#).
 - If one or more activation IDs cannot be mapped to the device, the Producer Portal highlights the activation IDs that did not pass validation and allows you to either remove them from the list or cancel the mapping operation.
 - To continue without the activation IDs that failed validation, first remove the failed activation IDs and then click **Re-validate**. When the re-validation passes successfully, proceed to [Step 4](#).
 - To cancel the mapping, click **Cancel**.
4. After the activation IDs have been validated, type values into **Qty to Add** for the entitlements you want to map.
5. Click **Save**.

The activation ID is mapped to the current device and its default view for a device or server page is shown.

See Also

- [Removing Licenses](#)
- [Supporting Devices](#)
- [Working with Licenses on a Device](#)

Removing Licenses

Licenses already mapped to a device can be manually removed via the default view for a device or server page. Licenses that are unmapped are returned to the pool of unused licenses.

The following table lists limitations for removing licenses from a license server:

Server Type	Limitation
Local License Server	Only concurrent licenses that are not in use can be removed from a local license server. To remove used licenses, you must unmap the licenses before deleting them. Licenses that are currently in use cannot be removed.

Server Type	Limitation
CLS Instance	<ul style="list-style-type: none"> Licenses for counted features that are currently in use cannot be removed. You must unmap used licenses first before deleting them. (Only licenses for uncounted features that are currently in use can be removed.) At any one time, you can remove licenses from a total of five activation IDs.
Auto-Provisioned License Server	Only unused licenses for metered features can be removed using Licenses > Remove Licenses. Refer to Auto-Provisioning for more information.



Task *To remove a license*

1. Click **Licenses > Remove Licenses**. The **Remove Licenses** page opens. On this page, the **Licenses Currently Mapped** table lists licenses that can be removed from the current device.
2. In the **Licenses Currently Mapped** table, type values into **Qty to remove** for the licenses you want to remove.
3. Click **Save**.

The Producer Portal removes the licenses from the current device and shows its default view for a device or server page.

See Also

- [Mapping an Entitlement Supporting Devices](#)
- [Working with Licenses on a Device](#)

Supporting Devices

Device support activities, like generating license files and capability responses or manually uploading capability requests, are covered here.

Table 5-8 ▪

Topic	Description
Generating a License File	Describes how to generate a license file for a device.
Generating a Capability Response	Explains how to generate a capability response for a device.
Uploading a Capability Request from the Device Page	Explains how to upload a capability request for a device from the Device page.

Some device support activities, such as assigning accounts and returning devices, are covered in the [Editing Devices](#) topic. For instructions on manually downloading a generated license file or capability response, see [Viewing Devices](#).

See Also

[Editing Devices](#)
[Managing Devices](#)

Generating a License File

You can generate a license file for a device from its **Device** | *<device name>* page.



Task **To generate a license file for a device**

- In the **Pre-installed Licenses** section of the **Device** | *<device name>* page, click **Generate license file**.

The license file is generated and a confirmation message is shown.

After a license has been generated, you can download it by clicking **View > Download License File**. See [Downloading a License File for a Device](#) for details.

See Also

[Viewing a License File for a Device](#)
[Downloading a License File for a Device](#)
[Supporting Devices](#)

Generating a Capability Response

You can generate a capability response for a device from its default view for a device or server page.



Task **To generate a capability response for a device**

- In the **Model Details** section of the default view for a device or server page, click **Generate capability response (Generate response)**.

The response is generated and a confirmation message is shown.

After a response has been generated, you can download it by clicking **View > Download Response**. See [Downloading a Response for a Device Request](#) for details.

See Also

[Viewing a Response for a Device Request](#)
[Supporting Devices](#)

Uploading a Capability Request from the Device Page

Capability requests can be manually uploaded by producers on the Producer Portal. You can upload a capability request from a device's default view for a device or server page.



Task *To upload a capability request for a device*

1. In the **Model Details** section of the default view for a device or server page, click **Browse** and locate the capability request on your local system. (The exact controls vary depending on the browser you are using.)
2. Click **Upload capability request (Upload request)**.

The capability request is processed.

After the capability request is processed, download the capability response and process it on your device. (See [Generating a Capability Response](#).) In offline activation scenarios, for example, the producer communicates the capability response to the end user of a device that cannot connect directly to the Internet, and the end user applies it to their device to activate the capabilities to which they are entitled.

See Also

- [Uploading a Capability Request from the Offline Device Management Page](#)
- [Downloading a Response for a Device Request](#)
- [Supporting Devices](#)

Offline Device Management

Offline device management activities are covered here.

Table 5-9 -

Topic	Description
Uploading a Capability Request from the Offline Device Management Page	Explains how to upload a capability request for a device from the Offline Device Management page.
Uploading Synchronization History	Explains how to upload synchronization history from the Offline Device Management page.

Uploading a Capability Request from the Offline Device Management Page

Capability requests can be manually uploaded by producers on the Producer Portal. You can upload a capability request from the **Offline Device Management** page.



Task *To upload a capability request for a device from the Offline Device Management page*

1. On the **Offline Device Management** page, for **Upload type**, select **Generate license**.
2. Click **Browse** and locate the capability request (.xml, .bin, or .key) on your local system. (The exact controls vary depending on the browser you are using.)

3. Click **Upload**.

The capability request is processed.

After the capability request is processed, download the capability response and process it on your device. (See [Generating a Capability Response](#).) In offline activation scenarios, for example, the producer communicates the capability response to the end user of a device that cannot connect directly to the Internet, and the end user applies it to their device to activate the capabilities to which they are entitled.

See Also

[Uploading a Capability Request from the Device Page](#)

[Downloading a Response for a Device Request](#)

[Supporting Devices](#)

Uploading Synchronization History

Synchronization history can be manually uploaded by producers on the Producer Portal. You can upload synchronization history from the **Offline Device Management** page.



Task

To upload synchronization history

1. On the **Offline Device Management** page, for **Upload type**, select **Upload synchronization history**.
2. Click **Browse** and locate the sync history (.xml, .bin, or .syncreq) files on your local system; up to 100 files per submission can be selected. (The exact controls vary depending on the browser you are using.)



Important - All files uploaded as part of one submission must be located on the same license server.

3. Click **Upload**. The sync history files are uploaded, device details are displayed, and a confirmation message is shown.
4. The application offers you a response file (sync acknowledgment) to download and process on your license server.

Managing Usage

Producers who use FlexNet Operations with FlexNet Usage Management and FlexNet Embedded licensing can create software and devices that support usage-based, pay-for-use and pay-for-overage models. The following topics cover the management of usage data and reporting in the Producer Portal.

Table 6-1 -

Topic	Description
About Usage Management	Discusses usage management concepts in the following subsections: <ul style="list-style-type: none"> • Usage Management Concepts • About Usage Models • About Usage Reports
Viewing Usage Reports	Explains how to show usage history reports for your product lines.
Listing Usage Models	Shows how to list usage models.
Uploading Usage Data	Describes how to upload historical usage data for internal testing purposes.

For information about creating license models that support usage-based licensing, see [Administering License Models](#). For information about usage functionality in products and features, see [Packaging Products](#).

See Also

[Administering License Models](#)

[Packaging Products](#)

[About FlexNet Usage Management](#)

About Usage Management

This section describes general concepts involved in working with FlexNet Usage Management in FlexNet Operations.

Table 6-2 -

Topics	Description
Usage Management Concepts	Discusses the way features, capability requests, and capability responses are used in software and devices that use usage-based licensing.
About Usage Models	Describes usage models and how they are used to designate the statement interval and reset period (if any) for usage history reports.
About Usage Reports	Covers the usage history reporting available in the Producer Portal: usage gauges, tables, timelines, and comparisons.

See Also

[Creating a Feature](#)

Usage Management Concepts

Software and devices that incorporate usage-based licensing make use of the same features and capability requests and responses as other FlexNet Embedded software and devices. This section discusses the use of features and capability requests and responses in the context of FlexNet Usage Management.

Features

The smallest unit for which usage can be captured is a *feature*. You define the feature or features that make up your products in FlexNet Operations, and your usage-capture code sends information about these features. In addition, feature-clipping code checks for the availability of certain features to determine a product's functionality.

During execution, your capped-usage or feature-clipping code uses FlexNet Embedded functions that attempt to *acquire* a license. The FlexNet Embedded libraries validate such conditions as the feature not having expired. If the license acquisition succeeds, your code would then enable the corresponding capability.

Capability Requests and Responses

When your usage-capture code communicates with FlexNet Operations, the communications involve *capability requests* and *capability responses*. A capability request is generated by the client (either a client reporting usage or requesting features that it will acquire). The request data contains some combination of a host identifier, one or more desired features, and other optional data to pass to FlexNet Operations.

The hosted server instance then processes the request, reading the various identifiers, desired features, and custom data. If FlexNet Operations determines that the client requires a response, it generates a capability response. The response data contains current license rights available for the client. The capability response is

then conveyed back to the client, which processes the response, after which the features in the response can be queried for the sake of detecting if a quota has been exceeded or for feature clipping (programmatically restricting access to features based on the capability response).

Your usage-capture code specifies one or more *desired features*, which represent features whose usage is being reported or features desired for the sake of feature clipping, in the capability request.

Your code also specifies an *operation* in the capability request, which indicates whether it is simply reporting feature usage, or whether a response is expected. The “report” operation is used in uncapped-usage scenarios, when no response is needed; and the “request” operation is used in capped-usage and feature-clipping scenarios, where a response is needed. The request operation can also be used in untrusted environments to report uncapped usage to force a confirmation response from the server, ensuring that the usage has been reported. (There is also an “undo” operation, which enables recent information to be undone, in case of error or canceled usage.)

Hosted Servers

Your usage-capture clients send usage data to a FlexNet Embedded license server referred to in this guide as a *hosted server*. The hosted server can be a local license server or a license server instance in FlexNet Cloud Licensing Service that captures the metered usage data your usage-capture clients send.

See Also

[Working with Features](#)

[Creating Devices](#)

About Usage Models

Usage models designate the statement interval and reset period for usage-enabled products.




Statement interval describes how usage history data is summarized. Usage models support monthly, quarterly, and yearly statements.

Reset period defines whether or not usage history data is reset. When the usage model includes no reset, usage counts accumulate over time and across reporting interval statements. When the usage model includes a reset period, usage counts that accumulate during the statement interval are reset monthly or yearly.



Important - Usage models with a periodic reset cannot be used with license models that follow a metered-capped (limits to usage counts) approach. Only license models with unlimited (uncapped) usage support usage models with periodic reset.

Table 6-3 -

Usage Model ID	Description
1	Quarterly Statements (Reset yearly) Usage history data is summarized by quarter in usage reports. Counts are accumulated across quarters but reset annually.  Important - This usage model cannot be used with metered-capped license models.
2	Quarterly Statements (No Reset) Usage history data is summarized by quarter in usage reports. Counts are accumulated across quarters with no automatic reset.
3	Yearly Statements (Reset yearly) Usage history data is summarized by year in usage reports. Counts are reset each year so that multi-year usage reports show only the usage for each individual year.  Important - This usage model cannot be used with metered-capped license models.
4	Yearly Statements (No Reset) Usage history data is summarized by year in usage reports. Counts are accumulated across years with no automatic reset.
5	Monthly Statements (Reset monthly) Usage history data is summarized by month in usage reports. Counts are reset each month so that multi-month usage reports show only the usage for each individual month.  Important - This usage model cannot be used with metered-capped license models.
6	Monthly Statements (No Reset) Usage history data is summarized by month in usage reports. Counts are accumulated across months with no automatic reset.

When you create a product, you specify the usage model to identify how usage history data is summarized in usage reports, whether or not usage data is reset and, if so, how often.

You cannot edit the usage model for a deployed product. To edit the usage model, change the product status to Draft. Note that you can only change the status to Draft if the product has no entitlements.



Important • Products using the same feature must be configured with the same usage model per account. For an account, the usage model that is specified for a product containing a specific feature will be the usage model that is used for subsequent entitlements or products containing that specific feature.

Example:

- Product A (feature f1) and product B (features f1 and f2)
- Account C is first entitled to product A (feature f1) with usage model Monthly Statements (No Reset)
- Account C is then entitled to product B (features f1 and f2) with usage model Monthly Statements (Reset Monthly)
- Account C will use usage model Monthly Statements (No Reset) for both products A and B because they both contain feature f1 which was included in the first entitlement.

If Account C was first entitled to product B (features f1 and f2) with usage model Monthly Statements (Reset Monthly), this usage model would be used for both products/entitlements for the account.

See Also

[Listing Usage Models](#)
[Creating a Product](#)

About Usage Reports

FlexNet Operations enables you to view end users' current usage data in the Producer Portal. Similarly, your enterprise customers can view their current usage data in Usage Management in the enterprise portal you set up.

The following types of reports are supported with respect to usage capture. Usage data can also be downloaded as a text file in CSV format. After selecting what usage data to display—as described in [Viewing Usage Reports](#)—and selecting the desired usage period, you can select the type of graph in which to display the usage data.



Figure 6-1: Buttons for selecting the usage report type

These report type buttons correspond to [Usage Gauges](#), [Usage Tables](#), and [Usage Timelines and Comparisons](#).

See Also

[Viewing Usage Reports](#)
[Uploading Usage Data](#)

Usage Gauges

This type of graph shows usage data as a graphical gauge representing the percentage of usage compared to the overall entitled amount. The green region of the gauge indicates usage of none to 75 percent of the available count; the yellow region indicates 75 percent to 100 percent of the available count; and the red region indicates over 100 percent (overage) of the entitled amount.

Usage Reports

View Usage

The gauges below show the percentage of entitled amount used for the statement period which includes the selected date. Selecting a new date will show percentages for meters within the statement period surrounding the new date. Click the download link on a meter to see that meter's usage events for the selected statement period.




Figure 6-2: Usage gauge

Details of the usage information are displayed beneath the gauge.

Usage Tables

Usage information can also be displayed in a textual table.

[Download summary](#)

Meter	Unit	Actual Use	Entitled	Overage (since statement)	Overage (since reset)	%	Interval/Reset	Period
End2EndUHRP_MC-ReCH Download	copies	111	150	0	0	74	3 Month/12 Month	Feb 11, 2015- May 11, 2015
End2EndUHRP_MUC-NonRe Download	gb	101	100	0	1	101	3 Month/Never	Feb 11, 2015- May 11, 2015

Figure 6-3: Usage table

Usage Timelines and Comparisons

Usage information can also be displayed in an interactive Flash-based timeline. Commands in the upper left corner enable zooming in to different time periods, and you can click and drag the graph left and right to control the dates for which data are being displayed.



Figure 6-4: Interactive usage timeline

A similar interactive option is the **Compare Meters** graph, which simultaneously displays multiple features' usage information over the same period of time.

Viewing Usage Reports

Producers who use FlexNet Usage Management can view usage history reports in the Producer Portal. You first search for reports on your usage-enabled products by usage search criteria. The search results show matching usage reports primarily by the associated account ID. You can click the account ID for a particular report to view usage gauges (default), tables, and timelines for that account's report.

Usage Search Criteria

The table below describes the usage search criteria available on the Usage Search page.

Table 6-4

Attribute	Description
Account ID	The ID of the customer account for which you want to see usage reports.
Usage Threshold	Specifies a minimum usage percentage for any usage meter. To see usage reports for accounts that meet or exceed fifty percent of their entitled counts, for example, set Usage Threshold to 50. To see only accounts that are at or over their entitled limits, set Usage Threshold to 100. Only accounts for which at least one meter that meets or exceeds the specified threshold are included in the search results.

Table 6-4 -

Attribute	Description
As of Date	The date limit for usage reports. Reports that occur after the specified As of Date value are excluded from the search results.
Product Line	The product line for which you want to see usage reports. Only reports that include usage history for products in the specified product line are included in the search results.
Meter Name	The name of the meter (usually a feature name) for which you want to see usage reports.

Searching for Usage Reports

The following steps explain how to obtain usage reports for your customer accounts.



Task

To view a usage report

1. In the Producer Portal, click **Usage > Usage Search**. The Producer Portal opens the Usage Search page.
2. Specify search criteria for the usage reports you want to see.
3. Click **Search**. The Producer Portal shows a list of usage reports that match your search criteria.
4. Click the **Account ID** value for a report to see the usage report page for that account.

The Producer Portal opens the View Usage for Account: <customer account> page. This page includes usage gauges, tables, and timelines for the designated product line and date. Click the report type buttons to switch between report types.

This page also allows you to select different product lines and to alter the dates for which usage history data is shown.

- Click the **Product Family** control to choose from the product families to which the current customer account is entitled.
- Click the **As of Date** control to set a different date limit for the usage reports.

See Also

[About Usage Reports](#)

[About Usage Models](#)

Listing Usage Models

Producers who use FlexNet Usage Management can view available usage models in the Producer Portal. Usage models are selected when you create or edit a usage-enabled product. They mainly define the reporting interval for usage history reports.



Task **To list usage models**

- Click **Usage > List Usage Models**.

The Producer Portal opens the List Usage Models page.

See Also

[About Usage Models](#)

Uploading Usage Data

Mainly for internal testing, producers can upload raw usage data to the Producer Portal. This option allows you to see how usage data captured by your usage-enabled FlexNet Embedded clients is rendered in usage history reports without waiting for the clients to report data over long periods.

To upload historical usage data, you must create a comma-separated value file in which each line follows the syntax shown below:

```
ISO 8601 date,count,feature name,activation code[,requestor ID,acquisition ID,key=value, ...]
```

Additional file content and format requirements appear on the Upload Historical Usage page.



Task **To upload usage data**

1. In the Producer Portal, click **Usage > Upload Historical Usage**. The Producer Portal opens the Upload Historical Usage page.
2. On the Upload Historical Usage page, use the browser controls to specify a CSV file on your system to upload. (The exact controls vary in different web browsers.)
3. Click **Upload**.

The Producer Portal uploads the usage data.


Managing Accounts and Users

You can manage accounts and users using the commands in the Accounts & Users menu. See the following sections for instructions on account and user management:

Table 7-1 •

Topic	Description
Managing Users	Manage users and roles (sets of permissions) of an account.
Managing Accounts	Manage accounts and contacts.
Account Health	View account health parameters including overall health, renewal health, and consumption.

The figure below depicts relationships among accounts, sub-accounts, and users.



Managing Users

This section is organized into the following topics.

Table 7-2 • Managing Users

Topic	Description
About Users	Discusses users as they exist in FlexNet Operations.
FlexNet Operations Default Users	Describes the built-in, default users included with FlexNet Operations.
Managing Your Profile	Explains how to edit your profile and how to change your password.
Browsing Users	Shows how to browse existing users in the Producer Portal.
Creating a User	Explains how to create new users manually and how to import a new user from a directory service.
Editing a User	Covers editing existing users and resetting a user password.
Linking Product Lines to User Accounts	Describes how to link user accounts to product lines.
Deleting a User	Shows how to delete users from FlexNet Operations.

Table 7-2 • Managing Users

Topic	Description
Deactivating and Reactivating a User	Explains how to set a user's status to active or inactive.
Working with Roles and Permissions	Includes a discussion about the use of roles and permissions as well as instructions about adding, editing, activating and deactivating, and deleting roles.

See Also

[About Users](#)

[Managing Accounts](#)

About Users

A user can belong to one of four types. On the **Manage Users** page, each of these types has a tab as described below.

- Customer Users – End users of a producer's software or device.
- Producer Users – Software producer or intelligent device manufacturer users.
- Partner Users – Distribution partner users like wholesalers, distributors, resellers, and retailers.
- Self Registered Users – Users who self-register by logging in to the End-User Portal with an entitlement ID or activation ID and set up their own user account. Optionally, users can select to be associated with an existing Self-Registered account by providing the account ID upon self-registration, instead of creating a new account.

To log in to FlexNet Operations, a user must provide a user name and password. Revenera creates the initial user account for a producer's FlexNet Operations system administrator. Then that system administrator creates any additional users required for the producer's account and for the producer's customers (end users).

Beyond the ability to simply log in, the activities a user can perform are based on the permissions that user has been granted. However, permissions are not assigned to users directly. Instead, permissions are grouped into roles and FlexNet Operations users are assigned one or more roles. FlexNet Operations users belong to either a producer account or a customer account. Users who self-register through the End-User Portal belong to the accounts for Portal Accounts. If a self-registered user supplies a company name while registering, a new account is created for the new company name and the user assigned to it.

Some user names are intended to be shared logins. A shared login is intended as a proxy user, not as a user that logs in directly. For example, when any customer logs in to the End-User Portal with an activation ID, a shared login, portaluser, logs in on behalf of the customer. Shared logins are indicated on the Users page with an icon. They do not appear in the **Logged-In Users** page, their last login date is not recorded, nor are they deactivated automatically after a number of bad logins. The profile of a shared login cannot be edited.

Both shared and non-shared users can log in to FlexNet Operations from multiple browsers simultaneously.

See Also

[FlexNet Operations Default Users](#)

[Working with Roles and Permissions](#)

[Default Accounts](#)

FlexNet Operations Default Users

By default, the following users are provided with FlexNet Operations:

Table 7-3 ▪ FlexNet Operations Users

User Name	Description
admin	Non-shared login with the System Administrator role. This user cannot be made inactive.
portaluser	Shared login for users of the End-User Portal who log in with entitlement ID or activation ID. This user is assigned the Portal User role.
trustedstorageuser	Shared login that does not appear in any of the user management pages. It is displayed in the fulfillment history as the user who performs trusted transactions.
legacyuser	Shared login that does not appear in any of the user management pages. It is displayed in the fulfillment history as the user who imported legacy fulfillments from another system.

See Also

[Default Accounts](#)

[About Users](#)

Managing Your Profile

The following topics cover how to manage your own user profile and password settings.

Table 7-4 ▪

Topic	Description
Editing Your User Profile	Discusses how to change your user profile settings.
Changing Your FlexNet Password	Explains how to change your password.
If You Forget Your FlexNet Password	Explains how to follow the password recovery procedure when you forget your password.
Finding Your Container Registry Secret	Explains where to find your container registry secret that allows you to log in to the Reverera registry.

See Also

[About Users](#)

[FlexNet Operations Default Users](#)

Editing Your User Profile

You can edit your profile using the **User** menu. (The **User** menu is near the **System** menu at the top of the Producer Portal page. It shows the user name of the current user.)

If you are not a shared user, you can edit your user profile. A shared user can only view the profile.



Task **To view your profile or edit your profile**

1. In the **User** menu, click your user name and then click **My Profile**.
2. Edit any of the following fields:
 - **First Name**
 - **Last Name**
 - **Email Address**
 - **Opt-in to receive email**: If your instance of FlexNet Operations is integrated with an external marketing tool and you want to receive promotional marketing email messages from that tool, set this option to **Yes**.



Note - This option does not control whether you will receive automatically-generated emails sent by FlexNet Operations based on certain event triggers, such as to communicate about new entitlements or other events.

- **Old Password**
- **New Password**
- **Confirm Password**
- **Secret Question and Secret Answer**
- **Phone Number and Fax Number**
- **Street**
- **City**
- **State/Province**
- **Zip/Postal Code**
- **Country**
- **Time Zone**

Your user name, accounts, and whether the user name is a Shared Login cannot be edited through the user profile.



Note - The roles assigned to you are not displayed in the **Edit Profile** page.

3. Click **Save**.



Note - To change your password, enter the old password; then enter and confirm the new password. No email message is sent reminding you of your new password. The next time you log in, enter your new password.

See Also

[Changing Your FlexNet Password](#)
[If You Forget Your FlexNet Password](#)

Changing Your FlexNet Password

The **Change Password** page appears when you enter your user name and a system-generated FlexNet Operations password the first time you log in to FlexNet Operations. Use this page to change your system-assigned password to one that you choose.



Task **To change your FlexNet Operations password**

1. Enter your old password, the system-generated password that you entered when you logged in.
2. Enter and confirm a new password of your choice.
3. Select a secret question and the answer in case you forget your password. You must define a secret question and answer to reset your password yourself if you forget it.
4. Click **Continue** to complete the login process.



Note - You can change your password or add a secret question and answer at a later time by editing your user profile.

See Also

[Editing Your User Profile](#)
[If You Forget Your FlexNet Password](#)

If You Forget Your FlexNet Password

If you forget your password in the future and have specified a secret question and its answer, you can have your password sent to you by email.



Task **To have your FlexNet Operations password sent to you by email**

1. On the FlexNet Operations login page, click **Forgot your password?**
2. On the **Password Reset** page, enter your FlexNet Operations user ID and click **Continue**.

If FlexNet Operations recognizes your account, it displays your secret question and prompts you to enter the answer you specified when the account was created. This is required.

3. Enter the answer to your secret question and click **Continue**.

If you correctly answer the security question, FlexNet Operations sends an email containing a system-generated password to your email address. When you log in with that password, FlexNet Operations prompts you to change your password.



Note - If you did not specify a secret question and answer, you must contact the FlexNet Operations administrator to have a new password sent to you.

See Also

[Editing Your User Profile](#)

[Changing Your FlexNet Password](#)

Finding Your Container Registry Secret



Version - This functionality is only available for producers who use the Software Delivery module.

Producer users who distribute containerized software need the container registry secret to log in to the Revenera registry.

The container registry secret is only displayed for producer users with the **View and Manage Download Packages** permission.



Task **To determine your container registry secret**

Point to the **User** menu (next to the **System** menu at the top right corner of the Producer Portal page) and click **My Profile**. The option **Container registry secret** shows your secret. You can use **Copy** to copy the secret to the clipboard.

See Also

[Managing Containerized Applications](#)

Browsing Users

FlexNet Operations users are displayed in the Users page. Users assigned roles with the **View Users**, **View and Manage Users**, **View and Manage Customer Users**, or **View and Manage Partner Users** permissions can view users in the Producer Portal.



Task **To browse existing users**

- Click **Accounts & Users > All Users**.

The Producer Portal shows the **Manage Users** page. On the **Manage Users** page, you can view the following information:

- Whether a user is a shared user. (Shared users are marked with an icon showing several people.)
- **Display Name:** Full name of user.

- **User Name:** Login name of the user.
- **Email Address:** The user's email address.
- **Type:** Select either **User** or **Contact**. A contact is a user account that cannot log in, and is maintained for account contact purposes.
- **Account:** All accounts to which the user belongs.

Click on a user to view user details, edit the user, view the transaction history for the user account, and so forth.

See Also

[About Users](#)

[Creating a User](#)

[Editing a User](#)

[FlexNet Operations Default Users](#)

Creating a User

FlexNet Operations users appear in the Users page of FlexNet Operations.



Note - To perform tasks using FlexNet Operations, a user is required to have one or more permissions that are defined by the application. Permissions are not assigned to users directly. Instead permissions are grouped into roles and FlexNet Operations users are assigned one or more roles. Users assigned a role with **View and Manage Users** permission can view, add, and edit all types of users. Users assigned roles with the **View and Manage Customer Users** permission or **View and Manage Partner Users** permission can view all users but can add and edit only customer users or partner users, respectively.



Task

To add a FlexNet Operations user

1. Click **Accounts & Users > Create User**. This link opens the **Create a User** page.
2. In **User Details**
 - a. **End-User Portal Access?**: A user who can log in is able to access FlexNet Operations. If not, the user account is maintained for contact purposes only. Such users are sometimes referred to as *contacts*.
 - b. **User Name**: FlexNet Operations users use their email address to log in.
 - c. **Time Zone**: If the user can log in, select the user's time zone from the drop-down list.
 - d. **Status**: Leave the user status set to Active. (The records of an Inactive user remain on file, but the user no longer has access to FlexNet Operations.)



Note - Multiple entries of an incorrect password automatically set the user's status to Inactive. The user can be reactivated by an administrator after the user's legitimacy is confirmed.

- e. **Shared Login**: Select Shared Login if this user account is to be shared by multiple people. A shared login can be useful for setting up proxy or group user accounts, such as a user who submits web service requests.

3. In **Contact Details**

- a. Enter the **First Name** and **Last Name** of the user (required).
- b. Enter the **Email Address** of the user (required). If this is a shared login, specify the email address of a FlexNet Operations administrator in this field. The email address serves as the user name.
- c. **Opt-in to receive email:** If your instance of FlexNet Operations is integrated with an external marketing tool and you want this user to receive promotional marketing email messages from that tool, set this option to **Yes**.



Note - This option does not control whether the user will receive automatically-generated emails sent by FlexNet Operations based on certain event triggers, such as to communicate about new entitlements or other events.

- d. **Expiring Entitlements Email:** Select whether the user receives renewal reminders about expiring and expired entitlements (only for customer users).
 - e. Enter the user's contact information: **Phone Number, Fax Number, Street, City, State/Province, ZIP/Postal Code, and Country**.
 - f. Select the **Locale** of the user. This setting is applied when using the option **View As End User** (see [View End-User Portal as End-User](#)). This setting will be overwritten by the default locale or the locale explicitly selected by the user when logging in to the End-User Portal. In addition, the **Locale** setting specifies the language of some of the emails sent by FlexNet Operations (such as the Reset Password email).
4. Link the user to one or more accounts. Each user must be linked to one or more accounts. If the user must log in to the Producer Portal (an internal user), link the user account with a producer account. If the user must log in to the End-User Portal, either as a customer or a partner, link the user account to a customer or partner account. A user can belong to multiple accounts but all of those accounts must be of the same type. After a user is saved as a member of a customer account, the account can be changed only to another customer account.

To link users to an account, click **Link Existing Accounts** to link existing accounts to the user. Select the accounts you want to link and click **OK**.



Note - When linking a user to an account, an optional expiration date can be set if the **Enable User Expiration** is enabled in the system configuration. See [Configuring System Settings](#) for more information.

5. Optionally, for customer users, link the user to one or more product lines now, or product lines can be linked later. See [Linking Product Lines to User Accounts](#).



Note - Linking of product lines is available only when product lines functionality is enabled in the system configuration page (**System > Configure > FlexNet Operations**). See [Managing Product Lines](#) for details.

6. Click **Save**.

When a new user account is saved, an email containing a system-generated password and login instructions is sent to the user's email address. To log in the first time, the user logs in using the system-generated password and is immediately prompted to change the password.

See Also

[FlexNet Operations Roles](#)

[FlexNet Operations Permissions](#)

Editing a User

Users assigned a role with the **View and Manage Users** permission can view, add, and edit all types of users. Users assigned roles with the **View and Manage Customer Users** permission or **View and Manage Partner Users** permission can edit only customer users or partner users, respectively. The **Create a User** page displays the date the user was created and last logged in (if a non-shared user) and is also used to reset the user's password.

Edit User Information

Use the following instructions to modify a user's details, contact information, or account. Remember: To locate a difficult to find user, use the search feature on the **Manage Users** page.



Task *To edit an existing FlexNet Operations user*

1. Click **Accounts & Users > All Users**. This link opens the **Manage Users** page.
2. On the **Manage Users** page, locate the user you want to edit. Note: Users can appear on different tabs. Be sure you are looking at the right tab for the user.
3. In the **Users** list, click a user name to view the **Create a User** page.
4. Edit the values of any of the editable fields. Email address is never editable. At least one account must be linked to the user. If the user must log in to the End-User Portal or Producer Portal, at least one role must be assigned.
5. Click **Save** to save your changes to the user.

Reset a Password

Use the following steps to reset the password of a user.



Task *To reset a user's password*

1. Click **Accounts & Users > All Users**. This link opens the **Manage Users** page.
2. On the **Manage Users** page, locate the user you want to edit. Note: Users can appear on different tabs. Be sure you are looking at the right tab for the user.
3. In the **Users** list, click a user name to view the **Create a User** page.
4. On the **Create a User** page, click **Reset Password**.

If the user is not shared, an email is sent to the user with a new system-generated password. The user logs in with the system-generated password and is immediately prompted to change the password.

If the user is shared, the email containing a system-generated password is sent to a FlexNet Operations administrator (if you specified the administrator's email address when the user was created). The administrator must log in to FlexNet Operations with the system-generated password, then change the password and keep a record of it. The administrator must send this new password to all users of the shared login.

View End-User Portal as End-User

Users assigned a role with the **View As End User** permission can access the End-User Portal as a selected end-user in view-only mode. Any data that is updated when acting as end-user does not persist.



Task *To view the End-User Portal as end-user*

1. Click **Accounts & Users > All Users**. This link opens the **Manage Users** page.
2. On the **Manage Users** page, locate the user you want to act as. Note: Users can appear on different tabs. Be sure you are looking at the right tab for the user.
3. In the **Users** list, click a user name to view the **Create a User** page.
4. On the **Create a User** page, click **View As End User**.

Set or Clear an Expiration Date

Use the following instructions to control how long a user is linked to an account.



Version - This option is only available if the **Enable User Expiration** field is enabled in the System Configuration. See [Configuring System Settings](#) for more information.



Task *To set or clear the expiry date for a user*

1. Click **Accounts & Users > All Users**. This link opens the **Manage Users** page.
2. On the **Manage Users** page, locate the user you want to edit. Note: Users can appear on different tabs. Be sure you are looking at the right tab for the user.
3. In the **Users** list, click a user name to view the **Create a User** page.
4. Under **Accounts**, find the account you want to limit the user's access to.
5. Under **Expiry date** for an Account, either enter a date to set an expiration date or clear the field to remove an expiration date. To disable the expiration date for all users, unselect the **Enable User Expiration** in the System Configuration. If the expiration date is cleared or disabled, a user's access to the account does not expire. See [Configuring System Settings](#) for more information.

See Also

[Deleting a User](#)
[Working with Roles and Permissions](#)
[About Users](#)

Linking Product Lines to User Accounts

When the product lines functionality (with visibility restrictions) is enabled, FlexNet Operations filters what customer users see based on the product lines linked to the users' accounts. Only line items that include products in product lines to which the user account is linked are visible.



Important - A user account cannot be linked to product lines until the user has been linked to accounts.

The required product lines functionality can be enabled in **System > Configure > FlexNet Operations > Enable Product Lines for Products, Users, and Accounts**. (See [Managing Product Lines](#) for details.)



Task To link product lines to a user account

1. On the **Create a User** page, click **Link Product Lines**. The Select Product Lines for the User page opens in a pop-up window.
2. On the Select Product Lines for the User page, select the product lines you want to link, and click **OK**.

Product lines are linked to the current user account when you click OK. It is only necessary to save the user account if you have made other changes to the user.



Task To remove product lines from a user account

1. On the **Create a User** page, select the product lines you want to remove and click **Remove Product Lines**.
2. Click **OK** to confirm the removal.

See Also

[Creating a User](#)
[Mapping a Product to a Product Line](#)
[Managing Product Lines](#)

Deleting a User

You can delete users from FlexNet Operations if users have no dependencies (such as, for example, line items, entitlements, or alert subscriptions). Deleted users are removed permanently from the database. If you want to keep the user in the database but restrict access, consider deactivating the user instead.

You cannot permanently delete a user who has dependencies. However, you can perform a force delete by confirming that you want to remove a user, when prompted by a dialog. The force delete ensures that the user record and its dependencies are retained but placed in an inactive state. In this state, all fields on the user record are rendered obsolete, login-credential resets for the user are prohibited, and no further access to the user record is allowed.

Note that this option applies only to the forced deletion of non-producer users with dependencies.



Task *To delete a user*

1. Click **Accounts & Users > All Users**. The **Manage Users** page opens.
2. On the **Manage Users** page, select the user you want to delete.
3. Click **Delete**.
4. Click **OK** to confirm deletion.
5. If the user has dependencies, click **Delete** to confirm the force delete.

See Also[Creating a User](#)[Deactivating and Reactivating a User](#)[About Users](#)

Deactivating and Reactivating a User

User status is displayed in the **Create a User** page. Both shared and non-shared users can be deactivated manually or automatically. A non-shared user can be reactivated only manually; a shared user can be reactivated manually or automatically.

Users assigned a role with the **View and Manage Users** permission can deactivate and reactivate all types of users manually. Users assigned roles with the **View and Manage Customer Users** permission or **View and Manage Partner Users** permission can deactivate and reactivate only customer users or partner users, respectively.



Task *To deactivate a user manually*

1. Click **Accounts & Users > All Users**. The **Manage Users** page opens.
2. In the **Users** list, click a user name to deactivate.
3. In the Status drop-down list, select **Inactive**.
4. Click **Save**.

A user is deactivated automatically after more incorrect consecutive login attempts than allowed. For non-shared users, the default number of consecutive failed authentications is 3; for shared users, the default number of consecutive failed authentications is 6. This number can be configured in the FlexNet Platform Server configuration (setting **Consecutive Failed Authentications**). When a user is deactivated automatically, the User Deactivated alert is triggered (if that alert is configured).

A deactivated non-shared user must be reactivated manually.



Task *To reactivate a user manually*

1. Click **Accounts & Users > All Users**. The **Manage Users** page opens.
2. In the **Users** list, click a user name to reactivate.
3. In the Status drop-down list, select **Active**.

4. Click **Save**.

A reactivated user is informed by email. Reactivation does not affect a user's password. If the reactivated user is shared, an administrator receives the email stating that the user is reactivated.

Automatically Reactivating Shared Users

When a shared user account is deactivated due to too many failed consecutive login attempts, it can be automatically reactivated after a specified time. You can set this time in the FlexNet Platform Server configuration (setting **Minutes for re-enabling a shared login after deactivation**). The default is 3 minutes.

Reactivating Using Google reCAPTCHA

The Google reCAPTCHA mechanism enables a shared user whose account is locked (due to too many consecutive failed login attempts) to have their account reactivated before the timeout (set in the FlexNet Platform Server configuration) has elapsed. In this case, the login screen of the End-User Portal shows the "I'm not a robot" check box which enables the shared user to validate their account. To use Google reCAPTCHA, you need to provide the site key and the secret key in the FlexNet Platform Server configuration.

See Also

[Editing a User](#)

[Configuring the FlexNet Platform Server](#)

Working with Roles and Permissions

You can administer roles and permissions for user access.



Important - Regarding FlexNet Operations roles and permissions, keep in mind the following:

- Permissions do not have hierarchies. For one user to manage another user, the managing user must have at least all of the permissions of the user they want to manage.
- A permission can only be assigned to a user if that assignee has that permission themselves.

Table 7-5 - Working with Roles and Permissions

Topic	Description
Assigning a Role to a User	Shows how to assign one or more roles to an existing user.
Browsing Roles	Explains how to browse roles from the Administer Roles and Permissions page.
Browsing Users with a Role	Describes how to view users who are assigned a particular role.
Adding a Role	Shows how to add a user-defined role.
Editing a Role	Describes how to edit an existing role.
Deleting a Role	Explains how to delete a role.

Table 7-5 ▪ Working with Roles and Permissions

Topic	Description
Deactivating and Reactivating a Role	Shows how to manually deactivate or reactivate a role.
FlexNet Operations Permissions	Describes FlexNet Operations permissions. Permissions are grouped into roles.
FlexNet Operations Roles	Describes FlexNet Operations roles. Permissions are grouped into roles. Roles are assigned to user accounts.

Assigning a Role to a User

You can assign a role to a user on the user's **Create a User** page. These assignments are made per account in the Account table near the end of the page.



Note ▪ *Not all users have sufficient permissions to assign or remove roles.*



Task *To assign a role to a user*

1. On the **Create a User** page, select the check boxes for the roles you want to assign to the current user. The user must have at least one role assigned for each account to which they are linked. (Possible roles appear in the Roles column of the Accounts table—one set per account.)
2. Click **Save**.

The Producer Portal saves the role modifications and refreshes the **Create a User** page.



Task *To remove a role from a user*

1. On the **Create a User** page, select the check boxes for the roles you want to remove from the current user.
2. Click **Save**.

The Producer Portal saves the role modifications and refreshes the **Create a User** page.

See Also

[Editing a User](#)
[Creating a User](#)
[Working with Roles and Permissions](#)

Browsing Roles

Roles for FlexNet Operations are displayed in the **Roles** page. Users assigned a role with the **View Roles** or **View and Manage Roles** permission can view a summary of roles.



Task *To view a summary of existing roles*

1. Click **Accounts & Users > All Roles**.
2. In the **Roles** page, you can view the following information:
 - **Role Name:** Name of the role.
 - **Status:** Whether the role is active or inactive and whether it is a system-defined role.
 - **Mapped Users:** Shows links to users who are assigned to this role.

See Also

[FlexNet Operations Roles](#)
[FlexNet Operations Permissions](#)

Browsing Users with a Role

It is possible to view all of the users who have been assigned a particular role. Users assigned a role with the **View Users** and **View Roles** permissions can view users with a particular role.



Task *To view the users who have been assigned a particular role*

1. Click **Accounts & Users > All Roles**.
2. To see the users with a specific role, click the Users link for that role under Mapped Users.
3. In the **Users for Role** page, you can view the list of users who are assigned this role. In addition, you can determine whether a user is shared. Shared users are marked with an icon showing several people. The following summary information is displayed.
 - **User Name:** Login name of the user (typically, an email address).
 - **Display Name:** Full name of the user.
 - **Date Created:** Date the user was created.
 - **Date of Last Login:** Date of last login by the user; this date is not recorded for shared users.
 - **Status:** Whether the user is active or inactive.

See Also

[FlexNet Operations Roles](#)

Adding a Role

To perform tasks using FlexNet Operations, a user must have the appropriate permissions defined by the application. Permissions are not assigned to users directly; permissions are grouped into roles and FlexNet Operations users are assigned one or more roles.

Roles are either system-defined or user-defined. System-defined roles cannot be edited by any users; users assigned a role with the **View and Manage Roles** permission can view, add, and edit user-defined roles.



Task **To add a user-defined role**

1. Click **Accounts & Users > All Roles**.
2. Click **Add Role**.
3. In the **Add Role** page:
 - a. Enter the **Name** of the role, for example, User Management Administrator. A role is usually given the name of a type of user.
 - b. Enter the **Description** of the role.
 - c. In Role Type, select **Publisher Role** if the role is intended for producer users, or **Portal Role** if the role is intended for End-User Portal users.
 - d. Leave the **Status** of the role **Active**.
 - e. Assign one or more permissions to the role.
4. Click **Save**.
5. Verify in the **Roles** page that the role was added.

See Also

[FlexNet Operations Roles](#)
[FlexNet Operations Permissions](#)

Editing a Role

Roles are either system-defined or user-defined. System-defined roles cannot be edited; users assigned a role with the **View and Manage Roles** permission can view, add, and edit user-defined roles.



Task **To edit an existing role**

1. Click **Accounts & users > All Roles**.
2. In the **Roles** table, click a role name to view the **Edit Role** page.
3. Edit the values of any of the editable fields. At least one permission must be assigned to a role.



Important - Changing the role type is only allowed if the role whose type is being changed is not currently assigned to a user.

4. Click **Save** to save your changes to the role.

See Also

[FlexNet Operations Roles](#)
[FlexNet Operations Permissions](#)

Deleting a Role

Roles can be deleted from FlexNet Operations.



Task *To delete an existing role*

1. Click **Accounts & Users > All Roles**.
2. In the **Roles** table, click the name of the role you want to delete.
3. Click **Delete**.
4. Click **OK** to confirm deletion.

See Also

[FlexNet Operations Roles](#)

Deactivating and Reactivating a Role

A role can be deactivated or reactivated manually. Users assigned a role with the **View and Manage Roles** permission can deactivate and reactivate roles.



Task *To deactivate or activate an existing role*

1. Click **Accounts & Users > All Roles**.
2. In the **Roles** table, click a role name to view the **Edit Role** page.
3. Set the **Status** to **Inactive** or **Active**.
4. Click **Save** to save your changes to the role.

See Also

[Editing a Role](#)

[FlexNet Operations Roles](#)

FlexNet Operations Permissions

Permissions are grouped into roles, and roles are assigned to users. The following permissions are available in FlexNet Operations:

- [Alert Management](#)
- [System Administration](#)
- [Operations Feature Bundles](#)
- [Operations License Models](#)
- [Operations Entitlements \(Producer Portal\)](#)
- [Accounts \(End-User Portal\)](#)

- [Trusted Storage Licensing \(End-User Portal\)](#)
- [Operations Web Services](#)
- [Operations Export Import](#)
- [User Management](#)
- [Account Management](#)
- [Operations Features](#)
- [Operations Products, Suites, and Maintenance](#)
- [Operations Part Numbers \(Producer Portal\)](#)
- [Operations License Management \(Producer Portal\)](#)
- [Operations Policies](#)
- [Operations Trusted Storage Licensing \(Producer Portal\)](#)
- [Reporting](#)
- [Child Account \(End-User Portal\)](#)
- [License Technologies](#)
- [FlexNet Embedded](#)
- [FlexNet Embedded \(End-User Portal\)](#)
- [Customer Growth](#)
- [Usage](#)
- [Updates](#)

Alert Management

The following Alert Management permissions are available:

Table 7-6 - Alert Management Permissions

Permission	Description
View and Subscribe Alerts	Allows a user to browse available alerts and subscribe to them.
View and Manage Alert Configurations	Allows administrator to configure alerts and access the alert cleanup service.

System Administration

The following System Administration permissions are available:

Table 7-7 - System Administration Permissions

Permission	Description
View System Information	View system information displayed in the System Information page (click System > About Advanced Lifecycle Management Module).
View and Manage Configurations	Configure the database connection, the behavior of the FlexNet Platform Server, the behavior of the Producer Portal, and the behavior of different portions of FlexNet Operations. Access to all functionality of the System Configuration page (click System > Configure).
View and Manage Custom Content	Create and maintain custom content, including the ability to enable/disable its visibility on the End-User Portal.
View and Manage Email Templates	Maintain email templates, including enabling/disabling and creating variations.
Create Custom Attribute	Create and edit generic custom attributes.
Merge Entitlements from Self-Registered Account to Customer Account	Merge data (entitlements and users) from self-registered account to customer accounts.

Operations Feature Bundles

The following FlexNet Operations Feature Bundles permissions are available:

Table 7-8 - Operations Feature Bundles Permissions





Permission	Description
View Feature Bundles	View feature bundles in read-only mode.
Update Feature Bundles	Edit feature bundles.  Important - If Update Feature Bundles is assigned to a role, also assign View Feature Bundles .
Create Feature Bundles	Add feature bundles.  Important - If Create Feature Bundles is assigned to a role, also assign Update Feature Bundles .

Table 7-8 ▪ Operations Feature Bundles Permissions

Permission	Description
Change Feature Bundle State	<p>Change the state of feature bundles, such as deploying a feature bundle.</p>  <p>Important ▪ If Change Feature Bundle State is assigned to a role, also assign Update Feature Bundles.</p>
Delete Feature Bundles	<p>Delete feature bundles.</p>  <p>Important ▪ If Delete Feature Bundles is assigned to a role, also assign View Feature Bundles.</p>

Operations License Models

The following FlexNet Operations License Models permissions are available:

Table 7-9 ▪ Operations License Models Permissions





Permission	Description
View License Models	View license models in read-only mode.
Create License Models	<p>Add license models.</p>  <p>Important ▪ If Create License Models is assigned to a role, also assign View License Models.</p>
Update License Models	<p>Edit license models.</p>  <p>Important ▪ If Update License Models is assigned to a role, also assign View License Models.</p>
Delete License Models	<p>Delete license models.</p>  <p>Important ▪ If Delete License Models is assigned to a role, also assign View License Models.</p>

Table 7-9 - Operations License Models Permissions

Permission	Description
Change License Model State	Change the state of license models. 
	Important - If Change License Model State is assigned to a role, also assign Update License Models .

Operations Entitlements (Producer Portal)

The following FlexNet Operations Entitlements permissions are available:

Table 7-10 - Operations Entitlements (Producer Portal) Permissions








Permission	Description
View Entitlements	View entitlements in read-only mode.
Update Entitlements	Edit entitlements. This includes changing any attributes of the entitlement, adding line items to the entitlement, upgrading an entitlement, renewing an entitlement, merging entitlements and fulfillments, and upselling an entitlement. 
	Important - If Update Entitlements is assigned to a role, also assign View Entitlements .
Upsell Entitlements	Upsell entitlements. 
	Important - If Upsell Entitlements is assigned to a role, also assign Update Entitlements .
Upgrade Entitlements	Upgrade entitlements. 
	Important - If Upgrade Entitlements is assigned to a role, also assign Update Entitlements .
Renew Entitlements	Renew entitlements. 
	Important - If Renew Entitlements is assigned to a role, also assign Update Entitlements .

Table 7-10 • Operations Entitlements (Producer Portal) Permissions

Permission	Description
Create Entitlements	<p>Add entitlements.</p>  <p>Important - If Create Entitlements is assigned to a role, also assign Update Entitlements.</p>
Change Entitlement State	<p>Change the state of entitlements.</p>  <p>Important - If Change Entitlement State is assigned to a role, also assign Update Entitlements.</p>
Delete Entitlements	<p>Delete entitlements.</p>  <p>Important - If Delete Entitlements is assigned to a role, also assign View Entitlements.</p>
Edit Sent Emails	Allows email content to be updated after the message has been sent. Used to correct errors.
Edit Unsent Emails	Allows the user to copy an email, and edit email content and distribution list.
Create Email Notifications	Send email to users entitled to download packages or files.
Queue Email	Allows the user to schedule email delivery after approving the message content.

Accounts (End-User Portal)

The following End-User Portal account permissions are available:

Table 7-11 • Accounts (End-User Portal) Permissions

Permission	Description
View Entitlements	View entitlements for user's accounts in read-only mode.

Table 7-11 ▪ Accounts (End-User Portal) Permissions





Permission	Description
Generate Licenses	<p>Generate a certificate license through the End-User Portal.</p>  <p>Important ▪ If Generate Licenses is assigned to a role, also assign View Entitlements.</p> <p>For FlexNet Embedded, when Generate Licenses permission is assigned to a role, an end user can map add-ons to a device.</p>
Rehost	<p>Rehost a certificate license through the End-User Portal.</p>  <p>Important ▪ If Rehost is assigned to a role, also assign Generate Licenses.</p>
Repair	<p>Repair a certificate license through the End-User Portal.</p>  <p>Important ▪ If Repair is assigned to a role, also assign Generate Licenses.</p>
Return	<p>Return a certificate license through the End-User Portal.</p>  <p>Important ▪ If Return is assigned to a role, also assign Generate Licenses.</p> <p>For FlexNet Embedded, when Return permission is assigned to a role, an end user can remove add-ons from a device.</p>
Manage Users	Manage users through the End-User Portal.
Manage Accounts	Manage accounts through the End-User Portal.
View Licenses	View licenses for a user's accounts in read-only mode.
Transfer Line Items	Transfer entitlement line items through the End-User Portal.
View Devices	View devices for a user's accounts in read-only mode.
Split Line Items or Bulk Entitlements	Split line items or bulk entitlements through the End-User Portal.
View Accounts	View accounts in read-only mode.
View Users	View users in read-only mode.
Transfer Hosts/Move Devices	Transfer hosts or move devices through the End-User Portal.

Table 7-11 ▪ Accounts (End-User Portal) Permissions

Permission	Description
Get Downloads	Get downloads through the End-User Portal.
View Expiring Entitlements	View the Expiring Entitlements page, subscribe to renewal reminders, receive Renewal Reminder email messages. The View Expiring Entitlements covers both expiring entitlement and expired entitlement features.

Trusted Storage Licensing (End-User Portal)

The following End-User Portal trusted storage licensing permissions are available:


Table 7-12 ▪ Trusted Storage Licensing (End-User Portal) Permissions

Permission	Description
Short Code Activation	Enable short code activation in End-User Portal.
Manual Activation	Allow manual activation of trusted storage rights in End-User Portal.
Manual Return and Repair	Allow manual return and repair of trusted storage rights in End-User Portal.
Short Code Return and Repair	Allow short code return and repair of trusted storage rights in End-User Portal.

Operations Web Services

The following FlexNet Operations Web Services permission is available:

Table 7-13 ▪ Operations Web Services Permissions

Permission	Description
Execute Web Services	<p>The authenticated Web services user must have this permission to perform any FlexNet Operations task through the public Web services.</p>  <p>Important ▪ <i>In addition to this permission, the user must have task-specific permissions as well.</i></p>

Operations Export Import

The following FlexNet Operations Export Import permission is available:

Table 7-14 • Operations Export Import Permissions

Permission	Description
Export and Import	<p>This permission allows the user to import legacy fulfillments using the Importing and Exporting Entities page. For more information about how to export fulfillments from a previous version of FlexNet Operations and import them into this version, refer to Importing and Exporting Entities.</p> <p>It also enables producers to control user access to data export options for a FlexNet Operations entity to prevent inexperienced users from exporting large amounts of data and negatively impacting system performance or causing an outage. Users without Export and Import permission see only data export options with low impact, such as Selected Items, on an entity's Export drop-down menu. Users with Export and Import permission see the complete list of data export options, including those with high impact, such as All Items and Data Import Template.</p>

User Management

The following User Management permissions are available:

Table 7-15 • User Management Permissions




Permission	Description
View Users	View the list of users.
View and Manage Users	<p>View, add, and edit all types of users (customer users, producer users, partner users, and self-registered users). Reset a user's password. Access to all functionality of the Manage Users page.</p> <p></p> <p>Important - If View and Manage Users is assigned to a role, the role automatically also has the permissions defined in View and Manage Customer Users and View and Manage Partner Users.</p>
View Roles	View the list of users and view the definition of a role in read-only mode.
View and Manage Roles	View, add, and edit roles. Access to all functionality of the Administer Roles pages.
View Logged-In Users	View the list of logged in users in the system.
View As End User	Allows the producer to act as the end user in view-only mode. The end-user role remains unchanged, but updated data does not persist.

Table 7-15 • User Management Permissions

Permission	Description
View and Manage Customer Users	View, add, and edit customer users. Reset a customer user’s password. Access to all functionality of the Customer Users tab on the Manage Users page.  <i>Important - If you want to only assign permissions to view and manage customer users (but not producer users), do not assign View and Manage Users as well as View and Manage Customer Users.</i>
View and Manage Partner Users	View, add, and edit partner users. Reset a partner user’s password. Access to all functionality of the Partner Users tab on the Manage Users page.  <i>Important - If you want to only assign permissions to view and manage partner users (but not producer users), do not assign View and Manage Users as well as View and Manage Partner Users.</i>

Account Management

The following Account Management permissions are available:

Table 7-16 • Account Management Permissions

Permission	Description
View Accounts	View the list of accounts and view an account and its contacts in read-only mode.
View and Manage Accounts	View, add, and edit accounts and their contacts. Access to all functionality of the Accounts pages.





Operations Features

The following FlexNet Operations Features permissions are available:

Table 7-17 • Operations Features Permissions

Permission	Description
View Features	View features in read-only mode. Features are the bottom level in the product hierarchy.

Table 7-17 ▪ Operations Features Permissions

Permission	Description
Update Features	Edit features.  Important ▪ If Update Features is assigned to a role, also assign View Features .
Create Features	Add new features.  Important ▪ If Create Features is assigned to a role, also assign Update Features .
Change Feature State	Change the state of features, such as deploying a feature.  Important ▪ If Change Feature State is assigned to a role, also assign Update Features .
Delete Features	Delete features.  Important ▪ If Delete Features is assigned to a role, also assign View Features .
Set Feature Override	View and set the following license strings on an individual feature, overriding the license string values specified for a license model: Vendor String, Notice, Serial Number, Counted, and Reusable. To see these fields, the FlexNet Operations license file must contain the FlexNet_Ops.FeatureOverride feature.

Operations Products, Suites, and Maintenance

The following FlexNet Operations Product, Suite, and Maintenance permissions are available:

Table 7-18 ▪ Operations Products, Suites, and Maintenance Permissions






Permission	Description
View Products, Suites, and Maintenance	View products, suites, and maintenance in read-only mode.
Update Products, Suites, and Maintenance	Edit products, suites, and maintenance.  Important ▪ If Update Products, Suites, and Maintenance is assigned to a role, also assign View Products, Suites, and Maintenance .

Table 7-18 • Operations Products, Suites, and Maintenance Permissions

Permission	Description
Create Products, Suites, and Maintenance	<p>Add products, suites, and maintenance.</p>  <p>Important ▪ If Create Products, Suites, and Maintenance is assigned to a role, also assign Update Products, Suites, and Maintenance.</p>
Change Products, Suites, and Maintenance State	<p>Change the state of products, suites, and maintenance.</p>  <p>Important ▪ If Create Products, Suites, and Maintenance is assigned to a role, also assign Update Products, Suites, and Maintenance.</p>
Delete Products, Suites, and Maintenance	<p>Delete products, suites, and maintenance.</p>  <p>Important ▪ If Delete Products, Suites, and Maintenance is assigned to a role, also assign View Products, Suites, and Maintenance.</p>
Assign Product Lines	<p>Link product lines to user accounts in a customer account. (The FlexNet Operations administrator must enable product lines functionality in system configuration settings.) This permission is provided only to accounts with the administrator or portal administrator user roles by default.</p> <p>Permission to link product lines to user accounts can be granted to other user accounts by an administrator. In all cases, a user with this permission can assign only those product lines to which he or she is currently linked.</p>  <p>Note ▪ The ability to map products to product lines operates independently from the Assign Product Lines permission.</p>
Delete File Images	<p>Remove the physical file; only the metadata remains.</p>
Download File Images	<p>Download the file from the Producer Portal.</p>
Deliver to Account	<p>Subset of View and Manage Download Packages permission: creating/updating/uploading files, associating files/download packages, and restricting files to accounts.</p>
View and Manage Download Packages	<p>Manage download packages and files: creating/updating/uploading files, creating/updating download packages, associating files/download packages, associating download packages/products, EULA management, restricting download packages to accounts, and restricting files to accounts.</p>

Operations Part Numbers (Producer Portal)

The following FlexNet Operations Part Numbers permission is available:

Table 7-19 - Operations Part Numbers (Producer Portal) Permissions

Permission	Description
Create Part Numbers	Import part numbers.

Operations License Management (Producer Portal)

The following FlexNet Operations License Management permissions are available:

Table 7-20 - Operations License Management (Producer Portal) Permissions










Permission	Description
View Licenses	View licenses in read-only mode.  Important - If View Licenses is assigned to a role, also assign View Entitlements .
Generate Licenses	Generate a license.  Important - If Generate Licenses is assigned to a role, also assign View Licenses .
Rehost Licenses	Transfer a license from one host ID to another.  Important - If Rehost Licenses is assigned to a role, also assign Generate Licenses .
Repair Licenses	Modify license attributes other than the supported host IDs.  Important - If Repair Licenses is assigned to a role, also assign Generate Licenses .
Correct Publisher Error	Regenerate a license because the publisher made an error generating the original license.  Important - If Correct Publisher Error is assigned to a role, also assign Generate Licenses .


Table 7-20 • Operations License Management (Producer Portal) Permissions

Permission	Description
Stop Gap Renewal	<p>Generate a license to provide to a customer whose license has expired and has not yet completed the process of updating or renewing an entitlement.</p> <p></p> <p>Important • If Stop Gap Renewal is assigned to a role, also assign Generate Licenses.</p>
Generate Emergency Licenses	<p>Generate an emergency license: a short-term license to provide to a customer whose license has not expired but is not functioning.</p> <p></p> <p>Important • If Generate Emergency Licenses is assigned to a role, also assign Generate Licenses.</p>
Return Licenses	<p>Return licenses.</p> <p></p> <p>Important • If Return Licenses is assigned to a role, also assign Generate Licenses.</p>
Email Licenses	<p>Email a license.</p> <p></p> <p>Important • If Email Licenses is assigned to a role, also assign View Licenses.</p>

Operations Policies

The following FlexNet Operations Policies permission is available:

Table 7-21 • Operations Policies Permissions

Permission	Description
Override Policies	<p>Override any policies.</p> <p></p> <p>Important • If Override Policies is assigned to a role, also assign Generate Licenses, Rehost Licenses, Repair Licenses, and Return Licenses.</p>

Operations Trusted Storage Licensing (Producer Portal)

The following FlexNet Operations Trusted Storage Licensing permissions are available. Additional permissions must also be assigned to view the **Package Products**, **Activate Licenses**, and **Support Licenses** pages to access the trusted storage licensing functionality.

Table 7-22 - Operations Trusted Storage Licensing (Producer Portal) Permissions







Permission	Description
View Transaction Keys	View transaction keys in read-only mode.
Create Transaction Keys	Create transaction keys.  Important - If Create Transaction Keys is assigned to a role, also assign View Transaction Keys .
Delete Transaction Keys	Delete transaction keys.  Important - If Delete Transaction Keys is assigned to a role, also assign View Transaction Keys .
View Activation Specification Records (ASRs)	View Local Trial and Short Code Activation Specification Records (ASRs).
Create Local Trial ASRs	Create Local Trial ASRs.  Important - If Create Local Trial ASRs is assigned to a role, also assign View Activation Specification Records (ASRs) .
Delete Local Trial ASRs	Delete Local Trial ASRs.  Important - If Delete Local Trial ASRs is assigned to a role, also assign View Activation Specification Records (ASRs) .
Create Short Code ASRs	Create Short Code ASRs.  Important - If Create Short Code ASRs is assigned to a role, also assign View Activation Specification Records (ASRs) .

Table 7-22 • Operations Trusted Storage Licensing (Producer Portal) Permissions

Permission	Description
Delete Short Code ASRs	Delete Short Code ASRs.  Important - If Delete Short Code ASRs is assigned to a role, also assign View Activation Specification Records (ASRs) .
Manual Activations	Activate a trusted storage license.
Manual Returns	Return a trusted storage license.
Manual Repairs	Repair a trusted storage license.
Short Code Activations	Activate a trusted storage license using a short code.
Short Code Returns	Return a trusted storage license using a short code.
Short Code Repairs	Repair a trusted storage license using a short code.
Trusted Activation Requests	View trusted activation requests.

Reporting

The following FlexNet Operations Reporting permissions are available.

Table 7-23 • Reporting Permissions

Permission	Description
View Reports	Allows viewing, creating and editing of any report.
Data Api	Grants access to the Data API.

Child Account (End-User Portal)

The following sub-accounts permissions are available:

Table 7-24 • Child Account (End-User Portal) Permissions

Permission	Description
View Child Line Items	View entitlement line items belonging to all sub-accounts of the user's accounts.
Return Child Fulfillments	Perform returns on fulfillments belonging to all sub-accounts of the user's accounts.

Table 7-24 • Child Account (End-User Portal) Permissions

Permission	Description
Rehost Child Fulfillments	Perform rehosts on fulfillments belonging to all sub-accounts of the user's accounts.
Upgrade Child Fulfillments	Perform upgrades on fulfillments belonging to all sub-accounts of the user's accounts.
Renew Child Fulfillments	Perform renewals on fulfillments belonging to all sub-accounts of the user's accounts.
Transfer Child Line Items	Perform transfers of entitlement line items belonging to all sub-accounts of the user's accounts.
View Child Licenses	View licenses belonging to all sub-accounts of the user's accounts.
Generate Licenses for Child Line Items	Generate licenses for all sub-accounts of the user's accounts.
Repair Child Fulfillments	Perform repairs on fulfillments belonging to all sub-accounts of the user's accounts.
Manage Child Users	Create, manage and delete users for all sub-accounts of the user's accounts.
Manage Child Accounts	Create, manage and delete accounts for all sub-accounts of the user's accounts.
View Child Devices	View devices belonging to all sub-accounts of the user's accounts.
View Child Accounts	View all sub-accounts of the user's accounts.
View Child Users	View users for all sub-accounts of the user's accounts.

License Technologies

The following FlexNet Operations License Technologies permission is available:

Table 7-25 • License Technologies Permissions

Permission	Description
License Technologies	This permission allows the user to manage license technologies using the License Technologies page in FlexNet Operations.

FlexNet Embedded

The following FlexNet Embedded permissions are available:



Table 7-26 • FlexNet Embedded Permissions

Permission	Description
Manage Devices	This permission allows the user to manage hardware devices using the Manage Devices page. See also: FlexNet Embedded permissions Generate Licenses and Return .
Manage Publisher Identities	This permission allows the user to manage publisher identities using the Manage Publisher Identity page.

FlexNet Embedded (End-User Portal)

The following FlexNet Embedded-specific permissions affect the functionality available to End-User Portal users:

Table 7-27 • FlexNet Embedded (End-User Portal) Permissions

Permission	Description
Map by Activation IDs	<p>This permission allows the user see the Map by Activation IDs page in the End-User Portal. On this page, an end user can map one or more entitlements to an existing device or license server.</p>  <p>Important • To succeed for users who are not in the account that owns the device or license server, this process also requires that the Skip Account Check system configuration setting be enabled.</p>
Claim Device and Activate	<p>This permission allows the user to see the Claim and Activate page in the End-User Portal. Users who can view the Claim and Activate page can potentially map entitlements to devices that are owned by unrelated accounts.</p>  <p>Important • To succeed, this process also requires that the Skip Account Check system configuration setting be enabled.</p>
Edit User on Device	This permission allows the user to update the device user.

Customer Growth

The following Customer Growth permissions are available:

Table 7-28 • Customer Growth Permissions

Permission	Description
Manage and View Customer Growth	This permission allows users to view and manage customer growth menus and pages.

Usage

The following Usage permissions are available:

Table 7-29 • Usage Permissions

Permission	Description
View Usage	This permission allows users to view usage menus and pages.
Edit Usage	Allows users to view the Usage Model drop down in the Create Product page and the ability to create Metered Usage model.

Updates

The following Update permissions are available:

Table 7-30 • Updates Permissions

Permission	Description
Manage and View Updates	This permission allows users to view and manage update menus and pages.

See Also

[FlexNet Operations Permission Dependencies](#)

FlexNet Operations Permission Dependencies

This section lists only the FlexNet Operations permissions that have dependencies on other permissions or system configuration settings. For the complete list of permissions and their descriptions, including any dependencies, refer to [FlexNet Operations Permissions](#).

Operations Feature Bundles

The following FlexNet Operations Feature Bundles permission dependencies exist:

Table 7-31 -

Permission	Dependency
Update Feature Bundles	If Update Feature Bundles is assigned to a role, also assign View Feature Bundles .
Create Feature Bundles	If Create Feature Bundles is assigned to a role, also assign Update Feature Bundles .
Change Feature Bundle State	If Change Feature Bundle State is assigned to a role, also assign Update Feature Bundles .
Delete Feature Bundles	If Delete Feature Bundles is assigned to a role, also assign View Feature Bundles .

Operations License Models

The following FlexNet Operations License Models permission dependencies exist:

Table 7-32 -

Permission	Dependency
Create License Models	If Create License Models is assigned to a role, also assign View License Models .
Update License Models	If Update License Models is assigned to a role, also assign View License Models .
Delete License Models	If Delete License Models is assigned to a role, also assign View License Models .
Change License Model State	If Change License Model State is assigned to a role, also assign Update License Models .

Operations Entitlements - Producer Portal

The following FlexNet Operations Entitlements permission dependencies exist:

Table 7-33 -

Permission	Dependency
Update Entitlements	If Update Entitlements is assigned to a role, also assign View Entitlements .
Upsell Entitlements	If Upsell Entitlements is assigned to a role, also assign Update Entitlements .
Upgrade Entitlements	If Upgrade Entitlements is assigned to a role, also assign Update Entitlements .

Table 7-33 -

Permission	Dependency
Renew Entitlements	If Renew Entitlements is assigned to a role, also assign Update Entitlements .
Create Entitlements	If Create Entitlements is assigned to a role, also assign Update Entitlements .
Change Entitlement State	If Change Entitlement State is assigned to a role, also assign Update Entitlements .
Delete Entitlements	If Delete Entitlements is assigned to a role, also assign View Entitlements .

End-User Portal

The following End-User Portal permission dependencies exist:

Table 7-34 -

Permission	Dependency
Generate Licenses	If Generate Licenses is assigned to a role, also assign View Entitlements .
Rehost	If Rehost is assigned to a role, also assign Generate Licenses .
Repair	If Repair is assigned to a role, also assign Generate Licenses .
Return	If Return is assigned to a role, also assign Generate Licenses .

Web Services

The following FlexNet Operations Web Services permission dependency exists:

Table 7-35 -

Permission	Dependency
Execute Web Services	In addition to this permission, the user must have task-specific permissions as well.

Operations Features

The following FlexNet Operations Features permission dependencies exist:

Table 7-36 -

Permission	Dependency
Update Features	If Update Features is assigned to a role, also assign View Features .
Create Features	If Create Features is assigned to a role, also assign Update Features .

Table 7-36 -

Permission	Dependency
Change Feature State	If Change Feature State is assigned to a role, also assign Update Features .
Delete Features	If Delete Features is assigned to a role, also assign View Features .

Operations Products, Suites, and Maintenance

The following FlexNet Operations Product, Suite, and Maintenance permission dependencies exist:

Table 7-37 -

Permission	Dependency
Update Products, Suites, and Maintenance	If Update Products, Suites, and Maintenance is assigned to a role, also assign View Products, Suites, and Maintenance .
Create Products, Suites, and Maintenance	If Create Products, Suites, and Maintenance is assigned to a role, also assign Update Products, Suites, and Maintenance .
Change Products, Suites, and Maintenance State	If Create Products, Suites, and Maintenance is assigned to a role, also assign Update Products, Suites, and Maintenance .
Delete Products, Suites, and Maintenance	If Delete Products, Suites, and Maintenance is assigned to a role, also assign View Products, Suites, and Maintenance .

Operations License Management

The following FlexNet Operations License Management permission dependencies exist:

Table 7-38 -

Permission	Dependency
View Licenses	If View Licenses is assigned to a role, also assign View Entitlements .
Generate Licenses	If Generate Licenses is assigned to a role, also assign View Licenses .
Rehost Licenses	If Rehost Licenses is assigned to a role, also assign Generate Licenses .
Repair Licenses	If Repair Licenses is assigned to a role, also assign Generate Licenses .
Correct Publisher Error	If Correct Publisher Error is assigned to a role, also assign Generate Licenses .
Stop Gap Renewal	If Stop Gap Renewal is assigned to a role, also assign Generate Licenses .
Generate Emergency Licenses	If Generate Emergency Licenses is assigned to a role, also assign Generate Licenses .

Table 7-38 -

Permission	Dependency
Return Licenses	If Return Licenses is assigned to a role, also assign Generate Licenses .
Email Licenses	If Email Licenses is assigned to a role, also assign View Licenses .

Operations Policies

The following FlexNet Operations Policies permission dependency exists:

Table 7-39 -

Permission	Dependency
Override Policies	If Override Policies is assigned to a role, also assign Generate Licenses, Rehost Licenses, Repair Licenses, and Return Licenses .

Operations Trusted Storage Licensing

The following FlexNet Operations Trusted Storage Licensing permission dependencies exist:

Table 7-40 -

Permission	Dependency
Create Transaction Keys	If Create Transaction Keys is assigned to a role, also assign View Transaction Keys .
Delete Transaction Keys	If Delete Transaction Keys is assigned to a role, also assign View Transaction Keys .
Create Local Trial ASRs	If Create Local Trial ASRs is assigned to a role, also assign View Activation Specification Records (ASRs) .
Delete Local Trial ASRs	If Delete Local Trial ASRs is assigned to a role, also assign View Activation Specification Records (ASRs) .
Create Short Code ASRs	If Create Short Code ASRs is assigned to a role, also assign View Activation Specification Records (ASRs) .
Delete Short Code ASRs	If Delete Short Code ASRs is assigned to a role, also assign View Activation Specification Records (ASRs) .

FlexNet Embedded - End-User Portal

The following FlexNet Embedded-specific permission dependencies exist:

Table 7-41 •

Permission	Dependency
Map by Activation IDs	To succeed for users who are not in the account that owns the device or license server, this process also requires that the Skip Account Check system configuration setting be enabled.
Claim and Activate	To succeed, this process also requires that the Skip Account Check system configuration setting be enabled.


See Also

[FlexNet Operations Permissions](#)

FlexNet Operations Roles

The figure below depicts relationships among users, product lines, and user roles.

Users and Roles



The following producer and end-user roles are available by default in FlexNet Operations.

Producer User Roles

These FlexNet Operations producer user roles are available: [Customer Support Representative](#), [Executive](#), [IT Back Office Manager](#), [Order Entry](#), [Product Manager](#), [Sales Operations Manager](#), [System Administrator](#), and [Super Administrator](#).

Customer Support Representative

The Customer Support Representative processes activation requests and provides post-activation support for licenses, such as processing license returns and repairs.

Table 7-42 ▪

Customer Support Representative Permissions	
Operations Feature Bundles	
View Feature Bundles	
Operations License Models	
View License Models	
Operations Entitlements – Producer Portal	
View Entitlements	Update Entitlements
Change Entitlement State	
Account Permissions – Producer Portal	
View Entitlements	Generate License
Return	View Licenses
Repair	View Devices
Rehost	
Trusted Storage Permissions	
Short Code Activation	Manual Return and Repair
Manual Activation	Short Code Return and Repair
Access to Trusted Storage Licensing Functionality in Producer Portal	
View Activation Specification Records (ASRs)	Short Code Activations
Manual Activations	Short Code Repairs
Manual Returns	Short Code Returns
Manual Repairs	Trusted Activation Requests
Usage	
View Usage	Edit Usage

Table 7-42 •

Customer Support Representative Permissions	
User Management	
View As End User	
Account Management	
View Accounts	
Operations Features	
View Features	
Operations Products, Suites and Maintenance	
View Products, Suites and Maintenance	Download File Images
Operations License Management – Producer Portal	
View Licenses	Stop Gap Renewal
Return Licenses	Generate Emergency Licenses
Rehost Licenses	Generate Licenses
Repair Licenses	Email Licenses
Correct Publisher Error	
Customer Growth	
Manage and View Customer Growth	
Updates	
Manage and view Updates	

Executive

The Executive role is for upper management personnel who want to view product definitions, associated license models, and existing entitlements.

Table 7-43 •

Executive Permissions
Operations Feature Bundles
View Feature Bundles
Operations License Models
View License Models

Table 7-43 -

Executive Permissions	
Operations Entitlements – Producer Portal	
View Entitlements	
Account Permissions – End-User Portal	
View Entitlements	View Devices
View Licenses	
Access to Trusted Storage Licensing Functionality in Producer Portal	
View Transaction Keys	View Activation Specification Records
Usage	
View Usage	Edit Usage
Account Management	
View Accounts	
Operations Features	
View Features	
Operations Products, Suites and Maintenance	
View Products, Suites and Maintenance	
Operations License Management – Producer Portal	
View Licenses	
Customer Growth	
Manage and View Customer Growth	
Updates	
Manage and view Updates	

IT Back Office Manager

The IT Back Office Manager is responsible for integrating FlexNet Operations with an ERP or CRM application.

Table 7-44 -

IT Back Office Manager Permissions	
System Administration	
View System Information	View and Manage Configurations
Operations Feature Bundles	
View Feature Bundles	
Operations License Models	
View License Models	
Operations Entitlements – Producer Portal	
View Entitlements	Queue Email
Edit Unsent Emails	
Account Permissions – End-User Portal	
View Entitlements	View Devices
View Licenses	
Access to Trusted Storage Licensing Functionality in Producer Portal	
View Activation Specification Records (ASRs)	Trusted Activation Requests
Usage	
View Usage	Edit Usage
User Management	
View Users	View As End User
Account Management	
View Accounts	
Operations Features	
View Features	
Operations Products, Suites and Maintenance	
View Products, Suites and Maintenance	Deliver to Account
Delete File Images	View & Manage Download Packages
Download File Images	

Table 7-44 •

IT Back Office Manager Permissions	
Operations License Management – Producer Portal	
View Licenses	
Customer Growth	
Manage and View Customer Growth	
Updates	
Manage and view Updates	

Order Entry

Order Entry personnel convert order information into entitlements and fulfillments. They can also provide post-fulfillment support.

Table 7-45 •

Order Entry Permissions	
Operations Feature Bundles	
View Feature Bundles	
Operations License Models	
View License Models	
Operations Entitlements – Producer Portal	
View Entitlements	Upsell Entitlements
Change Entitlement State	Upgrade Entitlements
Update Entitlements	Renew Entitlements
Create Entitlements	
Account Permissions – End-User Portal	
View Entitlements	Generate License
Return	View Licenses
Repair	View Devices
Rehost	
Trusted Storage Permissions	
Short Code Activation	Manual Return and Repair
Manual Activation	Short Code Return and Repair

Table 7-45 -

Order Entry Permissions	
Access to Trusted Storage Licensing Functionality in Producer Portal	
View Activation Specification Records (ASRs)	Short Code Activations
Manual Activations	Short Code Repairs
Manual Returns	Short Code Returns
Manual Repairs	
Usage	
View Usage	Edit Usage
User Management	
View As End User	
Account Management	
View Accounts	
Operations Features	
View Features	
Operations Products, Suites and Maintenance	
View Products, Suites and Maintenance	
Operations License Management – Producer Portal	
View Licenses	Stop Gap Renewal
Return Licenses	Generate Emergency Licenses
Rehost Licenses	Generate Licenses
Repair Licenses	Email Licenses
Correct Publisher Error	
Customer Growth	
Manage and View Customer Growth	
Updates	
Manage and view Updates	

Product Manager

The Product Manager is responsible for defining and packaging products.

Table 7-46 -

Product Manager Permissions	
System Administration	
View and Manage HTML Content	View and Manage Email Templates
	Create Custom Attributes
Operations Feature Bundles	
Delete Feature Bundles	Change Feature Bundle State
Create Feature Bundles	Update Feature Bundles
View Feature Bundles	
Operations License Models	
Update License Models	Create License Models
Delete License Models	View License Models
Change License Model State	
Operations Entitlements – Producer Portal	
View Entitlements	Edit Unsent Emails
Account Permissions	
View Entitlements	Create Email Notifications
View Licenses	Queue Email
View Devices	
Access to Trusted Storage Licensing Functionality in Producer Portal	
View Transaction Keys	Create Local Trial ASRs
Create Transaction Keys	Delete Local Trial ASRs
Delete Transaction Keys	Create Short Code ASRs
View Activation Specification Records (ASRs)	Delete Short Code ASRs
Usage	
View Usage	Edit Usage
Account Management	
View Accounts	

Table 7-46 -

Product Manager Permissions	
Operations Features	
Delete Features	Change Feature State
Create Features	Update Features
View Features	Set Feature Override
Operations Products, Suites and Maintenance	
View Products, Suites and Maintenance	Delete File Images
Update Products, Suites and Maintenance	Download File Images
Change Products, Suites and Maintenance State	Deliver to Account
Delete Products, Suites and Maintenance	View & Manage Download Packages
Create Products, Suites and Maintenance	
Operations Part Numbers – Producer Portal	
Create Part Numbers	
Operations License Management – Producer Portal	
View Licenses	
Reporting	
Create and Edit Reports	View Reports
Customer Growth	
Manage and View Customer Growth	
Updates	
Manage and view Updates	

Sales Operations Manager

The Sales Operations Manager is a supervisory role above Order Entry personnel and Customer Support Representatives. The Sales Operations Manager has complete entitlement and fulfillment permissions.

Table 7-47 -

Sales Operations Manager Permissions
System Administration
View and Manage Email Templates

Table 7-47 -

Sales Operations Manager Permissions	
Operations Feature Bundles	
View Feature Bundles	
Operations License Models	
View License Models	
Operations Entitlements – Producer Portal	
View Entitlements	Create Entitlements
Change Entitlement State	Edit Unsent Emails
Update Entitlements	Create Email Notifications
Delete Entitlements	Queue Email
Account Permissions – End-User Portal	
View Entitlements	Generate License
Return	View Licenses
Repair	View Devices
Rehost	
Trusted Storage Permissions	
Short Code Activation	Manual Return and Repair
Manual Activation	Short Code Return and Repair
Access to Trusted Storage Licensing Functionality in Producer Portal	
View Activation Specification Records (ASRs)	Short Code Activations
Manual Activations	Short Code Repairs
Manual Returns	Short Code Returns
Manual Repairs	
Usage	
View Usage	Edit Usage
User Management	
View As End User	
Account Management	
View Accounts	

Table 7-47 -

Sales Operations Manager Permissions	
Operations Features	
View Features	
Operations Products, Suites and Maintenance	
View Products, Suites and Maintenance	
Operations License Management – Producer Portal	
View Licenses	Stop Gap Renewal
Return Licenses	Generate Emergency Licenses
Rehost Licenses	Generate Licenses
Repair Licenses	Email Licenses
Correct Publisher Error	
Operations Policies	
Override Policies	
Customer Growth	
Manage and View Customer Growth	
Updates	
Manage and view Updates	

System Administrator

System Administrator Permissions are:

Table 7-48 -

System Administrator Permissions	
Alert Management	
View and Subscribe Alerts	View and Manage Alert Configurations
System Administration	
View and Manage Configurations	View and Manage Email Templates
Merge Entitlements from Self-Registered Account to Customer Account	Create Custom Attribute
View and Manage HTML Content	

Table 7-48 -

System Administrator Permissions	
Operations Feature Bundles	
Delete Feature Bundles	Change Feature Bundle State
Create Feature Bundles	Update Feature Bundles
View Feature Bundles	
Operations License Models	
Update License Models	Create License Models
Delete License Models	View License Models
Change License Model State	
Operations Entitlements – Producer Portal	
View Entitlements	Upgrade Entitlements
Change Entitlement State	Renew Entitlements
Update Entitlements	Edit Sent Emails
Delete Entitlements	Edit Unsent Emails
Create Entitlements	Create Email Notifications
Upsell Entitlements	Queue Email
Account Permissions – End-User Portal	
View Entitlements	Generate License
Return	View Licenses
Repair	Transfer Line Items
Rehost	View Devices
View Expiring Entitlements	
Trusted Storage Permissions	
Short Code Activation	Manual Return and Repair
Manual Activation	Short Code Return and Repair

Table 7-48 -

System Administrator Permissions	
Access to Trusted Storage Licensing Functionality in Producer Portal	
View Transaction Keys	Manual Activations
Create Transaction Keys	Manual Returns
Delete Transaction Keys	Manual Repairs
View Activation Specification Records (ASRs)	Short Code Activations
Create Local Trial ASRs	Short Code Repairs
Delete Local Trial ASRs	Short Code Returns
Create Short Code ASRs	Trusted Activation Requests
Delete Short Code ASRs	
License Technologies	
License Technologies	
Child Account Permissions	
View Child Line Items	Generate License for Child Line Items
Return Child Fulfillments	Repair Child Fulfillments
Rehost Child Fulfillments	View Child Devices
Upgrade Child Fulfillments	View Child Accounts
Renew Child Fulfillments	Manage Child Accounts
Transfer Child Fulfillments	View Child Users
View Child Licenses	Manage Child Users
Usage	
View Usage	Edit Usage
User Management	
View Users	View Logged-In Users
View and Manage Users	View As End User
View Roles	View and Manage Customer Users
View and Manage Roles	View and Manage Partner Users
Account Management	
View Accounts	View and Manage Accounts

Table 7-48 -

System Administrator Permissions	
Operations Features	
Delete Features	Change Feature State
Create Features	Update Features
View Features	Set Feature Override
Operations Products, Suites and Maintenance	
View Products, Suites and Maintenance	Delete File Images
Update Products, Suites and Maintenance	Download File Images
Change Products, Suites and Maintenance State	Deliver to Account
Delete Products, Suites and Maintenance	View & Manage Download Packages
Create Products, Suites and Maintenance	Assign Product Lines
Operations Part Numbers – Producer Portal	
Create Part Numbers	
Operations License Management – Producer Portal	
View Licenses	Stop Gap Renewal
Return Licenses	Generate Emergency Licenses
Rehost Licenses	Generate Licenses
Repair Licenses	Email Licenses
Correct Publisher Error	
Operations Policies	
Override Policies	
Operations Web Services	
Execute Web Services	
Operations Export Import	
Export and Import	
Reporting	
Create and Edit Reports	View Reports
FlexNet Embedded	
Manage Devices	Manage Publisher Identities

Table 7-48 •

System Administrator Permissions	
Customer Growth	
Manage and View Customer Growth	
Updates	
Manage and view Updates	

Super Administrator



Note • This role is reserved for Revenera administrators.

Super Administrator Permissions are:

Table 7-49 •

Super Administrator Permissions	
All	

See Also

[FlexNet Operations Permissions](#)

[End-User Customer Roles](#)

End-User Customer Roles

These FlexNet Operations end-user customer roles are available: [Portal Administrative User](#) and [Portal User](#).

Portal Administrative User

Portal Administrative User is an end-user customer role. Permissions are:

Table 7-50 •

Portal Administrative User Permissions	
Operations Feature Bundles	
View Feature Bundles	
Operations License Models	
View License Models	
Operations Entitlements – Producer Portal	
Change Entitlement State	Update Entitlements

Table 7-50 -

Portal Administrative User Permissions	
Account Permissions – End-User Portal	
View Entitlements	Split Line Items or Bulk Entitlements
Return	View Accounts
Repair	Manage Accounts
Rehost	View Users
Generate License	Manage Users
View License	Transfer Hosts / Move Devices
Transfer Line Items	Get Downloads
View Devices	View Expiring Entitlements
Trusted Storage Permissions	
Short Code Activation	Manual Return and Repair
Manual Activation	Short Code Return and Repair
Access to Trusted Storage Licensing Functionality in Producer Portal	
View Transaction Keys	View ASRs
Child Account Permissions	
View Child Line Items	Generate License for Child Line Items
Return Child Fulfillments	Repair Child Fulfillments
Rehost Child Fulfillments	View Child Devices
Upgrade Child Fulfillments	View Child Accounts
Renew Child Fulfillments	Manage Child Accounts
Transfer Child Fulfillments	View Child Users
View Child Licenses	Manage Child Users
Usage	
View Usage	Edit Usage
User Management	
View Users	View and Manage Customer Users
View and Manage Users	View and Manage Partner Users
View Roles	

Table 7-50 •

Portal Administrative User Permissions	
Account Management	
View Accounts	View and Manage Accounts
Operations Features	
View Features	
Operations Products, Suites and Maintenance	
View Products, Suites and Maintenance	Assign Product Lines
Operations License Management – Producer Portal	
View Licenses	Generate Licenses
Return Licenses	Email Licenses
Repair Licenses	
Customer Growth	
Manage and View Customer Growth	
Updates	
Manage and view Updates	

Portal User

Portal User is an end-user customer role. Permissions are:

Table 7-51 •

Portal User Permissions	
Operations Feature Bundles	
View Feature Bundles	
Operations License Models	
View License Models	
Operations Entitlements – Producer Portal	
Change Entitlement State	Update Entitlements

Table 7-51 •

Portal User Permissions	
Account Permissions – End-User Portal	
View Entitlements	View Licenses
Return	View Devices
Repair	View Accounts
Rehost	Get Downloads
Generate License	
Trusted Storage Permissions	
Short Code Activation	Manual Return and Repair
Manual Activation	Short Code Return and Repair
Access to Trusted Storage Licensing Functionality in Producer Portal	
View Transaction Keys	View ASRs
Usage	
View Usage	Edit Usage
Account Management	
View Accounts	
Operations Features	
View Features	
Operations Products, Suites and Maintenance	
View Products, Suites and Maintenance	
Operations License Management – Producer Portal	
View Licenses	Generate Licenses
Return Licenses	Email Licenses
Repair Licenses	
Customer Growth	
Manage and View Customer Growth	
Updates	
Manage and view Updates	

See Also

[FlexNet Operations Permissions](#)
[Producer User Roles](#)

Managing Accounts

FlexNet Operations provides a set of flexible tools for defining and managing accounts, sub-accounts, and distribution tiers. These tools allow you to define account relationships that mirror your customer and distribution partner relationships.



Note - *Not all users have access to the account pages.*

This section explains account concepts and includes instructions for account management tasks.

Table 7-52 -

Topic	Description
About Accounts	Discusses concepts related to accounts: default accounts, account types, and account tiers.
Browsing Accounts or Sub-Accounts	Describes how to navigate to the Manage Accounts page and browse different account types. Not all users have access to the account pages.
Creating a New Account	Explains how to create a new account, sub-account, or partner account and link users and other accounts to the new account.
Editing an Account or Sub-Account	Explains how to alter an existing account or sub-account.
Deleting an Account	Describes the process of deleting an account.

About Accounts

An account is an entity in FlexNet Operations. Accounts can represent the structure of a customer enterprise, the internal structure of your software publisher or device manufacturer and, optionally, the relationships between the publisher and its distribution chain. Each entitlement is tied to at least one account

Accounts can have sub-accounts, which can be used to reflect the hierarchical nature of corporate structures. Accounts and sub-accounts are defined in a parent-child relationship. For example, you could define Acme Global as the main account, and set up Acme US and Acme EMEA as sub-accounts.

An account hierarchy can have multiple levels to flexibly accommodate different models. For example, a single account can have multiple sub-accounts, which would share a sibling relationship. Sub-accounts can themselves have sub-accounts. In addition, accounts can have multiple parents.



Note - It is recommended that the total number of associated sub-accounts for any given account does not exceed 1000.

The following topics provide more information about account concepts.

Table 7-53 -

Topic	Description
Default Accounts	Identifies the accounts that FlexNet Operations supports without any additional configuration: MYORG, UNKNOWN_ORG_UNIT, and PORTAL_ORG_UNIT.
Account Types	Describes the different account types possible in FlexNet Operations: Producer, Customer, Partner, and Self-Registered.
Partners and Distribution Tiers	Explains how FlexNet Operations handles partner accounts and distribution tiers.

See Also

[Managing Accounts](#)

Default Accounts

The following accounts are available in FlexNet Operations by default:

Table 7-54 - FlexNet Operations Accounts

Account	Description
My Organization (MYORG)	The producer account. Only the account name (My Organization) can be updated on the Edit Account page. This account cannot be deleted.
Information Not Available UNKNOWN_ORG_UNIT	The account set as Sold To for any web register keys when account information is not provided and as the End Customer or Channel Partner for entitlements and devices that have not been assigned an owner account. UNKNOWN_ORG_UNIT is a temporary holding account used by FlexNet Operations, internally, when no owner account is assigned. When UNKNOWN_ORG_UNIT is the owner of an entitlement or a device, the Producer Portal shows Information Not Available for End Customer or Channel Partner. This account cannot be updated or deleted.

Table 7-54 • FlexNet Operations Accounts

Account	Description
Account ID for Portal Accounts (PORTAL_ORG_UNIT)	<p>The account that maps to end users who choose to self-register through the End-User Portal: Users who log in to the portal with an entitlement ID or activation ID can subsequently choose to self-register, set up a user account, or be associated with an existing Self-Registered account.</p> <p>This account cannot be updated or deleted.</p>

See Also

[Account Types](#)
[Partners and Distribution Tiers](#)

Account Types

FlexNet Operations categorizes accounts into four account types. On the **Manage Accounts** page, each of these account types has its own tab: Producer, Customer, Partner, and Self Registered.

Table 7-55 • Account types

Type	Description
Producer	The account for the software publisher or intelligent device manufacturer. Producers can also create sub-accounts to their producer account.
Customer	The category of accounts that are the end users of your software or device. This category includes PORTAL_ORG_UNIT—the default account that maps to users who choose to self-register through the End-User Portal.
Partner	The category of accounts that are distribution partners, like wholesalers, distributors, resellers, and retailers. Producers can map their distribution tiers by defining their distribution partners as partner accounts. These accounts then play a special role in FlexNet Operations.
Self Registered	This category includes users who self-register by logging in to the portal with an entitlement ID or activation ID and set up a their own user account. Optionally, users can select to be associated with an existing Self-Registered account by providing the account ID upon self-registration, instead of creating a new account.

See Also

[Default Accounts](#)
[Partners and Distribution Tiers](#)

Partners and Distribution Tiers



Version - Channel partner and distribution tier functionality is only available to producers who purchase FlexNet Operations with FlexNet Advanced Account Management.

Partner accounts identify accounts in your distribution chain—those accounts that act as distributors of your products and entitlements. Partner accounts exist in a distribution tier between your producer account and your end customers. You can add multiple partner accounts on the **Manage Accounts** page. These partner accounts all occupy the default distribution tier.

By default, FlexNet Operations provides a Distributor tier and an End Customer tier for entitlements and devices. The distribution chain allows entitlements and devices to move from the producer account to a distributor (partner account) to an end user (customer account). However, you can customize the distribution chain and add multiple tiers. Changes to the tiers in the distribution chain require the intervention of Revenera support.

Unique to partner accounts is their relationship to the parent, producer account. Information about the transactions in the partner accounts flows up through the distribution chain so that these transactions are visible on the Producer Portal.

Some FlexNet Operations features are only available to the producer account and partner accounts. For example, only partner accounts can move a device to other distribution tiers on the End-User Portal site.

See Also

[Default Accounts](#)
[Account Types](#)

Browsing Accounts or Sub-Accounts

Accounts and sub-accounts are displayed in the **Accounts** page. Users assigned roles with the **View Accounts** or **View and Manage Accounts** permission can browse accounts in the Producer Portal.

You can also view an account hierarchy, viewing the parent account and any sub-accounts associated with it.

The **Manage Accounts** page shows the following information:

- **Account ID:** Unique identifier of the account
- **Account Name:** User-friendly name of the account
- **Description, City, State, Country:** If included in the account settings, these columns are also populated in the Manage Accounts list.



Task

To browse existing accounts

1. Click **Accounts & Users > All Accountss**. The Producer Portal opens the **Manage Accounts** page.
2. Click the tab for the account type of the accounts you want to see. Choose from
 - **Producers**
 - **Customers** (default)
 - **Partners**

- **Self Registered**



Note ▪ You can also use the search feature to rapidly locate a specific account, especially when there are several pages of accounts to browse.

3. To view details about any existing account, click its **Account ID**.

To view any sub-accounts of an account, click the + icon to expand the tree view in the Manage Accounts list.

See Also

[About Accounts](#)

[Creating a New Account](#)

[Editing an Account or Sub-Account](#)

Creating a New Account

To be associated with an entitlement, a company must be entered as an account in FlexNet Operations. This procedure includes tasks that explain how to create a new account, sub-account, or partner account.

Users assigned a role with the **View and Manage Accounts** permission can view, add, and edit accounts.



Task

To create a new account

1. Click **Accounts & Users > All Accounts**. The Producer Portal opens the **Manage Accounts** page.
2. Choose an **Account Type** tab, and then click **Create an Account**.
3. On the **Create Account** page:
 - a. Enter the **Account ID** (required).
 - b. Enter the **Account Name** of the account (required).



Important ▪ Do not enter a colon (:) character in the **Account Name** field.

- c. Add additional address information as desired.



Note ▪ Producers who use download packages and who want to restrict end-users access to download packages by geographical location should populate the **Country** and **Region** fields.

- d. Set the **Visible to Others** check box (it is selected by default).
 - To prevent partners in different distribution tiers from seeing information about this account, unselect **Visible to Others**.
 - To allow partners to see information about this account, select **Visible to Others**.
4. Optionally, for producer accounts, link product lines to the account. Click **Link Product Lines**. Then, select the product lines to link and click **OK**. All members of the account have access to the linked product lines.



Note - *Link Product Lines* appears on this page only when product lines functionality is properly enabled in the system configuration page (**System > Configure > FlexNet Operations**). See [Managing Product Lines](#) for details.

5. To link users to the account, do one of the following:
 - Click **Create a User** to link a new user to the account. Then follow the steps outlined in [Creating a User](#) to create the new user account.
 - Click **Link Existing Users** to link existing users to the account. Select the users (and roles, if applicable) you wish to link and click **OK**.
6. Click **Next**. On the **Linked Sub-Accounts** page, select any sub-accounts you want to link to this account.
7. Click **Complete**.

After you have created an account, you can create sub-accounts for it.



Task **To create a new sub-account**

If you use the optional Advanced Organization Management module you can create new sub-accounts associated with a parent account.

1. Click **Accounts & Users > All Accounts**. The Producer Portal opens the **Manage Accounts** page.
2. On the **Manage Accounts** page, choose an **Account Type** tab.
3. Select the account with which you want to associate a sub-account, then click **Create a Sub-account**.
4. On the **Create an Account** page:
 - a. Enter the **Account ID** (required) of the sub-account.
 - b. Enter the **Account Name** of the sub-account (required).



Important - *Do not enter a colon (:) character in the **Account Name** field.*

- c. Add additional information as desired.
5. Click **Save**.

You can add additional sub-accounts by repeating [Step 3](#) through [Step 5](#).



Note - *It is recommended that the total number of associated sub-accounts for any given account does not exceed 1000.*



Task **To create a new partner account**

Partners are special accounts in FlexNet Operations. (See [Partners and Distribution Tiers](#) for more information.)

Users assigned a role with the **View and Manage Accounts** permission can view, add, and edit accounts.

1. Click **Accounts & Users > All Accounts**. The Producer Portal opens the **Manage Accounts** page.
2. Click the **Partners** tab, and then click **Create an Account**.
3. On the **Create an Account** page:
 - a. Enter the **Account ID** (required).
 - b. Enter the **Account Name** of the account (required).



Important - Do not enter a colon (:) character in the **Account Name** field.

- c. Add additional address information as desired.
 - d. Set the **Visible to Others** check box (it is selected by default).
 - To prevent partners in different distribution tiers from seeing information about this account, unselect **Visible to Others**.
 - To allow partners to see information about this account, select **Visible to Others**.
4. If you want to link users to the account, do one of the following:
 - Click **Create a User** to link a new user to the account. Then follow the steps outlined in [Creating a User](#) to create the new user account.
 - Click **Link Existing Users** to link existing users to the account. Select the users (and roles, if applicable) you want to link and click **OK**.
5. Click **Next**. On the **Linked Sub-Accounts** page, select any sub-accounts you want to link to this account.
6. Click **Next**. On the **Relate Accounts** page, select any partners you want to relate to this account.
7. Click **Complete**.

See Also

[About Accounts](#)
[Partners and Distribution Tiers](#)
[Editing an Account or Sub-Account](#)
[Browsing Accounts or Sub-Accounts](#)

Editing an Account or Sub-Account

An account or sub-account can be edited to change its name or to add, edit or delete users.



Task

To edit an existing account

1. Click **Accounts & Users > All Accounts**. The Producer Portal opens the **Manage Accounts** page.
2. Click the tab for the Account Type (**Producers**, **Customers**, **Partners**, or **Self Registered**) of the account you want to edit.
3. In the **Manage Accounts** list, click the account you wish to edit. The **Create an Account** page is displayed.

4. Edit the account name and identifier, or create or edit existing users.



Important - Do not enter a colon (:) character in the **Account Name** field.

5. Click **Save**.

See Also

[About Accounts](#)

[Browsing Accounts or Sub-Accounts](#)

[Creating a New Account](#)

Deleting an Account

An account or sub-account can be deleted from FlexNet Operations. You can use the **Delete Account** or the **Delete Subtree** buttons on the **Manage Accounts** page to delete accounts.

- **Delete Account**—removes the selected accounts. If the account has sub-accounts, those sub-accounts no longer have a parent account. The sub-accounts are retained but become top-level accounts. (For example, any sub-accounts of a deleted customer account become regular customer accounts.) Any sub-accounts that were also parents of sub-accounts also retain the hierarchy of sub-accounts beneath them.
- **Delete Subtree**—removes the selected account and all the sub-accounts in its hierarchy.



Task

To delete an account

1. Click **Accounts & Users > All Accounts**. The Producer Portal opens the **Manage Accounts** page.
2. Click the tab for the Account Type (**Producers, Customers, Partners, or Self Registered**) of the accounts you want to delete.
3. In the **Manage Accounts** list, select the accounts or sub-accounts you want to delete.
4. Click **Delete Account**.
5. Click **OK** to confirm deletion.

The Producer Portal deletes the selected accounts and refreshes the **Manage Accounts** page.



Task

To delete an account and all its sub-accounts

1. Click **Accounts & Users > All Accounts**. The Producer Portal opens the **Manage Accounts** page.
2. Click the tab for the Account Type (**Producers, Customers, Partners, or Self Registered**) of the accounts you want to delete.
3. In the **Manage Accounts** list, select the parent account to delete.

Remember that this operation deletes the selected account and all its sub-accounts.

4. Click **Delete Subtree**.
5. Click **OK** to confirm deletion.

The Producer Portal deletes the selected account along with its account hierarchy and refreshes the **Manage Accounts** page.

See Also

[About Accounts](#)

[Managing Accounts](#)

Account Health

Account health indicators provide users with insight into the key indicators that FlexNet Operations provides for accounts. These include:

- Service consumption (counts of total entitled vs. consumed)
- Renewal Health
- Total account health

Table 7-56 -

Topic	Description
Customer Growth Dashboard	Displays aggregated score for all accounts, alerts and selected individual accounts.
Accounts	Detailed health data for an account’s products users, renewals and alerts.
Alert List	List of health alerts.

Customer Growth Dashboard

Health Indicators

Visible from both the FlexNet Operations Home page and the **Customer Growth Dashboard** page (by going to **Accounts & Users > Dashboard**), the Health Indicators provide an at-a-glance view of overall health scores. This information is an aggregation of all accounts and displays the number of healthy, warning and at risk items for account health, renewal health, and consumption in a donut chart.



The overall score for all accounts is represented by the number in the middle of the donut. Hover over the colored sections to find the number of accounts in that category. Click on a donut to be taken to the **Account** page. The arrows indicate trends, whether the scores are going up or down. In addition, you can display all accounts or only those selected to be on a watchlist.

Accounts

The **Customer Growth Dashboard** page also displays the overall health score and 30 day trend for all accounts. The list can be filtered to show only those accounts on the watchlist by selecting the **Watchlist** button.

Alerts

The **Customer Growth Dashboard** page also displays a list of alerts, the accounts, and type of alerts. Alerts are only displayed if the watched accounts are selected by clicking the **Watchlist** button. An alert is generated when either a renewal or consumption score crosses a threshold: Healthy, Warning, or At Risk—in either direction.

The alert shows:

- How long ago the alert was triggered
- The score when the alert was triggered
- The type of change, i.e. from Warning to At Risk

Clicking on an alert notice takes you to the Alerts tab for that account and filters the results based the type of alert selected (i.e. Renewal Health or Consumption). See [Configuring System Settings](#) for more information on setting Renewal and Consumption Health thresholds.

Alert List

Use the topics in this section to learn more about viewing Account Alerts:

Table 7-57 •

Topic	Description
Listing Account Alerts	Shows how to list alerts for all accounts.
Filtering Accounts Alerts	Explains how to filter the alert list by account type, alert type, or the direction the alert score changed.

Listing Account Alerts



Task *To see a list of alerts for all accounts*

- Click **Accounts & Users > Alerts**. The **Accounts Health** page opens.

On the **Accounts Alerts** page, you can filter the account list by account type and alert type. See [To filter the Accounts Alerts list](#) for more information. The list contains the following information:


Column	Description
Alert	The type of alert that was triggered.
Account name	The name of account the alert was triggered for. Click on the name to be taken to the account's Alerts tab. See Account Alerts for more information.
Account ID	The unique identifier of the account.
Score	The score at the time of the alert along with an arrow indicating whether the alert score increased or decreased.
Date	The date the alert was triggered.
Alert age	The age of the alert in whole days (i.e. 24 hour periods).

Filtering Accounts Alerts

By default, the alerts list defaults to display all account types (watched and unwatched) by alert date and all alert types and directions of alert changes. To quickly reduce the size of the accounts list displayed on the accounts alerts page, filter it by account type, alert type and/or the direction the alert score changed.



Task **To filter the Accounts Alerts list**

1. On the **Accounts Alerts** page, hover the cursor over the  filter icon to display the filter selection list. By default, the **Accounts Alerts** page is set to display the Renewal Health and Consumption scores for all accounts (whether they are on the watchlist or not) as well as the direction the score changed for the alert.
2. To change the default filter setting, do one of the following:
 - Select the Watched box to only view accounts on the Watchlist.
 - Unselect one of the Alert types, **Renewal Health** or **Consumption**. If both the Alert type boxes are unselected, a warning appears to remind you that at least one alert type must be selected.
 - Select either the **Increased** or **Decreased** direction of the alert score. Both directions unselected is the same as both directions selected.
3. Click **Apply** to filter the accounts according to your selections.

The number in the red bubble indicates how many filters are active.

You can also search a filtered account list. Use the drop-down list to narrow your search to **Account name** or **Account ID**.

Accounts

Use the topics in this section to learn more about viewing and managing account health metrics.

Table 7-58 ▪

Topic	Description
Listing Accounts	Shows how to list existing accounts.
Filtering the Account List	Explains how to filter the account list by account type and health status.
Account Health Overview	Shows the current overall health, renewal health, and consumption scores.
Account Product Health	Shows the health score for products consumed, as well as the number of items consumed and the total quantity of consumable items.
Account Renewal Health	Shows the list of account renewals so producers can take action on accounts that are near expiration.
Account Alerts	Shows the account alerts so producers can be aware of accounts that have passed a threshold, either up or down.

Listing Accounts

Use the following instructions to list health metrics for existing accounts on the Producer Portal.





Task

To list accounts

- Click **Accounts & Users > Accounts**. The **Accounts Health** page opens.

On the **Accounts Health** page, you can filter the account list by account type, scores, and health status. See [Filtering the Account List](#) for more information. The list contains the following information:

Table 7-59 -

Column	Description
Account Name	The account name.
Account ID	Unique identifier of the account.
Products	The score of all consumed products to the total number of consumable items.
Consumption	<p>Total of all consumed products for an account vs the actual quantity. Consumed products include:</p> <ul style="list-style-type: none"> ● Licensing technologies ● Fulfillments generated ● Licenses activated ● Features acquired <p>See Account Product Health for more information about how consumption is counted.</p>
Renewal Health	The Renewal Health score is a weighted calculation of days until expiration and the consumption value. See Account Renewal Health for more details on how the renewal score is calculated.
Account Health	The Account Health score is a combination of Consumption and Renewal Health scores: $(\text{Renewal Score} + \text{Consumption Score}) / 2$.
Watchlist	<p>Select the icon to add or remove an account from the watchlist.</p> <p> - Unwatched</p> <p> - Watched</p>

To view a particular account, click its **Account name**. On the **Account <account name>** page, you can view details of the health metrics and alerts.



Note - You can sort the list by Account name, Account ID, Consumption, Renewal Health, or Account Health.

See Also

[Account Product Health](#)

[Account Renewal Health](#)


Filtering the Account List

By default, the account list defaults to display all account types (watched and unwatched) by Account health score and all health statuses. To quickly reduce the size of the accounts list displayed on the accounts Health page, filter it by type, score, and health status.



Task

To filter the accounts list

1. On the **Accounts Health** page, hover the cursor over the  filter icon to display the filter selection list. By default, the **Accounts Health** page is set to display the Account Health score with all statuses.
2. To change the default filter setting, do one of the following:
 - Select the Watched box to only view accounts on the Watchlist.
 - Unselect the Account Health and select either the Renewal Health or Consumption scores.



Note - At least one of the scores must be selected: Account Health, Renewal Health, or Consumption. Only one score can be selected at a time; the other scores are inactive. To change scores, unselect the active one to make them all active before selecting the score to be filtered on.

- Unselect one or more of the statuses. All statuses unselected is the same as all statuses selected.
3. Click **Apply** to filter the accounts according to your selections.

The number in the red bubble indicates how many filters are active.

You can also search a filtered account list. Use the drop-down list to narrow your search to **Account name** or **Account ID**.

Account Health Overview

On the **Account <account name>** page, the **Overview** tab is displayed by default.

The **Overview** tab displays the account, renewal, and consumption scores related to that account.

There is also a health meter line graph showing the trends for that health metric. Hover over a point on the graph to see the date and its related health score for that metric.

To add or remove the account from the watchlist, click the **Watch** or **Unwatch** button in the upper right hand corner.

Account Product Health

On the **Account <account name>** page, click on the **Products** tab to see the list of products.

The list contains the following information:

Table 7-60 ▪


Column	Description
Score	The calculated health score. This number is based on the number of consumed versus total available consumable features and/or licenses for that product. The number is then assigned a status of healthy, warning, or at risk, depending on the threshold set in the system configuration. See the Customer Growth settings under Configuring System Settings .
Consumed quantity	The total number of licenses and/or features that have been consumed. If feature consumption exists, this number is displayed as a link. Consumed products include <ul style="list-style-type: none"> • FlexNet Publisher—fulfillments generated from entitlements • FlexNet Embedded (Standalone device)—licenses mapped from entitlements • FlexNet Embedded (Local or Cloud license server)—features checked out by served devices • Third part license technology—fulfillments generated from entitlements
Total quantity	The sum of all possible features or licenses plus all possible quantities not mapped to a server.
Product name	The name of the product.
Description	A description of the product.



Note ▪ The list can be sorted by Score, Consumed quantity, Total quantity, and Product name.



Task To filter the products list

1. On the **Products** tab, hover the cursor over the  filter icon to display the filter selection list. By default, the **Products** tab is set to display the product health score with all statuses, **At risk**, **Warning**, or **Healthy**.
2. To change the default filter setting, unselect one or more of the conditions. If all the condition boxes are unselected, a warning appears to remind you that at least one of the score filters must be selected.
3. Click **Apply** to filter the products according to your selections.

The number in the red bubble indicates how many filters are active.

You can also search a filtered product list. Use the drop-down list to target your search to a product's **Product Name** or **Description**.



Task **To view Feature Consumption**

- Click on the **Consumed quantity** value to open the **Feature Consumption** window.


The **Feature Consumption** window displays the consumption of features attached to any given product, if there are any. Any feature with an embedded license model, and mapped to a license server, is included in the consumption numbers.



Note ▪ The list can be sorted by *Score, Consumed quantity, Total quantity, or Feature name.*



Task **To filter the feature consumption list**

1. On the **Feature Consumption** window, hover the cursor over the  filter icon to display the filter selection list. By default, the **Feature Consumption** window is set to display the feature health score with all conditions, **At risk**, **Warning**, or **Healthy**.
2. To change the default filter setting, unselect one or more of the conditions. If all the status boxes are unselected, a warning appears to remind you that at least one of the score filters must be selected.
3. Click **Apply** to filter the features according to your selections.

The number in the red bubble indicates how many filters are active.

You can also search a filtered feature list. Use the drop-down list to target your search to for a feature by **Name** or **Description**.

Account Renewal Health

On the **Account <account name>** page, click on the **Renewals** tab to see the renewal health of each product the account has licenses for.

The list contains the following information:

Table 7-61 ▪

Column	Description
Score	A calculated value based the number of days until the product expires and the consumption value.
Days remaining	The number of days before the license expires.
Expiration	The date the license expires.
Product name	The name of the product.

Table 7-61 •

Column	Description
Type	The type of product. Options include: <ul style="list-style-type: none"> • Subscription • Maintenance
Activation ID	The activation ID of the product. Click on the Activation ID to see the Entitlement Details.



Note • The list can be sorted by Score, Days remaining, Expiration, or Product name

Calculating the Renewal Score

The formula for calculating the Renewal Score is based on two factors:

1. How far the products are from their expiration dates (for subscription or maintenance lines).
2. The Consumption value. The Consumption score is derived from the ratio of consumed quantities to purchased quantities for the account, on a 100-point scale. For example, if an account purchased a quantity of 42 but consumed a quantity of 21, the Consumption value is 0.5 and the Consumption score is 50.

For the first factor, there are three weighted renewal periods, based on how close the entitlements are to their expiration dates: Renewal Look Ahead, Expiring Window, and Renewal Critical. These renewal periods are labels for how close an entitlement is to its expiration date.

Table 7-62 • Weights and Thresholds for Each Renewal Period

Renewal Period	Weight	Default Threshold
Renewal Look Ahead	.25	200 days
Expiring Window	.50	90 days
Renewal Critical	.90	30 days

The renewal period *weights* are fixed and not configurable; however, producers can configure the renewal period *threshold* values in their system configuration settings. In the Producer Portal, click **System > Configure > FlexNet Operations > Renewals**.

The complete formula for the renewal score is


$$(1 - ((\text{Renewal Look Ahead} * .25) + (\text{Expiring Window} * .50) + (\text{Renewal Critical} * .90) + \text{Consumption Value})) / 2$$

where the value for each renewal period is either 0 or 1.

Using the renewal period values, only one renewal period (Renewal Look Ahead, Expiring Window, or Renewal Critical) is factored into the score at a time. After a product enters a specific renewal period, that renewal period has a value of 1 and all other renewal periods have a value of 0.



Task **To filter the renewals list**

1. On the **Renewals** tab, hover the cursor over the  filter icon to display the filter selection list. By default, the **Accounts** page is set to display the product health score with all conditions, **At risk**, **Warning**, or **Healthy**, with types, **Subscription** and **Maintenance**, and with a status of **Expiring**.
2. To change the default filter setting, unselect one or more of the statuses, types and/or conditions. If all the status boxes are unselected, a warning appears to remind you that at least one status must be selected. All types unselected is the same as all types selected.
3. Click **Apply** to filter the renewals according to your selections.

The number in the red bubble indicates how many filters are active.

You can also search a filtered renewal list. Use the drop-down list to target your search to a **Product Name** or **Activation ID**.



Task **To view Entitlement Details**

- Click on the **Activation ID** value to open the **Entitlement Details** window.

The **Entitlement Details** window displays the information for a particular entitlement including ID information (Entitlement ID, state, sold-to, description and activation ID), the name and description of the products the entitlement is associated with, and the activation information.

Account Alerts

On the **Account <account name>** page, click on the **Alerts** tab to see the alerts for an account.

The list contains the following information:

Table 7-63 -

Column	Description
Alert	The type of alert generated. One of the following: <ul style="list-style-type: none">● Renewal Health● Consumption
Score	The score at the time of the alert. The score also includes an arrow to show if the alert level was raised or lowered.
Date	The date the alert was generated.
Alert age	The age of the alert in days. Maximum days: 30. By default, the list is sorted by the alert age.




Note - You can sort the list by either Alert or Alert age.



Task

To filter the alerts list

1. On the **Alerts** tab, hover the cursor over the  filter icon to display the filter selection list. By default, the **Alerts** page is set to display both the Renewal Health and Consumption score. If the page was loaded by clicking on an account from the Customer Growth Dashboard, it automatically filters the list based on the selected alert.
2. To change the default filter setting, unselect one of the Alert types and/or select either the Raised or Lowered direction. If all Alert type boxes are unselected, a warning appears to remind you that at least one alert type must be selected. Both directions unselected is the same as both directions selected.
3. Click **Apply** to filter the alert types according to your selections.

The number in the red bubble indicates how many filters are active.



Analyzing Usage and Entitlement Data (Early Access)



Note - The functionality described in this manual is applicable only to customers who use Revenera's Amazon Web Services (AWS) instances of FlexNet Operations.


FlexNet Operations' embedded Analytics functionality leverages data from the data warehouse to deliver a 360-degree view of your customers. The Analytics functionality, available on the **Analytics** menu, is split into two areas:

Table 1 - FlexNet Operations Analytics

Feature	Description
Data Visualizations 	<p>Help you translate usage and entitlement data into actionable insights. Using subscriptions, share insights from dashboards and reports within your organization and even end-users.</p> <p>These features are found under Analytics > Reports.</p>
Conditional Notifications 	<p>Provide you with an automated framework to act on the data.</p> <p>These features are found under Analytics > Conditional Notifications.</p>

Usage and entitlement data offer insights crucial for prediction, customer success and retention, and identifying upsell opportunities. You can view data visualizations to gain insight into customer trends and then perform actions relating to those insights using conditional notifications.

The following diagram illustrates how visualizations and conditional notifications complement each other:



Sections in This Manual

FlexNet Operations provides reporting and notification features through its **Analytics** menu.

Table 2 - Sections in this guide

Topic	Description
Understanding Data Freshness	Describes the Data As Of and Data Last Updated dates displayed on each dashboard.
Setting Up Conditional Notifications Based on Data Changes	View and configure conditional notifications that are triggered either whenever a specific event occurs or on a set schedule.
Using Analytics Reports to Explore Customer Data	See an overview of your most important FlexNet Operations entities related to your customer accounts and their entitlement usage. Build reports to identify trends.
Filtering Data	Explains how to use filters to focus on the portion of the data relevant to your analysis, affecting the data displayed in a report, dashboard or metric.
Formulas	Describes how to create calculated columns that can be used like any other column of data.
Bucketing Data	Explains how to group multiple data points into a single item to simplify analysis.
Tokens	Learn how to use tokens, which act as containers for data.

Understanding Data Freshness

This section describes how you can determine the freshness of the data that is available for analysis.

The Analytics Dashboard and each report shows two dates on the right side: **Data As Of** and **Data Last Updated**.

Analytics Dashboard

The Analytics Dashboard provides a visual representation of the most important FlexNet Operations entities.

Data As Of: 2023-08-19 03:51:06 (UTC) ⓘ
Data Last Updated: 2023-09-04 02:11:03 (UTC) ⓘ

Entitlement Line Items	Served Devices	Customers	Customer Users	Partners	Partner Users
43.8k	10	2.16k	959	352	428

- **Data As Of**—This is the earliest date from which data is available for analysis.

This date is only relevant for customers who previously used an instance of FlexNet Operations that was hosted in Revenera’s own data center, and who only recently moved to an AWS instance (which uses the Snowflake data warehouse). For these customers, only recent data is currently available for data analysis. Data will be backfilled over time.

- **Data Last Updated**—This is the date and time when any data used in a chart on a dashboard was last updated in the data warehouse.



Note ▪ Data is pulled from the Snowflake data warehouse, which is updated on a regular cycle (currently every four hours). For more information on the data flow and refresh cycles, see the next section, [Setting Up Conditional Notifications Based on Data Changes](#).

Both dates are in Coordinated Universal Time (UTC).

Setting Up Conditional Notifications Based on Data Changes

On the **Conditional Notifications** page (available from the **Analytics** menu), you can configure automated alerts based on conditions you define.

Conditional notifications help to drive business tracking and decisions by ensuring the relevant data is sent to you in a timely way. For example, decisions around customer renewals, or discussions with customer about their utilization of purchased products, can be informed by data that is sent to you in an automated way.

You can set up conditional notifications triggered either by specific events or on a schedule. Data which you choose to include is then published either to a webhook or sent to a specified email address. The section [Example Walkthroughs for Conditional Notifications](#) provides examples for different scenarios.

Conditional notifications track data changes in the FlexNet Operations Reporting Database, which is refreshed on a regular cycle (currently four hours). The conditions track this incoming data and send your notifications according to the rules you set up.

DATA FLOW FOR CONDITIONAL NOTIFICATIONS




Figure 1: Data flow for conditional notifications

The following topics are discussed in this section:

- [Types of Conditional Notifications](#)
- [Components for Conditional Notifications](#)
- [Viewing Conditional Notifications](#)
- [Creating Conditional Notifications](#)
- [Editing a Conditional Notification](#)
- [Deleting Conditional Notifications](#)
- [Conditional Notification Activity Log](#)
- [Example Walkthroughs for Conditional Notifications](#)

Types of Conditional Notifications

FlexNet Operations supports two types of conditional notifications:

- **Based on Aggregate (Metric) Values**—Users define thresholds for an aggregate value of a specific field. A notification is triggered when the defined threshold has been reached.
- **Based on Field (Column) Values**—Users specify a field and value. FlexNet Operations compares the defined field value with the field value in the dataset and triggers a notification in case of a match.

Components for Conditional Notifications

Conditional notifications are built from the following types of components:

- **Metrics**—Aggregated data that can form the basis of a conditional notification. Using a metric for a conditional notification is optional.
- **Triggers**—Events that initiate execution of a conditional notification.
- **Conditions**—Filters that can allow or prevent actions from happening.
- **Send Actions**—Actions that send results to a user or process.
- **Data Action: Submit Data**—Actions that access or update data.

For example, you can create a simple conditional notification so that whenever an entitlement is updated in FlexNet Operations (*trigger*), you are sent a conditional notification email (*action*), but only if the entitlement is for a specific customer (*condition*).

Metrics

You use metrics to specify the parameters for the dataset on which a conditional notification is based. Use filters to narrow down the dataset to the data that you want to target.

For example, you could create a metric that defines the benchmark *number of accounts created after a specified date in a particular country*. This metric can be the basis of a conditional notification that is triggered when the benchmark has been reached.

Topics in this section:

- [Metrics Overview](#)
- [Building a Metric](#)

Metrics Overview

The various areas and panels of the Metrics tab are introduced in the following image:

Edit Conditional Notification




Figure 2: Overview of the **Metrics** tab on the **Edit Conditional Notification** page

1. **Metrics Panel**—Lists predefined metrics that are available to you.
2. **Data Panel**—Data fields from the selected dataset are listed in this panel and can be dragged and dropped in various areas of the screen to be analyzed. The data fields are divided into **Categories** and **Values** and their data type is presented with an icon next to each.
3. **Values Shelf**—You can drag and drop data columns that you want to analyze to the fields in this shelf. The number of fields in the shelf and their expected data types vary from chart to chart. Each column pill offers additional options for the field in it, like changing its data format, aggregation, sorting, etc.
4. **Canvas**—The area where your chart will appear and where you can add/change the name and description of the chart.
5. **Filter Panel**—Filtering enables you to focus on the portion of the data relevant to your analysis. See also [Filtering Data](#).
6. **Toolbar**—A quick way to add buckets, formulas, and filters, and save your work, among other quick actions. For more information, see the topics [Formulas](#), [Bucketing Data](#), and [Filtering Data](#).

The Data Panel

The Data Panel is located on the left-hand side of the Metrics tab and is where the data for the chart is picked from.




Figure 3: Overview of the Data Panel on the **Metrics** tab

1. **Dataset name**—The name of the dataset you are currently using.
2. **Categories**—Categories are text and date type columns that can be used as dimensions that allow you to slice and group your data. They contain categorical information like *country*, *customer name*, *created on*, etc.
3. **Values**—Values are numeric columns that can be used as measures most of the time. Value columns can be used as they are, or be aggregated. Examples of aggregated values are *remaining copies*.

Column Pill

Column Pills represent the dataset fields that appear either under **Category** or **Value** in the Data Panel. These column pills can be dragged from the Data Panel and dropped either onto corresponding shelves or directly onto the canvas to its corresponding axis. The values appear in blue (**Category**) or green (**Value**), regardless of the shelf or axis they're dropped onto.

Text values are always considered as **Category** values, although in some cases they may not be good candidates for grouping. The following diagram shows what the values shelf looks like after a column pill has been added to it.



1. The drag handle—a six-dot icon you can use to “grab and drag” the pill anywhere on the Metrics tab.
2. The name of the dataset field alongside a symbol that represents its data type.

3. The aggregation that has been applied to the value.
4. The three-dot menu where you can manage aggregation features. The content of the three-dot menu depends on the type of the value (**Category** or **Value**).
 - Aggregation features for text values and date values: Count, Distinct Count
 - Aggregation features for numeric values: Sum, Average, Median, Count, Distinct Count, Minimum, Maximum

Building a Metric

If you selected **Aggregate (Metric) value** when you set up your conditional notification, you are prompted to define the metric on the **Metric** tab. This is displayed after you click **Continue** in the **Create Conditional Notification** dialog (see [Creating Conditional Notifications](#) for more information).

Reverera recommends that you familiarize yourself with the options on the **Metrics** tab by reading the [Metrics Overview](#) section before you attempt to build a metric.



Task

To create a metric

1. Perform the steps in [Creating a Conditional Notification](#).
2. On the **Metric** tab, define the metric on which the conditional notification is based.
3. Drag a desired **Category** or **Value** from the panel on the left side to the **Values** shelf at the top.
As soon as you add the field, the value will be shown.
4. If desired, configure your metric using a filter or a tool from the toolbar. Refer to the sections [Formulas](#), [Bucketing Data](#), and [Filtering Data](#) for more information.
5. Enter a name and a description for your metric.
6. Click **Save Chart** to save your metric.

The **Edit Conditional Notification** page shows the **Notification** tab, where you can configure your conditional notification. For more information, see the task described in [Configuring a Conditional Notification](#), in section [Creating Conditional Notifications](#).



Tip - Refer to the [Example Walkthroughs for Conditional Notifications](#) to see an example of how to create a metric.

Triggers

Triggers are the components that begin, i.e. initiate, a conditional notification. This section describes the trigger types and how to use them in your conditional notifications. If you're not yet familiar with the mechanics of a conditional notification, consult the [Types of Conditional Notifications](#) section.

The following topics are discussed in this section:

- [Scheduling](#)

- New Data
- Update Data

Scheduling



Note - Only use the **Scheduling** trigger for notifications that are based on aggregate (metric) values.

Use the scheduling trigger for when you want the conditional notification to start on a date and time of your choosing. Select the frequency and the time you would like your trigger to run. You can also choose a start date and an ending date.

Trigger - Scheduling

Start On At End

Repeat Every

Figure 4: Overview of the scheduling trigger for a conditional notification

When you finish setting your scheduling presets, continue building your conditional notification by adding conditions and actions.

New Data



Note - Only use the **New Data** trigger for notifications that are based on field values.

Use the **New Data** trigger when you want the conditional notification to run as soon as new data is received—for example, when a new record has been added to a data source.

To set up a new data trigger, just drag and drop the **New Data** trigger, then select the name of the dataset you would like to monitor. The conditional notification will start when a change is detected.

Update Data



Note - Only use the **Update Data** trigger for notifications that are based on field values.

Use the **Update Data** trigger when you want the notification to start whenever information in an existing dataset has been updated. Select the dataset name you would like this notification to monitor, then continue with your conditions and actions.



Important - Be aware that the **Update Data** trigger might result in notifications being sent every four hours (as per the refresh cycle of the FlexNet Operations Reporting Database).

Conditions

Conditions are components that can be added to triggers to test if certain filter criteria are met. Depending on the test results, some of the following actions may or may not be executed. This allows for refining trigger conditions, as well as for branching within conditional notifications. This section reviews what conditions are and how you can deploy them in your conditional notifications to control actions.

The following topics are discussed in this section:

- [Adding Conditions](#)
- [Types of Conditions](#)
- [Using Conditions](#)

Adding Conditions

Conditions can be added to any trigger to control when the trigger causes the conditional notification to run. For example, you can add a condition to a **New Data** trigger to define scenarios that must be met before the trigger will run. Another possibility is to add a condition to a scheduling trigger, e.g. to send a conditional notification if a metric is outside preset bounds.



Task

To add a condition


1. Perform the steps in [Creating a Conditional Notification](#).
2. Drag the **If** condition onto the canvas, and drop it below the trigger or action option it will apply to.
3. Define the specific conditions that need to be met. Any actions you drag below the condition will be run when the condition is met. Actions dragged below the **Else** box will be run when the condition is not met.
4. (Optional) To combine an existing IF condition with another IF condition, drag the **And - Or** condition onto the canvas. A new IF condition is automatically added. Select whether the conditions should be combined using AND or OR using the dropdown menu.
5. Continue with the steps in [Configuring a Conditional Notification](#).

Types of Conditions

Conditional notifications support different types of conditions depending on the trigger they are attached to:

For all triggers, the following two conditions can be used:

- **If Field** - allows you to specify a particular field that will trigger the action.
- **If Metric** - allows you to specify a metric threshold that will trigger the action.



Using Conditions

Once you have selected your conditions, you may drag as many Action blocks to your conditional notification as needed. Conditions and actions will be nested so you can easily follow along visually to see what is taking place and when.




Figure 5: Overview of conditions with Action blocks for a conditional notification

Send Actions

This section describes the conditional notification actions available under **Send Actions**:

- [Send to Webhook](#)
- [Send Email](#)

Send to Webhook

Use the **Send to Webhook** action to send data to an external Webhook URL. Just enter the URL you'd like to call and click **Add Parameters** to add data or tokens to your submission.




Figure 6: Overview of the **Send to Webhook** action for a conditional notification

For example, you could create the following action:

Field	Sample Value	Description
URL	https://webhook.site/123456789	Type the URL of the receiving application that will handle the data.
Parameters	count	Enter a string that describes the value or token output.
As	{{data.metric.average_ordered_seat_count.value}}	<p>Start by typing two curly brackets, {{, to bring up a list of tokens that are available for that specific context.</p> <p>The tokens available depend on the selected dataset and metric (for metric-based notifications) or selected dataset and field (for field-based notifications).</p> <p>For information about tokens, see Tokens.</p>

For the sample values above, the webhook site will receive a payload similar to the following:

```
{  
  "count": "260393.66344234662"  
}
```

Send Email

Use the **Send Email** action to send notifications via email. To use this action, enter a comma-delimited list of email addresses along with a subject and a message. The message body can be formatted with any of the standard options provided, including bold, italic, and underline. There are also justification and link options.




Figure 7: Overview of the **Send to Email** action for a conditional notification

You'll see Flexera's signature at the bottom of the action card. The signature will appear by default at the bottom of every email sent by the action. If you do not want to include this signature as part of your emails' body, clear the option **Include Signature** located on the right side of the toolbar.

Data Action: Submit Data

Data actions work with connected data sources such as Elasticsearch, SQL and Oracle databases.

Use the **Submit Data** action to send data to a third party system via URL, similar to a "form POST" in HTML. Provide the URL you'd like to submit your data to and the format you'd like to use, followed by the parameters or field/value pairs you'd like to send.

Choose the desired authentication type—**Basic Authentication** or **API Key**—for authentication against any external systems to which you want to send data.



Tip • The **Submit Data** action also supports tokens to use dynamic values.

The screenshot shows a configuration window titled "Action Submit Data". It includes the following sections:

- Method:** A dropdown menu set to "Get" and a text input field labeled "URL" with the placeholder "Type your URL".
- Authentication Type:** A dropdown menu set to "None".
- Headers:** A table with two columns: "Type Name" and "Type value or token". There are plus and minus icons to the right.
- Parameters:** A table with two columns: "Type Name" and "Type value or token". There are plus and minus icons to the right.
- Body Type:** A dropdown menu set to "JSON".
- Body:** A text area containing a single row with the value "{}". A status bar at the bottom left of the text area shows "Ln: 1 Col: 1".

Figure 8: Overview of the **Submit Data** action for a conditional notification

Viewing Conditional Notifications

The **Conditional Notifications** page displays a list of all conditional notifications. You can also search for specific conditional notifications based on specific criteria by specifying sorting criteria for each column in the table.



Task *To view a list of all conditional notifications*

Click **Analytics > Conditional Notifications**.

Creating Conditional Notifications

You start creating a conditional notification on the **Conditional Notifications** page, which also displays a list of all conditional notifications. Your conditional notification can be based on a metric or it can target a specific field of a dataset.

Creating a conditional notification usually involves the following steps:



Defining a metric is optional.

Creating a Conditional Notification

The initial step involves naming your conditional notification and specifying basic parameters, such as metric (if using one), dataset and trigger type.



Task To create a conditional notification

1. Click **Analytics > Conditional Notifications**.
The **Conditional Notifications** page opens.
2. Click **New Notification**.
3. In the **Create Conditional Notification** dialog, define the broad parameters for your notification:
 - Enter a **Name** for the notification (maximum number of characters: 100).



Tip - You might want to indicate in the notification name whether the notification is based on a metric. This enables you in the conditional notifications overview to differentiate between the different notification types.

- Select the **Dataset** on which the notification should be based.
- Select the **Notification type**.
 - Select **Aggregate (Metric) value** if you want the notification to be based on aggregated data.
 - Select **Field (Column) value** if the notification is based on the comparison of a raw value in a dataset field.
- 4. Click **Continue**.
- 5. If you selected **Aggregate (Metric) value** in step 3, continue with the task described in section [Building a Metric](#), under [Metrics](#). If you are not using a metric, continue with the task in section [Configuring a Conditional Notification](#).

Configuring a Conditional Notification

Configuring a notification involves defining the triggers that initiate the notification and actions that send results to a user or process.

See the following sections for information about the components that you use to configure your notification:

- [Triggers](#)
- [Conditions](#)
- [Send Actions](#)
- [Data Action: Submit Data](#)



Task *To configure a conditional notification*

1. Perform the steps in [Creating a Conditional Notification](#).
2. On the **Design** tab, specify the trigger that initiates the notification. Start by dragging one of the triggers from the **Triggers** section on the right side onto the **Trigger - New Data of Dataset <dataset_name>** area.

The type of trigger suitable for a condition depends on the condition type:

- Use the **Scheduling** trigger for notifications based on aggregate (metric) values.
- Use the **New Data** and **Update Data** triggers for notifications based on field values.



Tip - Point to each trigger option to display a tooltip with information about each trigger.

3. After adding the trigger, drag and drop a condition or an action under the new trigger area.
4. Configure the **Triggers** and **Conditions** dragged onto the conditional notification canvas.
5. Continue with the steps in [Activating a Conditional Notification](#).

All changes are saved automatically as you build your conditional notification.

Activating a Conditional Notification

When you have finished building your notification, click the **Activate** button in the upper-right corner to make it operational.




Figure 9: Activating a conditional notification

A message confirming that your conditional notification is active appears.

Once your conditional notification is active, the **Activate** button will be replaced with a **Pause** button, which can be used to suspend the conditional notification at any stage.

Editing a Conditional Notification

You cannot edit an active conditional notification. If you want to edit a notification, you need to pause it first. You can then edit it and re-activate it.



Task *To edit a conditional notification*


1. Click **Analytics > Conditional Notifications**.
2. Click the name of the notification you want to edit.
3. Click **Pause**.
4. Edit the notification.
5. Click **Activate**.

Deleting Conditional Notifications

The **Conditional Notifications** page displays a list of all conditional notifications. You can also search for specific conditional notifications based on specific criteria by specifying sorting criteria for each column in the table.



Task *To delete a conditional notification*

1. Click **Analytics > Conditional Notifications**.
2. In the table, click the Delete icon  for the notification that you want to delete.

Conditional Notification Activity Log

Every conditional notification keeps a log of all its activities, including any changes made by creators and every occasion the conditional notification is triggered. If you have any questions about how your notification is performing, the activity log is the place to see detailed information about its activities, errors and events.



Task *To access the activity log for a conditional notification*

1. Click **Analytics > Conditional Notifications**.
2. In the table, in the **Activity** column, click the **See Activity** link.

The activity log can be searched and filtered to make finding relevant events easier.

Use the **Refresh** button to fetch new activity log events.

Example Walkthroughs for Conditional Notifications

This section shows you how to create conditional notifications for the following fictitious use cases:

- [Use Case: Send Notification When an Account Is Created in a Specific Region \(Field Value\)](#)
- [Use Case: Send Notification when Number of Feature Requests Exceeds Threshold \(Aggregate Values\)](#)

Use Case: Send Notification When an Account Is Created in a Specific Region (Field Value)

In this use case, you create a conditional notification that sends an email to a specified email address whenever an account is created in a specific region (that is, in the account record, the **Region** field is populated with the desired value). The notification uses the Field Value type and the New Data trigger.

The process is broken up into the following steps:

1. [Creating the Notification of Type “Field Value”](#)
2. [Defining the Conditions for the Field to Compare](#)

Creating the Notification of Type “Field Value”

In this first step, you create a notification and specify its broad parameters, such as name, dataset, and notification type.



Task *To create the conditional notification*

1. Click **Analytics > Conditional Notifications**.
The **Conditional Notifications** page opens.
2. Click **New Notification**.
3. In the **Create Conditional Notification** dialog, specify the following:
 - Enter a meaningful name for the notification, for example, **New Account in EMEA**.
 - Select the dataset **Accounts and Users**.
 - Select the notification type **Field (Column) value**.

The following image shows the **Create Conditional Notification** dialog with the sample parameters mentioned in the description above.

Create Conditional Notification

Name
New Account in EMEA

Dataset
Accounts and Users

Notification type
 Aggregate (Metric) value
 Field (Column) value

Cancel Continue

4. Click **Continue**.

The **Edit Conditional Notification** page opens with the **Notification > Design** tab selected.

5. Continue with the steps in [Defining the Conditions for the Field to Compare](#).

Defining the Conditions for the Field to Compare

In this step, you define the trigger, conditions and actions for the conditional notification.



Task *To design your conditional notification*

1. Perform the steps in [Creating the Notification of Type “Field Value”](#).
2. Select the trigger that initiates the notification. In this example, you want the conditional notification to run as soon as a new account with the account region Sweden is added. The trigger **New Data** should be preselected. If it isn't, drag the **New Data** trigger from the **Triggers** section on the right side onto the **Trigger** area in the main screen.



Tip - You already selected the **Accounts and Users** dataset in step [Creating the Notification of Type “Field Value”](#). If you accidentally selected a different dataset, you can correct this by clicking in the **Trigger** field. You can then select the desired dataset from the dropdown list:

Trigger - New Data

Datasets

Accounts and Users

Search

Create New Dataset

Fulfillment from Entitlements (Dataset)

Served Device (Dataset)

Entitlements (Dataset)

Accounts and Users (Dataset)


3. Define the field value in the **If** condition. Whenever a new account record with the defined field value is added to the dataset, an action takes place. Click anywhere in the **If Field** area to expand it, and specify the following parameters:
 - a. **Field:** Select **Account Region**.
 - b. **Is:** Select **Equals**.




Note - Selecting **Contains** would produce the same results.

- c. **Value:** Type EMEA.

The **If** condition will look similar to the following:



4. Define the action that should occur when the **If** condition is met. To do so, click **Action - Send E-mail** to open the panel. Enter suitable information in the **To** and **Subject** fields. For example, for **Subject**, type **New Account in EMEA**.
5. In the **Message** field, enter a meaningful email message.
6. Also in the **Message** field, click the **Tokens** icon (**{ }**) to include dynamic information about the new account in the email. For example, you could select the following tokens:
 - `{{trigger.accounts.and.users.account.id}}`
 - `{{trigger.accounts.and.users.account.name}}`
 - `{{trigger.accounts.and.users.account.description}}`
 - `{{NOW}}`
7. Your notification should now look similar to the following:



8. Click **Activate** to activate the notification.

Use Case: Send Notification when Number of Feature Requests Exceeds Threshold (Aggregate Values)

This section provides instructions for a fictitious use case where you want to be notified when the cumulative count of requests for a specific feature exceeds a certain threshold value over this quarter. This example walkthrough describes the basic process of configuring the conditional notification with its filters and metric.

The process is broken up into the following steps:

1. [Creating the Notification of Type “Aggregate Value”](#)
2. [Defining the Conditions for the Metric to Compare](#)
3. [Scheduling the Notification With Threshold](#)

Creating the Notification of Type “Aggregate Value”

In this first step, you create a notification and specify its broad parameters, such as name, dataset, and notification type.



Task **To create the conditional notification**

1. Click **Analytics > Conditional Notifications**.
The **Conditional Notifications** page opens.
2. Click **New Notification**.
3. In the **Create Conditional Notification** dialog, specify the following:
 - Enter a meaningful name for the notification, for example, **Feature “abc” exceeds 50 requests over the quarter**.
 - Select the dataset **Served Device**.
 - Select the notification type **Aggregate (Metric) value**.

The following image shows the **Create Conditional Notification** dialog with the sample parameters mentioned in the description above.

Create Conditional Notification

Name
Feature “abc” exceeds 50 requests over the quarter

Dataset
Served Device

Notification type
 Aggregate (Metric) value
 Field (Column) value

Cancel Continue

4. Click **Continue**.
The **Edit Conditional Notification** page opens with the **Metric** tab selected.
5. Continue with the steps in [Defining the Conditions for the Metric to Compare](#).

Defining the Conditions for the Metric to Compare

In this step, you create the metric with appropriate filters on the **Metric** tab in the **Edit Conditional Notification** page. The metric defines the threshold value used for comparison with the data from the dataset.




Task **To create the metric**

1. Perform the steps in [Creating the Notification of Type “Aggregate Value”](#).
2. In the **Untitled Chart** field, add a name for your metric, for example, **Cumulative Count of Requests for Feature “abc” Over This Quarter**. You can also add a description.
3. Add filters to focus on a specific feature and time frame.

To do so, open the **Filter** panel if it is not already open. In the **Filter** panel, click **Add Filters**. The **Filter** dialog box opens.

- a. Define the filter Feature Name Equals abc.
- b. Add a second filter Last Modified Date In, Exclusive, This Quarter.

When the filters have been defined, the Filter panel should look similar to this:



4. Create a cumulative aggregate for your metric:
 - a. From the **Data** section on the left, drag and drop the value **Quantity** to the **Values** shelf at the top.
As soon as you add the field, the value will be shown.
 - b. In the **Values** shelf, click the three-dot menu and select the aggregation feature **SUM**.
5. Click **Save Chart**.

The metric should look similar to the following:




Figure 10: Example metric for cumulative count of requests for feature “abc” over a quarter

The screenshot shows the steps for creating the metric:

1. Naming the metric
2. Defining filters for the feature name and time frame
3. Defining the aggregate value
4. Saving the metric

After saving the metric, FlexNet Operations displays the **Notification** tab.

Continue with the steps in [Scheduling the Notification With Threshold](#).

Scheduling the Notification With Threshold

In this last step of the example walkthrough, you define the threshold value, configure the schedule and define the action that should occur when the notification is triggered. You do this in the **Design** area on the **Notification** tab of the **Edit Conditional Notification** page. After you set up the notification, you can monitor its activity on the **Activity** tab on this page.




Task To schedule the notification and define the trigger

1. Perform the steps in [Defining the Conditions for the Metric to Compare](#).
2. The trigger **Scheduling** should be preselected. If it isn't, drag the **Scheduling** trigger from the **Triggers** section on the right side onto the **Trigger** area in the main screen.

- Configure the schedule to start on a particular date and time and set how often it should be executed (for example, every 4 hours). To do so, click **Trigger - Scheduling** to open the panel. Specify parameters similar to the following:

- **Start On:** 07/01/2023
- **At:** 12:00pm
- **End:** Never
- **Repeat Every:** 4 Hours


The resulting trigger will look similar to the following:



- Define the threshold value in the **If** condition. At the scheduled intervals, the trigger compares the specified threshold with the data from the dataset and takes action. To define the threshold, click **If Metric** to open the panel. Specify the following parameters:

- Metric:** Accept the prepopulated metric, **Cumulative Count of Requests for Feature “abc” Over This Quarter**
- Type of value:** Select **Value**.
- Is:** Select **Greater than or equal to** from the dropdown
- Value:** Type in a value, for example, **50**.

The **If** condition will look similar to the following:



- Define the action that should occur when the **If** condition is met. To do so, click **Action - Send Email** to open the panel. Enter relevant information in the **To**, **Subject**, and **Message** fields.
- Click **Activate** to activate the notification.
- Click **Activity** to open the activity area. The **Activity** area shows the notification that you just created, along with any other notifications.

The following image shows a sample notification:




Figure 11: Example conditional notification triggered if count of feature “abc” exceeds 50 requests over quarter

Using Analytics Reports to Explore Customer Data

The Analytics Dashboard and reports—available from the **Analytics** menu—provide a visual representation of the most important FlexNet Operations entities related to your customer accounts and their entitlement usage. The dashboard and reports are designed to help stakeholders from a wide range of areas—from Renewals Management, Customer Success Management and Support to Product Management—identify trends.

This section introduces the following topics:

- [Data Flow for Data Analytics](#)
- [Analytics Dashboard](#)
- [Reports](#)
- [Downloading Data](#)
- [Sorting Data in Tables](#)
- [Drilldown Action in Charts](#)
- [Subscribing to Dashboards](#)

Data Flow for Data Analytics

The Analytics Dashboard and reports present data from the FlexNet Operations Data Warehouse. The data fetched from the Data Warehouse is refreshed every four hours.

The following diagram shows the data flow from the Data Warehouse for the Analytics Dashboard and reports.

DATA FLOW FOR DATA ANALYTICS




Figure 12: Data flow for data analytics

Analytics Dashboard

Use the Analytics Dashboard (available from the **Analytics** menu) for an overview of your key data, presented as tiles and charts:

The following image shows an example of the Analytics Dashboard:

All filters persist when you navigate away from the Analytics Dashboard page and return to it within the same session.



Tip • The Filter panel might show a condensed view of the applied filters. To see an expanded view, click the filter name. See also [Condensed vs Expanded View](#).

For more detailed information on filters, see [Filtering Data](#).

Drilldown Action in the Analytics Dashboard

You can drill down in the **Fulfillment: Total vs. Available Quantity Per Product** chart by clicking one of the bars in its chart. The drilldown takes you from a high-level view of data to a more granular one, which enables you to go deeper into the data being analyzed.

When you click on a bar, the Analytics Dashboard changes to focus on the product that you are drilling into. FlexNet Operations opens a filtered view which shows only the fulfillments for that product, as shown in the following screenshot:




Figure 14: The Analytics Dashboard after drilldown into the **Fulfillment: Total vs. Available Quantity Per Product** chart

When you drill down into a chart on the Analytics Dashboard, the Filter panel displays the filters that are currently applied to the data. Any filters that were applied *before* the drilldown do not persist.

To drill back up to the previous view of the dashboard, click the **Back** button:



Tiles in the Analytics Dashboard

In its top area, the Analytics Dashboard presents a number of tiles showing key data.



Note - You can filter the data of each tile, using the filter icon in the tile's top right corner (see also [Filtering Data in the Analytics Dashboard](#)).

In the following table, the Dataset column indicates the dataset from which each entity draws its data (for more information, see [FlexNet Operations Data Access APIs](#)).

Table 3 - Tiles in the Analytics Dashboard

Dashboard Element	Description	Dataset
Entitlement Line Items	The total number of line items that customers are entitled to.	Entitlements
Devices	The total number of devices. This includes Cloud License Server (CLS) instances, local license servers, and standalone devices (devices that directly connect to FlexNet Operations, which manages device ownership, state, features, and more).	Devices
Served Devices	The total number of served devices (devices that request licenses from a license server).	Served Device
Customers	The total number of regular customer accounts.	Accounts
Customer Users	The total number of users associated with a customer account.	Accounts
Partners	The total number of partner accounts. Distribution partners are wholesalers, distributors, resellers, and retailers.	Accounts
Partner Users	The total number of users associated with a partner account.	Accounts

Charts in the Analytics Dashboard

Below the tiles, the dashboard shows a number of charts. These charts provide an initial overview over a particular set of data (maximum 6 months).

To see a chart's full data, click anywhere in a chart. This opens the respective dashboard with a detailed view.




Important - The behavior of charts has changed. In the previous version of the Analytics Dashboard, clicking a bar in a chart would filter the data that was displayed. In the current version, clicking a bar or data point does not apply a filter, but opens a more detailed view.

In the following table, the Dataset column indicates the dataset from which each chart or table draws its data.



Note - For more information, see [FlexNet Operations Data Access APIs](#).

Table 4 - Charts in the Analytics Dashboard

Dashboard Element	Description	Dataset
Renewal: Active Accounts by Business Region	Bar chart showing the number of active and expired entitlements, grouped by account region.	Entitlements
Fulfillment: Total vs Available Quantity Per Product	Bar chart showing the number of purchased entitlements vs the number of fulfilled entitlements per product. This is also referred to as the Fulfillment Report .	Entitlements
Top Products by Standalone Devices	Each bar shows how many devices use a product.  Note - The figure does not take the device status into account.	Standalone Devices
Top Feature Requests by Served Devices	Trend is based on the Last Modified Date (on the x-axis); it shows when something happened to the device—indicating if a device is active	Served Devices

Renewal: Active Accounts by Business Region

The **Renewal: Active Accounts by Business Region** table shows the total number of active and expired accounts, grouped by the region in which the customer account is located. An account is considered active if it has one or more entitlements with an expiration greater than the current date.



Note - For a reference of the country groupings into the different business regions, see [Countries by Region](#).



Important - The business regions referred to in the context of this table are different from the region that you can optionally specify when you create an account. The region that you specify during account creation is not taken into account in the **Renewal: Active Accounts by Business Region** table.

You can customize the table by filtering it to show only the region or accounts that you want to focus on. The table is based on data from the Entitlements data set and covers subscription licenses only.

Account Business Region	Active Accounts	Expired Accounts	Total Accounts	% Active	% Expired
APAC	33	115	148	22	78
EMEA	1	12	13	8	92
NA	273	1,849	2,122	13	87
Unknown	1	5	6	17	83
	Sum: 308	Sum: 1,981	Sum: 2,289	Average: 15	Average: 85

Figure 15: An example of the **Renewal: Active Accounts by Business Region** table

The **Renewal: Active Accounts by Business Region** table and its detailed dashboard track and visualize churn over time, thereby helping producers gain insights into their customer retention KPI. It helps identify patterns and trends associated with customer departures, which impact their overall Annual Recurring Revenue (ARR) goals. For example:

- Which customers or accounts are canceling their software subscriptions or ceasing to use the software altogether.
- The regions or countries with the highest and lowest churn rates.
- Which products were most affected by churn.
- When the churn occurred.

Detailed View of Renewal: Active Accounts by Business Region

Click anywhere in the **Renewal: Active Accounts by Business Region** table to display its detailed dashboard view. (Note that the cursor doesn't change shape to indicate that the table is clickable.) The view is grouped into the following elements:

- **Active Accounts by Business Region**—Table showing the percentages of active vs expired accounts, grouped by business region.

Clicking a row for a specific business region changes the data in all tables on the page to focus on the selected business region.



Note - The Filter panel displays the filter that the drilldown applied. To return to the previous view, delete or disable the filter.

- **Active Accounts by Country**—Table showing the percentages of active vs expired accounts, grouped by country.

Clicking a row for a specific country changes the data in all tables on the page to focus on the selected country.



Note - The Filter panel displays the filter that the drilldown applied. To return to the previous view, delete or disable the filter.

- **Active Activations by Product**—Table showing the number of active vs expired activations, grouped by product.
- **Entitlements and Activations Details**—Table listing all entitlement and activation details.



Note - The data for the **Renewal: Active Accounts by Business Region** tables is based on the Entitlements data set and covers subscription licenses only. Therefore, a global filter has been defined for an expiration date of 8000-01-01, which filters out any permanent licenses.

The image, below, shows a sample of the **Renewal: Active Accounts by Business Region** detailed view.




Figure 16: Detailed view of the **Renewal: Active Accounts by Business Region** tables

Countries by Region

Countries are grouped into the following business regions:

- APAC (Asia-Pacific)

- EMEA (Europe, the Middle East and Africa)
- LATAM (Latin America)
- NA (North America)

To confirm the categorization of a specific country, refer to the following table.

Table 5 - Business region grouping

Country Code	Country Name	Region	AD
ad	Andorra	EMEA	AD
ae	United Arab Emirates	EMEA	AE
af	Afghanistan	EMEA	AF
ag	Antigua and Barbuda	LATAM	AG
ai	Anguilla	LATAM	AI
al	Albania	EMEA	AL
am	Armenia	EMEA	AM
ao	Angola	EMEA	AO
aq	Antarctica	EMEA	AQ
ar	Argentina	LATAM	AR
as	American Samoa	APAC	AS
at	Austria	EMEA	AT
au	Australia	APAC	AU
aw	Aruba	LATAM	AW
ax	Åland Islands	EMEA	AX
az	Azerbaijan	EMEA	AZ
ba	Bosnia and Herzegovina	EMEA	BA
bb	Barbados	LATAM	BB
bd	Bangladesh	APAC	BD
be	Belgium	EMEA	BE
bf	Burkina Faso	EMEA	BF

Table 5 • Business region grouping

Country Code	Country Name	Region	AD
bg	Bulgaria	EMEA	BG
bh	Bahrain	EMEA	BH
bi	Burundi	EMEA	BI
bj	Benin	EMEA	BJ
bl	Saint Barthélemy	EMEA	BL
bm	Bermuda	LATAM	BM
bn	Brunei Darussalam	APAC	BN
bo	Bolivia, Plurinational State of	LATAM	BO
br	Brazil	LATAM	BR
bs	Bahamas	LATAM	BS
bt	Bhutan	APAC	BT
bv	Bouvet Island	EMEA	BV
bw	Botswana	EMEA	BW
by	Belarus	EMEA	BY
bz	Belize	LATAM	BZ
ca	Canada	NA	CA
cc	Cocos (Keeling) Islands	APAC	CC
cd	Congo, the Democratic Republic of the	EMEA	CD
cf	Central African Republic	EMEA	CF
cg	Congo	EMEA	CG
ch	Switzerland	EMEA	CH
ci	Côte d'Ivoire	EMEA	CI
ck	Cook Islands	EMEA	CK
cl	Chile	LATAM	CL

Table 5 • Business region grouping

Country Code	Country Name	Region	AD
cm	Cameroon	EMEA	CM
cn	China	APAC	CN
co	Colombia	LATAM	CO
cr	Costa Rica	LATAM	CR
cu	Cuba	LATAM	CU
cv	Cabo Verde	EMEA	CV
cw	Curaçao	EMEA	CW
cx	Christmas Island	APAC	CX
cy	Cyprus	EMEA	CY
<b.cz< b=""></b.cz<>	Czechia	EMEA	CZ
de	Germany	EMEA	DE
dj	Djibouti	EMEA	DJ
dk	Denmark	EMEA	DK
dm	Dominica	LATAM	DM
do	Dominican Republic	LATAM	DO
dz	Algeria	EMEA	DZ
ec	Ecuador	LATAM	EC
ee	Estonia	EMEA	EE
eg	Egypt	EMEA	EG
eh	Western Sahara	EMEA	EH
er	Eritrea	EMEA	ER
es	Spain	EMEA	ES
et	Ethiopia	EMEA	ET
fi	Finland	EMEA	FI

Table 5 • Business region grouping

Country Code	Country Name	Region	AD
fj	Fiji	APAC	FJ
fk	Falkland Islands (Malvinas)	LATAM	FK
fm	Micronesia, Federated States of	APAC	FM
fo	Faroe Islands	EMEA	FO
fr	France	EMEA	FR
ga	Gabon	EMEA	GA
gb	United Kingdom of Great Britain and Northern Island	EMEA	GB
gd	Grenada	LATAM	GD
ge	Georgia	EMEA	GE
gf	French Guiana	EMEA	GF
gg	Guernsey	EMEA	GG
gh	Ghana	EMEA	GH
gi	Gibraltar	EMEA	GI
gl	Greenland	EMEA	GL
gm	Gambia	EMEA	GM
gn	Guinea	EMEA	GN
gp	Guadeloupe	EMEA	GP
gq	Equatorial Guinea	EMEA	GQ
gr	Greece	EMEA	GR
gs	South Georgia and the South Sandwich Islands	LATAM	GS
gt	Guatemala	LATAM	GT
gu	Guam	APAC	GU
gw	Guinea-Bissau	EMEA	GW
gy	Guyana	LATAM	GY

Table 5 • Business region grouping

Country Code	Country Name	Region	AD
hk	Hong Kong	APAC	HK
hm	Heard Island and McDonald Islands	EMEA	HM
hn	Honduras	LATAM	HN
hr	Croatia	EMEA	HR
ht	Haiti	LATAM	HT
hu	Hungary	EMEA	HU
id	Indonesia	APAC	ID
ie	Ireland	EMEA	IE
il	Israel	EMEA	IL
im	Isle of Man	EMEA	IM
in	India	APAC	IN
io	British Indian Ocean Territory	APAC	IO
iq	Iraq	EMEA	IQ
ir	Iran, Islamic Republic of	EMEA	IR
is	Iceland	EMEA	IS
it	Italy	EMEA	IT
je	Jersey	EMEA	JE
jm	Jamaica	LATAM	JM
jo	Jordan	EMEA	JO
jp	Japan	APAC	JP
ke	Kenya	EMEA	KE
kg	Kyrgyzstan	EMEA	KG
kh	Cambodia	APAC	KH
ki	Kiribati	APAC	KI

Table 5 • Business region grouping

Country Code	Country Name	Region	AD
km	Comoros	EMEA	KM
kn	Saint Kitts and Nevis	LATAM	KN
kp	Korea, Democratic People's Republic of	APAC	KP
kr	Korea, Republic of	APAC	KR
kw	Kuwait	EMEA	KW
ky	Cayman Islands	LATAM	KY
kz	Kazakhstan	EMEA	KZ
la	Lao People's Democratic Republic	APAC	LA
lb	Lebanon	EMEA	LB
lc	Saint Lucia	LATAM	LC
li	Liechtenstein	EMEA	LI
lk	Sri Lanka	APAC	LK
lr	Liberia	EMEA	LR
ls	Lesotho	EMEA	LS
lt	Lithuania	EMEA	LT
lu	Luxembourg	EMEA	LU
lv	Latvia	EMEA	LV
ly	Libya	EMEA	LY
ma	Morocco	EMEA	MA
mc	Monaco	EMEA	MC
md	Moldova, Republic of	EMEA	MD
me	Montenegro	EMEA	ME
mf	Collectivity of Saint Martin	EMEA	MF
mg	Madagascar	EMEA	MG

Table 5 - Business region grouping

Country Code	Country Name	Region	AD
mh	Marshall Islands	APAC	MH
mk	Macedonia, the former Yugoslav Republic of	EMEA	MK
ml	Mali	EMEA	ML
mm	Myanmar	APAC	MM
mn	Mongolia	APAC	MN
mo	Macao	APAC	MO
mp	Northern Mariana Islands	APAC	MP
mq	Martinique	EMEA	MQ
mr	Mauritania	EMEA	MR
ms	Montserrat	LATAM	MS
mt	Malta	EMEA	MT
mu	Mauritius	EMEA	MU
mv	Maldives	APAC	MV
mw	Malawi	EMEA	MW
mx	Mexico	LATAM	MX
my	Malaysia	APAC	MY
mz	Mozambique	EMEA	MZ
na	Namibia	EMEA	NA
nc	New Caledonia	EMEA	NC
ne	Niger	EMEA	NE
nf	Norfolk Island	APAC	NF
ng	Nigeria	EMEA	NG
ni	Nicaragua	LATAM	NI
nl	Netherlands	EMEA	NL

Table 5 - Business region grouping

Country Code	Country Name	Region	AD
no	Norway	EMEA	NO
np	Nepal	APAC	NP
nr	Nauru	APAC	NR
nu	Niue	APAC	NU
nz	New Zealand	APAC	NZ
om	Oman	EMEA	OM
pa	Panama	LATAM	PA
pe	Peru	LATAM	PE
pf	French Polynesia	EMEA	PF
pg	Papua New Guinea	APAC	PG
ph	Philippines	APAC	PH
pk	Pakistan	APAC	PK
pl	Poland	EMEA	PL
pm	Saint Pierre and Miquelon	EMEA	PM
pn	Pitcairn	APAC	PN
pr	Puerto Rico	LATAM	PR
ps	Palestine, State of	EMEA	PS
pt	Portugal	EMEA	PT
pw	Palau	APAC	PW
py	Paraguay	LATAM	PY
qa	Qatar	EMEA	QA
re	Réunion	EMEA	RE
ro	Romania	EMEA	RO
rs	Serbia	EMEA	RS

Table 5 • Business region grouping

Country Code	Country Name	Region	AD
ru	Russian Federation	EMEA	RU
rw	Rwanda	EMEA	RW
sa	Saudi Arabia	EMEA	SA
sb	Solomon Islands	APAC	SB
sc	Seychelles	EMEA	SC
sd	Sudan	EMEA	SD
se	Sweden	EMEA	SE
sg	Singapore	APAC	SG
sh	Saint Helena, Ascension and Tristan da Cunha	EMEA	SH
si	Slovenia	EMEA	SI
sk	Slovakia	EMEA	SK
sl	Sierra Leone	EMEA	SL
sm	San Marino	EMEA	SM
sn	Senegal	EMEA	SN
so	Somalia	EMEA	SO
sr	Suriname	LATAM	SR
ss	South Sudan	EMEA	SS
st	Sao Tome and Principe	EMEA	ST
sv	El Salvador	LATAM	SV
sx	Sint Maarten	EMEA	SX
sy	Syrian Arab Republic	EMEA	SY
sz	Swaziland	EMEA	SZ
tc	Turks and Caicos Islands	LATAM	TC
td	Chad	EMEA	TD

Table 5 • Business region grouping

Country Code	Country Name	Region	AD
tf	French Southern Territories	EMEA	TF
tg	Togo	EMEA	TG
th	Thailand	APAC	TH
tj	Tajikistan	EMEA	TJ
tk	Tokelau	APAC	TK
tl	Timor-Leste	APAC	TL
tm	Turkmenistan	EMEA	TM
tn	Tunisia	EMEA	TN
to	Tonga	APAC	TO
tr	Turkey	EMEA	TR
tt	Trinidad and Tobago	LATAM	TT
tv	Tuvalu	APAC	TV
tw	Taiwan, Province of China	APAC	TW
tz	Tanzania, United Republic of	EMEA	TZ
ua	Ukraine	EMEA	UA
ug	Uganda	EMEA	UG
um	United States Minor Outlying Islands	APAC	UM
us	United States of America	NA	US
uy	Uruguay	LATAM	UY
uz	Uzbekistan	EMEA	UZ
va	Holy See	EMEA	VA
vc	Saint Vincent and the Grenadines	LATAM	VC
ve	Venezuela, Bolivarian Republic of	LATAM	VE
vg	Virgin Islands, British	LATAM	VG

Table 5 • Business region grouping

Country Code	Country Name	Region	AD
vi	Virgin Islands, U.S.	LATAM	VI
vn	Vietnam	APAC	VN
vu	Vanuatu	APAC	VU
wf	Wallis and Futuna	EMEA	WF
ws	Samoa	APAC	WS
ye	Yemen	EMEA	YE
yt	Mayotte	EMEA	YT
za	South Africa	EMEA	ZA
zm	Zambia	EMEA	ZM
zw	Zimbabwe	EMEA	ZW

Fulfillment: Total vs Available Quantity Per Product

The **Fulfillment: Total vs Available Quantity Per Product** chart helps you gain an understanding of how your customers are utilizing the licenses they've procured.

To see a detailed visualization of the data, which is referred to as the Fulfillment report, click anywhere in the chart or select **Analytics > Fulfillment**. For more information about this report, see [Fulfillment Report](#).

Top Products by Devices

The **Top Products by Devices** chart is based on data from standalone devices (devices that directly connect to FlexNet Operations), Cloud License Server (CLS) instances, and local license servers. Click a bar in the chart to open its detailed dashboard, which includes the following:

- **Top Products by Devices**—Each bar shows how many devices use a particular product. The view covers devices of any state (active/returned/obsolete).
- **Device Status Trend**—This bar chart is based on the devices' last modified date and visualizes changes in the device status.
- **Devices Details**—Use the table to view detailed information.




Figure 17: Example dashboard for Top Products by Devices

Top Feature Requests by Served Devices

The **Top Feature Requests by Served Devices** chart is based on served devices data. Served devices are devices that request licenses from a license server. The chart shows the most frequently requested features, grouped by served devices.

Click a bar in the chart to open its detailed dashboard.




Figure 18: Example dashboard for **Top Feature Requests by Served Devices**

For more information about this report, see [High-Water Mark Report](#).

Reports

The Analytics Reports (available from the **Analytics** menu) are an easy-to use tool for ad-hoc reporting and data analysis. The table format provides an easy way to view the data and perform various analytical functions, such as grouping, sorting, and filtering. For more information the available tools, see the sections [Sorting Data in Tables](#) and [Filtering Data](#).

Any filters that you define for a report will persist when you navigate away from the report and return to it at a later time within the same FlexNet Operations session. However, when you log out of FlexNet Operations, filters are reset to their default values.

The following table lists the available reports along with a short description:

Table 6 - Reports in the **Analytics > Reports** Menu

Report	Description
Renewals Report	Bar chart showing an up-to-date overview of your customers' renewal position for subscription licenses.
Fulfillment Report	Bar chart showing the number of purchased entitlements vs. the number of fulfilled entitlements per product.
Accounts Created Report	Table only. Shows recently created regular customer accounts.
Entitlement Line Items Created Report	Table only. Shows recently created entitlements and line items.
High-Water Mark Report	Includes two charts: <ul style="list-style-type: none"> Bar chart showing the most requested features (a feature is uniquely identified by its name and version) across served devices Line chart showing the feature usage of served devices over a configurable amount of time

Extending and Customizing Reports

Customers who want to extend the reporting capabilities offered by the Analytics reports can use the FlexNet Operations Data Access APIs to do so.

Every “Reports” section has an “Attributes” table which lists the equivalent field names that are used by the [FlexNet Operations Data Access APIs](#) to extract data from the data warehouse.

To see a diagram that indicates the relationships between the various entities that are returned by the FlexNet Operations Data Access API, refer to the [Data Access API Entity Relationship Diagram and Field Descriptions](#).

Renewals Report

The Renewals report provides a comprehensive and up-to-date overview of your customers' renewal position, covering subscription licenses. The report shows the entitlements that are about to expire within a configurable time frame (default: 90 days), along with information about the entitlements' owner, entitlement ID, activation ID, as well as information about the products mapped to the entitlements.

The Renewals report is useful in highlighting those customers whose renewal status is of most interest to the appropriate stakeholders, namely Renewals Managers and Customer Success Managers. Stakeholders also have the option to set up automated notifications using managed notifications (see [Setting Up Conditional Notifications Based on Data Changes](#)), or to download the data and send it to their customers directly.

The Renewals report can also be used to show entitlements that have already expired and use this as a basis to re-engage with customers.

Attributes for Renewals Report

The Renewals report draws data from the **Entitlements** dataset that is used by the FlexNet Operations Data Access API. For more information, see [FlexNet Operations Data Access APIs](#).

The table, below, lists the attributes included in the Renewals report.

Table 7 - Attributes in Renewals Report

Attribute	Description	Equivalent Field Name in Data Access API
Account Name	The account ID for the end user (customer) account that owns the entitlement.	CustomersAndPartners.EndCustomerAccount Name
Account ID	The account ID for the end user (customer) account that owns the entitlement.	CustomersAndPartners.EndCustomerAccount ID
Entitlement ID	A 19-digit unique identifier of the entitlement record as defined in FlexNet Operations.	EntitlementID
Activation ID	The unique identifier of the entitlement line item as defined in FlexNet Operations.	ActivationID
Expiration Date	Expiration date of the line item.	EndDate
Product Name	The name of the product entitled by the line item.	ProductName
Product Version	The version of the product entitled by the line item.	ProductVersion
Total Quantity	Net copies available for the line item. This includes all new, upgrade, upsell and renew orders, and excludes all upgraded, upsold, renewed, obsolete, and inactive orders for a line item.	OrderedSeatCount
Available Quantity	The difference between the quantity of the product entitled by the line item (as per entitlement field <code>lineItemQuantity</code>) and the number of copies that have not yet been mapped to a device or license server.	RemainingCopies

Sample of Renewals Report

The image, below, shows a sample of the Renewals report.




Figure 19: Renewals report example

Fulfillment Report

Use the Fulfillment report to gain insight into the utilization of the licenses your customers have purchased. Grouped by product, the report shows how many entitlements customers have bought and how many they're actually using. The report enables you to identify customers who are over-utilizing entitlements, which can then be targeted for upsell activities. Likewise, the report will show whether customers are under-utilizing specific products, so that your Customer Success team can engage with those customers and ensure their satisfaction with your product.

The report covers all license types, regardless of the license technology used.

By default, the report shows the number of all entitlement line items purchased grouped by product. The data can further be filtered by attributes such as account, entitlement IDs, line item activation IDs, product, or product version.

Attributes for Fulfillment Report

The Fulfillment report draws data from the **Entitlements** dataset that is used by the FlexNet Operations Data Access API. For more information, see [FlexNet Operations Data Access APIs](#).

The table, below, lists the attributes included in the Fulfillment report.

Table 8 - Attributes in Fulfillment Report

Attribute	Description	Equivalent Field Name in Data Access API
Account Name	A display name for an organization's account as defined in FlexNet Operations. (For example, Stark.) The Account Name is what FlexNet Operations displays on most of the Producer Portal and End-User Portal pages.	CustomersAndPartners.EndCustomerAccountName
Account ID	The account ID for the end user (customer) account that owns the entitlement associated with the product.	CustomersAndPartners.EndCustomerAccountID
Entitlement ID	A 19-digit unique identifier of the entitlement record as defined in FlexNet Operations.	EntitlementID
Activation ID	The unique identifier of the entitlement line item as defined in FlexNet Operations.	ActivationID
Product Name	The name of the product entitled by the line item.	ProductName
Product Version	The version of the product entitled by the line item.	ProductVersion
Total Quantity	Net copies available for the line item. This includes all new, upgrade, upsell and renew orders, and excludes all upgraded, upsold, renewed, obsolete, and inactive orders for a line item.	RemainingCopies
Available Quantity	The difference between the quantity of the product entitled by the line item (as per entitlement field <code>lineItemQuantity</code>) and the number or copies that have not yet been mapped to a device or license server.	
Last Modified Date	The date and time that the fulfillment record was last modified.	
Created On	The date on which the line item was created.	CreatedOn

Sample of Fulfillment Report

The image, below, shows a sample of the Fulfillment report.




Figure 20: Fulfillment report example

Accounts Created Report

The Accounts Created report is a table that shows accounts created within a specified time period with information about their account type, creation date, description, address, and number of users.

By default, the report shows the accounts created in the last 90 days.

If desired, use the Created Date filter widget above the table to set the date range for the report. For example, if you define the Created Date as **After Or On January 1st, 2023**, the report returns a list of accounts created since January 1st, 2023.

Attributes for Accounts Created Report

The Renewals report draws data from the **Account** dataset that is used by the FlexNet Operations Data Access API. For more information, see [FlexNet Operations Data Access APIs](#).

The table, below, lists the attributes included in the Accounts Created report.

Table 9 - Attributes in Accounts Created Report

Attribute	Description	Equivalent Field Name in Data Access API
Account ID	The account ID for the end user (customer) account that owns an entitlement or device.	AccountID

Table 9 - Attributes in Accounts Created Report

Attribute	Description	Equivalent Field Name in Data Access API
Account Name	A display name for an organization’s account as defined in FlexNet Operations. (For example, Stark.) The Account Name is what FlexNet Operations displays on most of the Producer Portal and End-User Portal pages.	AccountName
Account Display Name	A display name for an organization’s account as defined in FlexNet Operations. (For example, Stark.) The Account Name is what FlexNet Operations displays on most of the Producer Portal and End-User Portal pages.	AccountName
Account Description	The description associated with the account.	AccountDescription
Account Type	Identifies an account as one of the following types: <ul style="list-style-type: none"> ● CUSTOMER—Regular customer accounts. ● SELF_REGISTERED—Self-registered accounts. ● CHANNEL_PARTNER—Channel partner accounts. ● PUBLISHER—Producer accounts. Accounts without a standard account type are shown as UNKNOWN .	AccountType
Created Date	The date the account was first created in the FlexNet Operations system.	CreateDate
Account Address 1	The first line of the optional street address of the account.	Address1
Account Address 2	The second line of the optional street address of the account.	Address2
Account City	The city for the address associated with the account.	City
Account Country	The country code for the account.	Country

Table 9 - Attributes in Accounts Created Report

Attribute	Description	Equivalent Field Name in Data Access API
Account Region	The region where the account is situated. For instance, EMEA or APAC. Region is an optional field in the account creation process and can contain any region designation the user enters.	Region
Parent Account IDs	The account ID of the parent account, if any.	ParentAccountIDs
Parent Account Names	The name of the parent account, if any.	Derived based on the Parent Account IDs field.

Entitlement Line Items Created Report

The Entitlement Line Items Created report shows recently created entitlement line items with information about their owner, entitlement ID, activation ID, product name and version, as well as the entitlements' creation, expiration, and maintenance end dates.

By default, the report shows the entitlements and their line items created in the last 90 days.

If desired, use the Created On filter widget above the table to set the date range for the report. For example, if you define the Created On date as **After Or On January 1st, 2023**, the report returns a list of entitlements modified since January 1st, 2023.

Attributes for Entitlement Line Items Created Report

The Renewals report draws data from the **Entitlements** dataset that is used by the FlexNet Operations Data Access API. For more information, see [FlexNet Operations Data Access APIs](#).

The table, below, lists the attributes included in the Entitlement Line items Created report.

Table 10 - Attributes in Entitlement Line Items Created Report

Attribute	Description	Equivalent Field Name in Data Access API
End Customer Account Name	A display name for an organization's account as defined in FlexNet Operations. (For example, Stark.) The Account Name is what FlexNet Operations displays on most of the Producer Portal and End-User Portal pages.	CustomersAndPartners.EndCustomerAccountName
End Customer Account ID	The account ID for the end user (customer) account that owns the entitlement associated with the product.	CustomersAndPartners.EndCustomerAccountID

Table 10 - Attributes in Entitlement Line Items Created Report

Attribute	Description	Equivalent Field Name in Data Access API
Entitlement ID	A 19-digit unique identifier of the entitlement record as defined in FlexNet Operations.	EntitlementID
Line Item Activation ID	The unique identifier of the entitlement line item as defined in FlexNet Operations.	ActivationID
Product Name	The name of the product entitled by the line item.	ProductName
Product Version	The version of the product entitled by the line item.	ProductVersion
Total Quantity	Net copies available for the line item. This includes all new, upgrade, upsell and renew orders, and excludes all upgraded, upsold, renewed, obsolete, and inactive orders for a line item.	OrderedSeatCount
Available Quantity	The difference between the quantity of the product entitled by the line item (as per entitlement field lineItemQuantity) and the number of copies that have not yet been mapped to a device or license server.	RemainingCopies
License Model	The license model used for the line item.	LicenseModel

Table 10 - Attributes in Entitlement Line Items Created Report

Attribute	Description	Equivalent Field Name in Data Access API
Start Date Option	<p>Type of defined start date, as one of the following:</p> <ul style="list-style-type: none"> ● Specify at each activation: The user is prompted to specify a start date each time the line item is activated. Each fulfillment record gets a new start date, and for duration-based entitlements, each fulfillment record's expiration date is set to start date specified + duration. ● Specify value now: The start date was specified at the time of the entitlement's creation. All fulfillment records of this line item get this start date. ● Use first activation date: The date of the first activation is used as the start date. All fulfillment records for this line item get the same start date. ● Specify at first activation: The user is prompted to specify a start date when first activating the line item. This start date is used for all fulfillment records. ● Use each activation date: Every time the line item is activated, the activation date is used as the start date. Each fulfillment record gets a new start date. As a result, for duration-based entitlements, each fulfillment record's expiration date is set to activation date + duration. 	StartDateType
Start Date	Start date of the line item	StartDate
Created On	The date on which the line item was created.	CreatedOn
Expiration Date	<p>Expiration date of the line item.</p> <p>For perpetual licenses, this column shows Permanent.</p>	EndDate

High-Water Mark Report

The High-Water Mark report provides insights into your customers' usage patterns of specific features in enterprise applications over time. The report is based on served device records and shows the feature consumption over a configurable amount of time. It enables you to identify trends in feature usage, which can help you determine how features are being utilized amongst your customer base.

Filter by account name or feature name to see how feature use for a specific account is trending over time. See also [Drilldown in High-Water Mark Report](#).



Note ▪ A feature is uniquely identified by its name and its version.



Tip ▪ The High-Water Mark report shows data for served devices only. To get insight into license use for any license type, use the Fulfillments report.

Charts in the High-Water Mark Report

The High-Water Mark report includes the following charts:

- **Top (50) Feature Requests**—In this bar chart, each bar represents a particular feature. For each feature, the chart shows how many times the feature was requested in the time frame set by the filter (if applicable). The chart focuses on the 50 features with the highest number of requests.

Point to a bar to display a particular feature name and the number of times the feature was requested. Move through the list of features using the scroll bar until you see the feature that you want.



Note ▪ Each bar represents one feature and all of its versions (if more than one version exists for a feature). For example, if feature f1 has two versions v1.0 and v2.0, and f1 v1.0 was requested 5 times and f1 v2.0 was requested 7 times, pointing to the bar would display the feature information f1: 12.

- **Monthly Feature Consumption Trend**—In this line chart, each dot represents a particular month and the number of times the feature(s) were requested within that month.

Point to a dot to display the month and number of features requested in that month.

You can click on a bar or dot in each chart to drill down into the date. For more information, see [Drilldown in High-Water Mark Report](#).

Attributes for High-Water Mark Report

The High-Water Mark report draws data from the **Served Device** dataset that is used by the FlexNet Operations Data Access API. For more information, see [FlexNet Operations Data Access APIs](#).

The table, below, lists the attributes included in the High-Water Mark report.

Table 11 - Attributes in High-Water Mark Report

Attribute	Description	Equivalent Field Name in Data Access API
Feature Name	The name of the feature request by the served device from the license server.	FeatureName
Feature Version	The version of the feature request by the served device from the license server.	FeatureVersion
Server Host ID	The ID of the server that the device requests licenses from.	ServerHostID
Served Client Host ID	The ID of the served device.	ServedClientHostID
Quantity	The quantity of the feature request by the served device from the license server.	Quantity
Account Name	A display name for an organization's account as defined in FlexNet Operations. (For example, Stark.) The Account Name is what FlexNet Operations displays on most of the Producer Portal and End-User Portal pages.	DeviceAccountName
Account ID	The account ID for the end user (customer) account that owns the entitlement associated with the product.	DeviceAccountID
Expiration Date	Expiration date of the line item. For perpetual licenses, this column shows Permanent.	ExpirationDate
Last Modified Date	Date and time feature was last updated.	LastModifiedDate

Sample of High-Water Mark Report

The image, below, shows a sample of the High-Water Mark report.




Figure 21: High-Water Mark report example

Dropdown Filters in the High-Water Mark Report

The dropdown filters **Features** and **Account Name** above the **Monthly Feature Consumption Trend** chart work in a cascading fashion from left to right. In other words, if you select a specific feature from the **Features** dropdown filter, the **Account Name** dropdown filter only shows the accounts that requested that feature.

However, selecting an account from the **Account Name** dropdown filter has no effect on the **Features** dropdown filter.

The **Top (50) Feature Requests** chart, **Monthly Feature Consumption Trend** chart and the **Feature Consumption Details** table are updated regardless of the direction in which the dropdown filters are applied.

Drilldown in High-Water Mark Report

You can drill down into the charts of the High-Water Mark report to visualize lower levels of the underlying data. The drilldown acts as an additional filter, which is reflected in the Filter panel and in the filter menu of the **Feature Consumption Details** table (below the charts).



Note - The drilldown action has no effect on the **Features** and **Account Name** dropdown filters (above the **Monthly Feature Consumption Trend** chart).

Before you drill down, you can point to the desired data point (a dot in the line chart or a bar in the bar chart) to display the underlying data in the form of a string.

To drill down, click on a data point. Note that for every drilldown action, a relevant filter is added to the Filter panel. To drill back up to the previous view, remove or disable the filter that was added by the drilldown from the Filter panel (see also [Editing or Deleting a Filter](#)).

Any filters are reset to their default values when you navigate away from the High-Water Mark report.

You can drill down by feature name or by date range, or both.

- **Drilldown by Feature Name**—In the **Top (50) Feature Requests** bar chart, click on a bar to see all requests made for a particular feature within the time frame set by the filter (if applicable). You will notice the following:
 - The bar chart changes to a single bar which represents the total number of requests for the feature.
 - The **Overall Feature Consumption Trend** line chart adjusts to display the total number of counts for the selected feature for the specified time frame.
 - In the Filter panel, the particular feature name is added as a filter condition in the Dashboard layer, using the AND operator.
 - The **Monthly Feature Consumption Trend** chart and the **Feature Consumption Details** table adjusts to reflect the filter.
- **Drilldown by Date**—In the **Monthly Feature Consumption Trend** line chart, click on a dot to focus on the next-lower level of the date hierarchy (for example, you can drill down from showing feature requests for a duration of 3 months to a specific month). You will notice the following:
 - The line chart changes to represent the next level in the hierarchy (months or days).
 - The **Top (50) Feature Requests** bar chart adjusts to display the total number of feature requests for the specified time frame.
 - In the Filter panel, the **Last Modified Date** filter includes the new filter condition (for example, Equals (Month, Year): Apr 2023).

You can further filter the data by Feature or Account Name, or any field using the regular filters.

Downloading Data

You can download tables, dashboards, and reports in print-friendly formats such as PDF, as well as data dumps to CSV for further analysis in other tools such as Excel.

You can download the entire dashboard with all the panels or choose a single panel and download only that one. Depending on the chosen format and the context, the available formats are:

- **CSV**—For data export. The data downloaded is the “raw” data behind the visualizations and not aggregated in the same way that it appears in the visualizations. For aggregated data, use the CSV Summary export.
- **CSV Summary**—For data export. This option is fairly similar to the CSV export, in that it only includes the columns that have been used in the chart, but the data is reflected in its aggregated form in the same way that it has been aggregated for the chart.
- **EXCEL**—For data export. The same data is downloaded as for the CSV option.
- **JPG**—For visual layout export. The exported visuals are downloaded as they appear at the time of export and may include scroll bars or show only the part of the charts that are visible within the panels. The best way to describe this feature is that the JPG export looks exactly like a screenshot of the visual.
- **PDF**—For visual layout export, as well as data export in the case of table charts. This option produces results that look a lot like the JPG export, but are in PDF format. The feature that sets PDF export apart from other

formats is its different behavior when it comes to exporting tables: In this case, all of the data for the table is exported, much like a CSV export, but in PDF format.




Note - To prevent you from having to wait until your browser completes the export request, you are given the option to have the file emailed to you. If authentication has not been set up, you are asked to provide your email address.



Task *To download data for an individual dashboard, table, or report*

In the upper right corner of the chart or table, click the three dots menu, point to **Downloads** and then click the desired download format.



Task *To download data for an entire dashboard*

Open the dashboard and click the button with the three dots in the bottom right corner of the page:



The **Download** button is displayed:



Click the **Download** button and select the desired download format.



Important - When you download a report, you need to stay on the page until the download has completed. Each download is limited to a maximum of 50,000 records.

Sorting Data in Tables


Data in tables can be sorted by any one of the table columns or even by multiple table columns. An arrow icon in the column header indicates the sorting direction; the up arrow indicates ascending sort order and the down arrow indicates descending sort order.

Multi-column sorting gives you the option to first sort by one column and lets the next column's sorting be applied on top of the previous sorting. For example, in a table that contains a list of all Customers with their respective Country and City, you can choose to sort by either one of those columns by clicking on the column header.


- Sorting by Country in ascending order would result in a list where customers in Australia are listed first, but those in various cities in Australia may appear in any order.

- Sorting by City, on the other hand, would result in customers who live in Aachen, Germany, to be listed on top—if done in ascending order.

If you want to still list Australian customers on top, but also sort the cities that are in Australia—or in other words sort cities dependent on the previously-sorted countries—you can enable the feature by selecting it from the three-dot menu in any column's header.



Once the feature is enabled, an **Apply Multi-Column Sort** button appears above the table, from which various sorting options can be controlled. Sorting any of the columns after this point will result in it being sorted after—and on top of—the one that was sorted before it. The feature can be removed at any time by clicking on the X icon on the button, and columns can be added, removed or dragged to another position in the stack to determine the priority of their sorting level.



Drilldown Action in Charts


The Drilldown action on a line or bar chart enables you to filter the data by clicking on a data point (a dot in a line chart or a bar in a bar chart). For example, you may choose one of the values, and that action filters the chart according to the selected value. The Filter panel displays the additional filter that is applied to the data.

To drill back up to the previous view, remove the filter that was added by the drilldown from the Filter panel.

Any filters are reset to their default values when you navigate away from the page that you are on.

Subscribing to Dashboards

You can configure a scheduled delivery of dashboards and manage any existing subscriptions. You access the subscription functionality by clicking the three-dot menu in the bottom right corner of the Analytics Dashboard or any of the reports pages. This will bring up the Dashboard Subscription button. Click the button to show the available options:



Configuring Subscriptions

Choosing the **Subscribe to Dashboards** option from the menu opens up the Dashboard Subscription dialog box where you configure the subscription.

Each subscription configuration must be given a name. This name is used to identify the configuration if it needs to be modified or managed later. Choose a name that is meaningful to you and you can remember later.

You can choose any number (or all) of the pages and/or any number (or all) of the charts to be included in your scheduled export. Choose the format(s) for your export. The default format is PDF. If exporting charts and not only entire pages, you may also choose CSV summary or CSV raw formats. You have to have at least one format selected for subscriptions to work. Note that not all charts support CSV summary or CSV raw format and they won't be exported if those are your only selected export formats.

The next step is to configure the schedule of the exports:


- Select the date to start exporting and sending the objects.
- Choose the time for the export. The time zone is the same as yours.
- You can choose to continue the exports until you cancel it (choose **Never** from the **End** dropdown) or stop the delivery after a certain number of repetitions.
- Choose the schedule of repetitions; every 1 week, every 15 days, etc.

Next, enter any email addresses that you want the exports to be delivered to in the **To** field of the email section. Enter a subject for the email and the body of your email using the rich text box provided.

Once done with entering all of the needed information click the **Apply** button to finalize the configuration of your subscription. At the chosen time all of the selected pages will be exported to one file in PDF format. Each selected chart will be exported to an individual file, also in PDF format, and all of the files are packaged in a zip file and the link to download the file is added to the email that you set up. The download link is valid for 7 days from the date of creation.

Managing Subscriptions

Click **Manage Subscriptions** from the menu to open the following dialog.



All of the active subscription configurations that you have created in the past are listed and can be managed from here. The management options can be found in the three-dot menu to the right of each subscription. The **Unsubscribe** command gives you the option to only remove yourself, or all of the subscribers. If there are multiple subscribers and you remove your own email address from the list, others will continue to receive the emails. Once every email account has been removed from the list, the subscription is removed.

The **Edit** command opens the configuration dialog for the selected subscription and lets you modify it. The **Delete** command removes the subscription and all of its subscribers, thereby stopping the scheduled delivery of the emails.

Filtering Data

Filtering enables you to focus on the portion of the data relevant to your analysis, affecting the data displayed in a report, dashboard or metric.

There are many different ways you can filter your data to focus on the things that matter. The essential aspects of the filtering system are described for your reference in this section.

The following topics are discussed in this section:

- [Filter Hierarchy](#)
- [Filter Logic](#)
- [Filter Panel](#)
- [Including and Excluding Deleted Data in Dashboards](#)
- [Viewing Filters Directly from Reports](#)
- [Adding a Filter](#)
- [Editing or Deleting a Filter](#)
- [Defining a Filter](#)
- [Using Tokens in Filters](#)
- [Filtering Based On Relative Dates](#)
- [“Dates” Versus “Date Names”](#)

Filter Hierarchy

Filters apply in a hierarchical model: First, the data gets filtered by the global filters, then by dashboard filters, and then the panel filters refine it even further.

- **Global Filters** are at the top of the filter hierarchy. A global filter applies to all the panels on all tabs on all dashboards (*dashboards* are essentially the pages available from the **Analytics** menu). You define a Global filter in the Filter panel by selecting the **All dashboards** option.
- **Dashboard Filters** apply to all of the panels on all tabs within that dashboard. You define a Dashboard filter in the Filter panel by selecting the **Current dashboards** option.
- **Panel Filters** are applied directly to the charts. Their scope is local, meaning they only apply to the chart where they were defined. You define a Panel filter by clicking the Filter icon above a chart.

The filter panel is interactive and dynamically shows only the filters that apply to the selected component. For instance, if you have both Dashboard and Global filters defined on one dashboard, and you click on another dashboard, the Dashboard filters will be hidden from view, as they don't apply to this dashboard.

Each filter only applies to the selected dataset. For example, a Dashboard filter **Last Modified Date After 2024-01-01** defined for the Entitlements dataset will only apply to the **Renewals: Entitlement Expiration by Month** and **Fulfillment: Total vs. Available Quantity Per Product** charts, which are based on entitlement data. It will not affect the **Top (50) Feature Requests** and **Monthly Feature Consumption Trend** charts, which are based on the Served Device dataset.

Filter Logic

When applying a filter, several pieces come together to have the correct results, especially when mixing multiple filters. Each filter requires a boolean logic to refine the data based on your criteria. The filtering system uses the following logic for each piece that comprises the full filter set:

- Layers
- Columns
- Values

Layers

Each scope in the hierarchy of interactive filters is called a “Layer” - Global, Dashboard, and Chart panels are considered Layers. “AND” logic is used between each layer of filter to refine the data based on the hierarchy defined in the [Filter Hierarchy](#) section.

Example

The following image shows a case where you want to filter the number of Renewals for all pages to only include data for the account **TestOrg**. So a Global filter has been set to filter “*End Customer Account ID Equals TestOrg*”.

Also, assume you want to concentrate on the data for the month of April, 2022 in the Renewals report. So you set a Panel filter for the report to filter “*Expiration Date Equals April 2022*”. Since these two filters are on different layers, the logic between them is AND, resulting in the combined filter to show entitlement data for only April 2022 and the specified account.

Note that the field below the filter indicates the dataset that is being filtered. In this case, the dataset is “*Entitlements*”.




Figure 22: The Filter menu indicates the filter layer and dataset

Columns

When filtering on multiple columns within the same layer, by default “AND” logic is used among the column filters.

Example

Consider the same chart from the previous example. You still have set the Global filter to “End Customer Account ID Equals TestOrg”. But in this case, assume you want to filter all of the charts that are based on the same Entitlements dataset so that they show data for “Expiration Date Equals April 2022”. So you set this second filter at the Global level, too. By default, the filter logic between the two filters will be AND, resulting in the exact same visualization.






Figure 23: Filters are combined using AND logic

Values

When selecting multiple values of the same column to filter the data, “OR” logic is used.



In the Filter panel, you can select which filter should be applied by selecting or deselecting the relevant check box:



Filter Panel

The Filter panel on the right side of the screen is the main area where you can see, control, and interact with all filters that have been set for the features in the Analytics menu.




The panel has several options that can be controlled from the icons above it.

- **Add Filter**—Opens the filter modal where you define the filters.
- **Restore original filters | Restore my filters**—Toggle switch which restores the default filters or restores the last active filter set.
- **Options**—Disables or deletes all filters from the three-dot menu.
- **Collapse/Expand**—Collapses or expands the filter panel.

Filters are listed in groups based on their scope. See [Filter Hierarchy](#) to learn more about scopes and their effect on filters.

You can edit, disable or delete filters within a given scope by clicking the three-dot menu and choosing one of these actions. You can decide which filter values to apply by selecting or clearing the check box next to them.



The Filter panel is interactive and dynamically shows only the filters that apply to the selected component. For instance, if you have both Dashboard and Global filters, and you click on another dashboard, the Dashboard filters will be hidden from view, as they don't apply to this dashboard.

The Filter panel indicates the filter scope and the dataset to which the filter applies. For example, in the following screenshot, the following filters apply:

- The **Renewals** report has been filtered by End Customer Account ID (Equals TestOrg OR FNE_PERF_Org_42853). This is a Global filter affecting the Entitlements dataset across all dashboards, indicated by red boxes in the screenshot.
- The **High-Water Mark** report has been filtered by Feature Name (f1, f2, f3, r4) and Version (1.0). This is a filter affecting the Served Device dataset with a Dashboard scope, indicated by green boxes in the screenshot

Analytics Dashboard

The Analytics Dashboard provides a visual representation of the most important FlexNet Operations entities related to your customer accounts and their entitlement usage.

As of 3/27/2023, 7:54:33 PM




Figure 24: The Filter panel shows all filter scopes



Important - The Filter panel shows the filters in a consolidated fashion. If you are unclear about which filter applies to a particular chart, click the Filter icon above the chart to see which filters apply to it. See also the next section, [Viewing Filters Directly from Reports](#).

Condensed vs Expanded View

The Filter panel might show a condensed view of the applied filters. To see an expanded view, click the filter name. The following screenshots show examples of the different views:




Figure 25: Condensed view of filters in Filter panel





Figure 26: Expanded view of filters in Filter panel

Including and Excluding Deleted Data in Dashboards

For various reasons, companies may delete data, such as accounts, users, or products. Deleted data is retained in the data warehouse but marked as deleted. If needed, this data is still accessible using the Data Access API. For a graphical representation of the datasets and fields for deleted data, see the [Data Access API Entity Relationship Diagram and Field Descriptions](#).


By default, the dashboards and graphs available from the **Analytics** menu do not include any deleted data. Should you want to include deleted data in your analysis, disable or delete the relevant filter in the Filter panel, as shown in the following screenshot:



Because deleted data is managed using a global filter, any action you take affects all other dashboards.

Viewing Filters Directly from Reports

When any filter or filters apply to a report, the filter icon on the report panel is highlighted with a dot, indicating that the report data has been filtered. In that case, you can see these filters in a small popup, by hovering on the report's filter icon.



Any filters that apply to a report are also displayed in the Filter panel. For more information, see [Filter Panel](#).


Adding a Filter



Task *To to add a filter:*

Do one of the following:

- Open the **Filters** bar on the right to display the Filter panel. In the Filter panel, click the **Add Filter** button.
For filters added using the Filter panel, you can select whether the filter applies to all dashboards (Global filter) or only the current dashboard (Dashboard filter).

- Click the **Filters** icon  directly above a chart or table.
Filters added using the Filters icon above a chart or table will have the Panel scope (see also [Filter Hierarchy](#)).

All filters that you add will appear in the Filter panel and the filter list in the chart.

Editing or Deleting a Filter


Filters can be edited or deleted directly from the popup (using the Filters icon above a chart or table).




Task **To edit or delete a filter:**

1. Open the three-dot menu (either in the Filter panel or in the popup).
2. Click **Edit** or **Remove**.

The following screenshot shows the options in the three-dot menu in the popup:



If you only want to temporarily disable a filter (without removing it), open the same in the Filter panel and click **Disable**:



Defining a Filter

The filter modal is the central component when defining filters. It enables you to define the scope, column, conditions, and values to use when filtering your data.

The following image shows the initial state of the filter modal when it's opened. All data columns of the selected dataset are shown in the area in the center and they can be found using the search box. The filter's scope may be defined from the dropdown list in the bottom left corner.




Figure 27: Search or select a dataset's column to create a filter

Once a column is selected, the center part of the filter modal changes to enable you to define your desired criteria.




Figure 28: Elements of the filter modal

1. **Selected column to filter**—You can change your selection by clicking on the arrow on the right side to open the dropdown list of columns.
2. **The operand for filtering**—The default operand may change depending on the selected column's data type. A complete list of operands is available by clicking on the dropdown list component. The selected operand decides the layout of the next section.
3. **Select All and search box**—You can use the search box next to the **Select All** check box to search to add a specific value.
4. **Values available for the selected column**—If a column with text data type and the EQUAL operand is selected, a list of values based on the current data is displayed where you can pick any values from. Scrolling through a long list of values loads more and more of the available data.
5. Values that have been selected or excluded.

This section may look different depending on the operand and the selected column's data type.

When the **Select All** option is checked and the dataset is updated, new values are automatically added to the filter. For example, if you create a filter using the *Countries* column and choose to check **Select All**, and then new values are added to the *Countries* column, these values will be automatically added to the filter you had created.

When you choose **Select All** and clear the selection of some values, these unselected values will appear in the filter modal next to **All Except:** <name of the value>. If you choose to unselect some items, the filter will not include new values automatically when the dataset is updated and new values are added to it.

Once you have defined your filter's criteria, the **Apply** button at the bottom of the window will be enabled. Clicking **Apply** will create a new filter, and your data will be refined based on the selected criteria.

Using Tokens in Filters

Tokens can be used in place of any value that can be typed in or selected for a filter to provide additional flexibility. By typing {{ in any input box inside the filter dialog all system tokens, as well as aggregates of data columns are presented and can be selected from. This allows for creating filters with conditions to find records where the *customer's ordered seat count is less than the average value of the ordered seat count column* as shown in the following image.





Figure 29: Using tokens in the filter modal

Filtering Based On Relative Dates

FlexNet Operations offers a powerful feature for filtering date-type columns that enables you to create the filter based on a variable date, relative to an anchor date. For instance, if today's date is August 2, 2021 and you wish to see the data for the last ten months, instead of selecting the fixed date of October 3, 2020 you can simply select "last 10 months from today". To initiate a relative date filter select a date type column from your filter modal and select the "In" operator from the list of operators.



The screenshot shows a 'Filter' dialog box with the following configuration:

- Column: Expiration Date
- Operator: In
- Direction: The last
- Value: 30
- Unit: Day
- Calendar dates: (enabled)
- Include starting date: (enabled)
- Starting From: Current Date
- Date Selected: 01/16/2023 - 02/14/2023
- Apply to: All pages
- Buttons: Cancel, Apply

You can pick your needed unit (Hour, Day, Week, Month, Quarter, Year) and the direction (This, Next, Last). The other controls on the dialog may be removed or disabled based on these selections. Filters based on hours are only enabled if the date field contains time data.

Calendar Versus Rolling Date Ranges

If **The Last** or **The Next** is selected as the direction of the date filter, and the unit is set to anything but **Hour** or **Day**, the **Calendar dates** check box is enabled and defaults to checked, which takes a calendar-based approach to calculating filter date ranges.

A calendar-based approach calculates the date ranges, taking into account the start and end date of a calendar's period (week, month, year, etc.). For example, if today's date is any day in 2023, "the last 2 years" will be calculated as "the last 2 calendar years", aka 1/1/2022 through 12/31/2023 (assuming that the **Include starting date** check box and **Starting From** anchor are left at their default checked and **Current Date** values).

If the **Calendar dates** check box is unselected and the other controls stay at their same setting, the date range calculation will be "rolling". That means that the last two years will be calculated relative to the anchor date and automatically shift forward without considering calendar periods. So if today's date is February 8, 2023 the filter range will be February 8, 2021 through February 8, 2023 today and change to February 9, 2021 through February 9, 2023 tomorrow, and so on.

Inclusive Versus Exclusive Date Ranges


If **The Last** or **The Next** is selected as the direction of the date filter, and the unit is set to anything but **Hour** or **Day**, the **Include starting date** check box is enabled and defaults to selected. This setting includes the selected date of the anchor in calculating the date range. For example, if today's date is any day in 2023, "the last 2 years" will include 2023, resulting in January 1, 2022 through December 31, 2023. However, if the check box is unselected—making the date range exclusive of the anchor date—the last 2 years will result in January 1, 2021 through December 31, 2022.



Note - The **Dates Selected** label always shows the calculated date range based on the selected values for the controls.

“Dates” Versus “Date Names”

Sometimes there may be a need to filter based on “date names” and not dates. An example of this is when you want to find all data for the “month of January” and not “January 2023”. Or “Q3” in general, as opposed to “Q3 2022”. This can be accomplished by choosing **Quarter of Year**, **Month of Year**, etc. options in the date filter, as opposed to **Quarter**, **Month**, etc. This feature is available for date filters when using the Equals operator.



Formulas

You can use formulas to create new columns of data that do not already exist in a dataset. For example, you can create a formula to segment data, aggregate data, to convert the data type of a field (such as converting a string to a date), to aggregate data, to filter results, to calculate ratios, and much more. Once a formula is created and

saved, it is available as a category on the **Data** panel (on the **Edit Conditional Notification** page) and as a column in the **Filter** dialog for the relevant dataset (available in an Analytics report by clicking **Add Filters** in the **Filter** panel).

You create formulas using the Formula Builder.

This section covers the following topics:

- [Creating Formulas](#)
- [The Formula Builder Interface](#)
- [Data Engine Syntax Mode](#)
- [Standardized Syntax Mode](#)
- [Adding a Nested Formula](#)
- [Editing, Duplicating, and Deleting Formulas](#)

Creating Formulas

You create formulas using the Formula Builder. You access the Formula Builder from the **Metric** tab of a conditional notification, by clicking the uppercase sigma letter in the toolbar.



Task

To create a formula:

1. Click the **Formulas** icon.

The **Formulas** page opens, which lists all formulas that are available for the dataset on which the current conditional notification is based.

2. Click **Create Formula**.

The **Create Formula** page (Formula Builder) opens.

The Formula Builder provides the following modes for creating formulas:

- **Data Engine Syntax (legacy)**—Create formulas using the Elasticsearch syntax. For more information, see [Data Engine Syntax Mode](#).
- **Standardized Syntax**—Create formulas using a standardized syntax. For more information, see [Standardized Syntax Mode](#).

The Formula Builder Interface

The Formula Builder interface consists of three main sections, as indicated in the screen capture below:

- **Formula**—The editor in which you write the formula.
 - Standardized Syntax also provides a **Testing** tab, which enables you to define the input data to test your formula. For more information, see Using Standardized Syntax Mode.
 - Data Engine Syntax provides a **Test** link that tests the formula using random values from the dataset.
- **Insert Functions**—Lists all the functions available to use in your formula, provides a helpful description of each function, and enables you to add functions to the formula.
- **Insert Columns**—Lists all the dataset columns available to add to your formula.




Figure 30: Basic components of formulas

Data Engine Syntax Mode

Data Engine Syntax mode enables you to create formulas using the Elasticsearch syntax. For more information about Elasticsearch, see the [Elasticsearch Guide](#).

This section covers the following topics:

- [Creating a Formula Using Data Engine Syntax Mode](#)

- [Examples for Formulas Using Data Engine Syntax Mode](#)
- [Data Engine Syntax](#)
- [Functions Supported in Data Engine Syntax](#)

Creating a Formula Using Data Engine Syntax Mode

You create formulas in Data Engine Syntax mode using the Formula Builder. Any formulas that you create can be used in nested formulas (see [Adding a Nested Formula](#)).

For general information on using the Formula Builder interface, see [The Formula Builder Interface](#).



Task

To create a formula using Data Engine Syntax (Legacy) mode

1. Open the Formula Builder interface and select **Data Engine Syntax (legacy)**.
2. Enter a name in the **Formula Name** box.
3. To add a function to the formula, type it directly in the editor. A suggestion box is displayed with columns and functions that fit your text. You may also use the following method:
 - a. Under **Insert Functions**, select the function that you want to insert. The description box displays helpful information about the function.



Tip - To only display functions for a specific category, select a category from the dropdown box above **Insert Function**.

- b. Click **Add to Formula**. The formula displays in the **Formula** box.
4. To add a column to the formula, type it directly in the editor. A suggestion box is displayed with columns and functions that fit your text. You may also use the following method:
 - a. Insert the cursor in the desired location in the formula.
 - b. Under **Insert Columns**, click on the column that you want to insert. The column displays in the **Formula** box.
 5. Continue to add functions and columns until your formula is complete.
 6. Before you can use the formula, you must test it. At any time while building your formula, click **Test**. The formula will be tested with random values from the dataset. An error displays if the formula has a mistake.
 7. Click **Save** to save the formula.

Examples for Formulas Using Data Engine Syntax Mode

The following examples describe typical scenarios for using formulas.

- [Extracting a Month From a Date](#)
- [Aggregate Values of All Rows](#)

- Concatenating Text Columns
- Using an “if” Statement

Extracting a Month From a Date

The function that returns any part of a date or date/time value is dateFormat:

Table 12 • Extracting a Month from a Date

Item	Description
Function	dateFormat
Syntax	dateFormat(date_value, 'format')
Example	<p>orderDate is a date data type and we need to extract the month part of it to use on the x-axis of a bar chart.</p> <p>We can create a new formula as:</p> <pre>dateFormat([orderDate], 'MM')</pre> <p>and call it orderMonth. The new column will list the month number of order date (i.e. 01 for January, 02 for February, etc.)</p>

Aggregate Values of All Rows

You can get the aggregate of a column based on all rows of data to use in a calculation. An example use case of this would be calculating the percentage of one product's inventory to all products. All aggregate functions start with agg_.

Table 13 • Aggregate Values of All Rows

Item	Description
Function	agg_
Syntax	agg_sum(value)
Example	<p>quantityInStock is a number data type and we need to calculate the percentage of each product's quantity to the entire inventory of products. We can create a new formula as:</p> <pre>[quantityInStock]*100/agg_sum([quantityInStock])</pre> <p>and call it quantityPercent.</p>

Concatenating Text Columns

The simple + sign can be used to stitch strings of text together. An example would be creating full name from first and last name columns.

Table 14 - Concatenating Text Columns

Item	Description
Function	+
Syntax	value1 + value2 + value3...
Example	<p>contactFirstName and contactLastName are text type columns and we want to concatenate these together for searches with the last name at the beginning to facilitate sorting. We can create a new formula as:</p> <pre>[contactLastName]+' , '+ [contactFirstName]</pre> <p>and call it contactName. The returned result for a contact with first name 'John' and last name 'Doe' will be 'Doe, John'.</p>

Using an “if” Statement

You can use “if” and other scripting functions to create more sophisticated formulas. For example, suppose you want to create a formula that determines whether your shipping department shipped customer orders within three days. To do this, you would create an if statement that compares two columns in your ERP system, orderDate and shippedDate. If the order was shipped within three days, it returns the word, “fast”. If not, it returns, “slow”. In the example below, notice that the isNull() statement is used to provide some error-handling by changing a null value into a date value (now).

Table 15 - Using an “if” Statement

Item	Description
Function	if
Syntax	if (condition) {return result1;} else {return result2;}
Example	<p>orderDate and shippedDate are date type columns that contain order and shipping dates in an ERP system. We want to decide in which cases our shipping department did a good job and for which orders it reacted too slow.</p>
Function Example	<pre>if(dateDiff([orderDate],isNull([shippedDate],now()),'DAYS')<=3) {return 'fast';} else {return 'slow';}</pre> <p>First, make sure that _null_ values of shippedDate are replaced with a datavalue (now) and then run a comparison to get the result fast when shipping happened within three days of taking the order and slow in all other cases.</p>



Note - When using the action commands to add functions and columns to the formula dialog (rather than typing it in) pay attention to the position of your cursor. Functions are added within parentheses and unless you move your cursor inside the parentheses before adding columns or typing, you may create a syntax error in your formula. Make sure you test your formula before saving it.

Data Engine Syntax

This section describes formula syntax when using Data Engine Syntax mode.

- **Fields/Columns**—Use [] around the field or column name. For example:
[Sales]
- **Functions**—Function names must be in lowercase and must be followed by a bracketed argument list. For example:
sum([Items]) or avg([Temp])
- **Operators**—The following table shows the available operators. Note that normal operator precedence applies.

Table 16 - Available Operators

Symbol	Operation	Description
.	Apply	Apply the function following the dot to the string/text value before the dot.
*	Multiplication	Multiplication of two numbers.
/	Division	Division of two numbers.
+	Addition	Addition of two numbers.
-	Subtraction	Subtraction of two numbers, or negation of a number.
==	Equality	Test equality of two values.
>	Greater Than	Test if the first value is greater than the second value.
<	Less Than	Test if the first value is less than the second value.
>=	Greater Than or Equal	Test if the first value is greater than or equal to the second value.
<=	Less Than or Equal	Test if the first value is less than or equal to the second value.
!=	Inequality	Test inequality of two values.
^	Exclusive Or	Bitwise exclusive or (XOR) of two values.

Table 16 - Available Operators

Symbol	Operation	Description
AND	And	Logical and of two values.
OR	Or	Logical or of two values.
NOT	Not	Logical not of a value.
()	Evaluate Expression	Evaluate the bracketed expression before applying operators to it.

Functions Supported in Data Engine Syntax

Data Engine Syntax mode supports the following functions:

Numeric Functions

Formula Mode supports the Elasticsearch Math API (see [Elasticsearch Math API reference](#)).

Text Functions

Formula Mode supports the Elasticsearch Text API (see [Elasticsearch Text API reference](#)).

Date Functions

Supported date functions include:

- now
- dateFormat
- dateParse
- dateAdd
- dateSubtract
- dateDiff
- dateIsNull

Using dateFormat to display dates and times

The dateFormat function enables you to determine how to display the date and time. See for example the following function:

```
dateFormat("07/04/2001", "EEE, MMM d, 'yy")
```

The above function returns the following format:

```
Wed, Jul 4, '01
```



Note - You may use single or double quotes around the format string.



Note - All dates are treated as GMT.

The following table lists the formatting arguments:

Table 17 - Date and Time Patterns

Letter	Date or Time Component	Presentation	Examples
G	Era designator	Text	AD
y, Y	Year	Year	1996; 96
M	Month in year	Month	July; Jul; 07
w	Week in year	Number	27
W	Week in month	Number	2
D	Day in year	Number	189
d	Day in month	Number	10
F	Day of week in month	Number	2
E	Day name in week	Text	Tuesday; Tue
e	Day number of week (1 = Monday, ..., 7 = Sunday)	Number	1
a	AM/PM marker	Text	PM
H	Hour in day (0-23)	Number	0
k	Hour in day (1-24)	Number	24
K	Hour in AM/PM (0-11)	Number	0
h	Hour in AM/PM (1-12)	Number	12
m	Minute in hour	Number	30
s	Second in minute	Number	55
S	Millisecond	Number	978
z	Time zone	General time zone	PST; GMT-08:00

Table 17 • Date and Time Patterns

Letter	Date or Time Component	Presentation	Examples
Z	Time zone	RFC 822 time zone	-0800
x	Time zone	iso 8601 time zone	-08; -0800; -08:00

Standardized Syntax Mode

Standardized Syntax Mode enables you to create formulas using a standardized language rather than the Elasticsearch syntax.

This section covers the following topics:

- [Creating a Formula Using Standardized Syntax Mode](#)
- [Testing a Formula in Standardized Syntax](#)
- [Standardized Syntax Reference](#)
- [Supported Functions in Standardized Syntax](#)

Creating a Formula Using Standardized Syntax Mode

You create formulas in Data Engine Syntax mode using the Formula Builder. Any formulas that you create can be used in nested formulas (see [Adding a Nested Formula](#)).

For general information on using the Formula Builder interface, see [The Formula Builder Interface](#).



Task **To create a formula using Standardized Syntax**

1. Open the Formula Builder interface and select **Standardized Syntax**.
2. Enter a name in the **Formula Name** box.
3. To add a function to the formula, type it directly in the editor. A suggestion box is displayed with columns and functions that fit your text. You may also use the following method:
 - a. Under **Insert Functions**, select the function that you want to insert. The description box displays helpful information about the function.



Tip • To only display functions for a specific category, select a category from the dropdown box above **Insert Function**.

- b. Click **Add to Formula**. The formula displays in the **Formula** box.
4. To add a column to the formula, type it directly in the editor. A suggestion box is displayed with columns and functions that fit your text. You may also use the following method:
 - a. Insert the cursor in the desired location in the formula.

- b. Under **Insert Columns**, click on the column that you want to insert. The column displays in the **Formula** box.
5. Continue to add functions and columns until your formula is complete.



Tip - Standardized Syntax Mode provides automatic error detection features. The editor continuously evaluates formulas as you type, and it immediately notifies you of syntax errors as well as incorrect usage of data types. Hover over a highlighted error to display additional details.

6. Before you can use the formula, you should test it with sample data. If your formula uses correct syntax, you may display the **Testing** tab to test your formula. For more information, see the following section, “Testing a Formula in Standardized Syntax.”
7. Click **Save** to save the formula. In Standardized Syntax Mode, the **Save** button is displayed on the **Formula** tab.

Testing a Formula in Standardized Syntax



Task To test your formula in standardized syntax

1. In Standardized Syntax mode, create your formula and click **Testing**. If the formula contains any syntax errors or incorrect usage of data types, the **Testing** tab is not available.



Note - The **Input** box lists all the columns in the formula in JSON format, and it assigns values from the dataset to those columns.

2. In the **Input** box, review the values provided and modify as needed. To obtain a new set of values from the dataset, click **Randomize Data**.



Tip - You can evaluate more than one set of values at a time by editing the JSON and adding another set in the columns.

3. Click **Test Formula**. The output is displayed in the **Output** box. If an error occurs during formula evaluation, click **See Console Output** to display a detailed error response from the database engine.
4. Click **Save**. The formula is ready for use.

Standardized Syntax Reference

This section describes formula syntax when using Standardized Syntax mode.

Field/Column Syntax

Insert columns by using the **Insert Columns** dropdown, by entering the column name, or by selecting them from the **Column/Function** suggestion box. Columns are displayed as pills inside the formula.

Function Syntax

Function names must be in uppercase and must be followed by a bracketed argument list. For example:

```
ABS(25)
```

Comments Syntax

You can add single-line comments to the formula that should start with `//`. For example:

```
// This is a comment
```

Operator Syntax

The following table shows the available operators. Note that normal operator precedence applies.

Table 18 • Available Operators

Symbol	Operation	Description
*	Multiplication	Multiplication of two numbers.
/	Division	Division of two numbers.
+	Addition	Addition of two numbers.
-	Subtraction	Subtraction of two numbers, or negation of a number.
=	Equality	Test equality of two values.
>	Greater Than	Test if the first value is greater than the second value.
<	Less Than	Test if the first value is less than the second value.
>=	Greater Than or Equal	Test if the first value is greater than or equal to the second value.
<=	Less Than or Equal	Test if the first value is less than or equal to the second value.
<>	Inequality	Test inequality of two values.
()	Evaluate Expression	Evaluate the bracketed expression before applying operators to it.

Supported values

Data Types supported:

- **Numbers:** including decimals and negative numbers.
- **Strings:** any sequence of characters between two quotes.
- **Date time values:** strings with any of these formats: "MM/DD/YYYY" or "MM/DD/YYYY HH:MM:SS".

- **Boolean:** true or false values.

Supported Functions in Standardized Syntax

Standardized Syntax mode supports the following functions:

Table 19 - Functions in Standardized Syntax mode

Function name	Type	Description
ABS	Numeric	Returns the absolute value of a number.
AND	Logical	Evaluates different logical tests and returns true if all logical tests are true and false if at least one of the logical tests returns false.
CONCATENATE	String/Text	Joins two or more strings into one string.
DATEADD	Date/Time	Adds a specific date part value to a given date. Date part allows: "Y" years, "M" months, "D" days, "H" hours, "MI" minutes and "S" seconds.
DATESUBTRACT	Date/Time	Subtracts a specific date part value to a given date. Date part allows: "Y" years, "M" months, "D" days, "H" hours, "MI" minutes and "S" seconds.
DATEDIF	Date/Time	Calculates the difference between two dates based on the date part requested. Date part allows: "Y" the number of complete years in the period, "M" the number of complete months in the period, "D" the number of days in the period.
DAY	Date/Time	Returns the day of a date. The day is given as an integer ranging from 1 to 31.
DAYOFWEEK	Date/Time	Returns a number or string representative of the weekday for a given date.
EVEN	Numeric	Returns a number rounded to the next greatest even integer.
EXP	Numeric	Returns Euler's number e raised to the power of a number.
HOURL	Date/Time	Returns the hour of a datetime value. The hour is given as an integer ranging from 0 to 23.
IF	Logical	Performs a logical test and returns a value based on the result. You need to set a value in case the test result is true and one if it is false.
IFS	Logical	Allows different logical tests and returns the values set for the first condition equal to true.
INCLUDE	String/Text	Returns true if a string contains a specified sequence of characters. This function is case sensitive.
ISNULL	Logical	Replaces null values with the specified replacement value.

Table 19 - Functions in Standardized Syntax mode

Function name	Type	Description
LEFT	String/Text	Returns the first character or characters in a text string, based on the number of characters you specify.
LENGTH	String/Text	Returns the length of a string.
LOG	Numeric	Returns the logarithm of a number to the base you specify.
LOWER	String/Text	Converts all the characters in a string to lowercase.
MAX	Numeric	Returns the greater of two or more numeric or datetime values.
MID	String/Text	Returns a specific number of characters from a text string. The resulting substring begins at the specified beginIndex and extends, to the right, the number of characters specified on numChars.
MIN	Numeric	Returns the smaller of two or more numeric or datetime values.
MINUTE	Date/Time	Returns the minute of a datetime value. The minute is given as an integer ranging from 0 to 59.
MONTH	Date/Time	Returns the month of a date. The month is given as an integer ranging from 1 (January) to 12 (December).
ODD	Numeric	Returns a number rounded to the next greatest odd integer.
OR	Logical	Evaluates different logical tests and returns false if all logical tests are false and true if at least one of the logical tests returns true.
POWER	Numeric	Returns the value of the first argument raised to the power of the second argument.
PROPER	String/Text	Capitalizes the first letter in a string and any other letters in the text placed next to any character other than a letter or number. Converts the rest of the letters to lowercase.
RANDOM	Numeric	Returns a positive decimal number between 0 (inclusive) and 1 (exclusive).
REPLACE	String/Text	Looks for a specific sequence of characters inside a string and replaces it with a different sequence of characters. This function is case sensitive.
RIGHT	String/Text	Returns the last character or characters in a text string, based on the number of characters you specify.
ROUND	Numeric	Rounds a number to a specified number of digits.
ROUNDDOWN	Numeric	Rounds a number down to a specified number of digits.

Table 19 - Functions in Standardized Syntax mode

Function name	Type	Description
ROUNDUP	Numeric	Rounds a number up to a specified number of digits.
SECOND	Date/Time	Returns the second of a datetime value. The second is given as an integer ranging from 0 to 59.
SQRT	Numeric	Returns the positive square root of a value.
TRIM	String/Text	Removes all leading and trailing spaces from text.
UPPER	String/Text	Converts all the characters in a string to uppercase.
YEAR	Date/Time	Returns the year of a date. The year is given as an integer ranging from 1900 to 9999.

Adding a Nested Formula

You can create nested formulas (formulas inserted within formulas) by copying and pasting the syntax of one formula into another one or by selecting one of the formula columns the same way you do to insert a regular dataset column into a formula's syntax.



Task

To add a nested formula:

1. In the **Insert Columns** list, locate the formula column you want to insert and add it in the parentheses like you would with any other data column.
2. Add any additional parameters that are needed for the function.
3. Test the formula by clicking the **Test** button.
4. Enter a name in the **Formula Name** field.
5. Click **Save**.

Editing, Duplicating, and Deleting Formulas

Sometimes it is easier to create a new formula by duplicating and editing an existing formula. You edit, duplicate, and delete formulas in the **Formulas** panel.



Task

To edit, duplicate, or delete a formula:

1. On a conditional notification's **Metric** tab, click the **Formulas** icon.

The **Formulas** page opens, which lists all formulas that are available for the dataset on which the current conditional notification is based.

2. Click the three-dot menu to the right of a formula and select the desired option:
 - **Edit**—Allows you to edit the formula and save it.
 - **Duplicate**—Creates a duplicate formula with the same name and a “(Copy)” suffix.
 - **Delete**—Deletes the formula.

Bucketing Data

Bucketing is a powerful feature that allows for the grouping of multiple data points into a single item, called a bucket, to make analysis easier.

- [Creating Buckets](#)
- [Managing Bucketed Columns](#)



Note • Bucketing is not available for all data types.

Creating Buckets


This section explains how to create a bucket, a grouping of multiple data points into a single item.




Task

To create a bucket:

1. Navigate to the **Analyze** tab of your dataset, and look for the bucket icon in the upper-right toolbar.



The **Buckets** dialog box opens.



2. Click the **Add Bucketed Column** button.
3. Once inside the bucket editor, select the column of data you'd like to group into buckets and enter a label for your new (bucketed) column.

4. Select one of the following options:
 - **Basic**—If you choose a numeric column to bucket, you can allow Revenera to manage the buckets by selecting the **Basic** option. Within the **Basic** option, you can have either a variable or fixed number of buckets by using the **Dynamic** or **Fixed** options respectively.
 - **Dynamic**—When you choose **Dynamic**, the current set of buckets will be shown on the right; however, as your data changes, the buckets will be adjusted by Revenera.
 - **Fixed**—If you choose **Fixed** buckets, you can then specify the number of buckets, the minimum range value, and the maximum range value.
 - **Custom**—If you select **Custom** buckets, then the current set of Revenera generated buckets will be shown and you can label, adjust, remove or add buckets as you desire.
5. If you select a text column to bucket, then you can enter a comma delimited list of bucket names and click the **Add Bucket** button to create the buckets.
 - Each bucket name has an associated radio button—use this to select a bucket, and then use the check box next to each distinct text value in the values list on the right panel, to add or remove values from the bucket.
 - There is a search field at the top of the values list to help you find values easily. You can create an **Other** bucket using the **Unassigned Values As “Other”** option.
 - Use the **X** button for a bucket value to remove it, or use the **X** button for a bucket name to delete that bucket.
6. If you select a date column to bucket, then you can begin creating your buckets by clicking **+ Add Custom Bucket**.

< Add Bucketed Column

Column to Bucket

Create Date

New Column Label

+ Add Custom Bucket

Untitled Remove

Bucket Label

Type Label

Condition

Value

Equals

mm/dd/yyyy

Equals

Does not equal

Between

Year

Month + Year

Before


After

Buckets (1)

Untitled

Reset Save

7. For each custom date or numeric bucket you create, you will first give it a label, which will appear on all of your analytics going forward, and then set the condition and values that will place data points into your bucket. Use the **Remove** button on a custom bucket to remove it and use the drag handle to reorder custom buckets.
8. In the screenshot below, we've created buckets for the years 1999, 2000-2010, and 2011-2019. All data points will be grouped into these three buckets if conditions are met, and all outliers will be omitted unless catchall buckets are created. (i.e. year < 1999)



9. Once you are satisfied with your buckets, click **Create** to create them. Once created, your new bucketed data column will be available for analysis throughout the application.

Managing Bucketed Columns

Once you have added bucketed columns, then they will be listed in the **Buckets** modal window.

Each bucketed column has 3 associated icons which allow you to duplicate, edit or delete the column.



Important - Note that when you remove a bucketed column by clicking the **X** button, the bucketed column is removed immediately.

Tokens

Tokens are parameters or variables that act as containers for data. There are three categories of Tokens available: *System*, *Data*, and *User-Defined*. Tokens can be used across different contexts in the Analytics menu.

The following topics are discussed in this section:

- [Types of Tokens](#)
- [Tokens Suggestion Box](#)
- [Token Management](#)
- [System Tokens](#)


Types of Tokens

- **System Tokens**—Standard tokens provided by the system.
- **Data Tokens**—Tokens automatically generated from the rows/columns within a dataset and used to reference values from the data.
- **User-Defined Tokens**—Tokens created by you in text, numeric, or date format.

Tokens Suggestion Box

The suggestion box is a guide to show which tokens are available. It can be accessed by typing two curly brackets `{{` into the text field where you want to use a token. The tokens that are available for that specific context will be shown on the corresponding dropdown list.


From this box you can also access the **Tokens** modal by clicking **Add/Manage Tokens**.



Token Management

You access the **Tokens** modal by clicking **Add/Manage Tokens** in the suggestions box (see previous topic, [Tokens Suggestion Box](#)).

This view shows the available data and user-defined tokens, grouped into two corresponding tabs. Each token can be given a name, a value, an alias for easy reference, and a description. The **User Defined** tab is where you can create and manage your own tokens.



In the **Data** tab, you'll find automatically generated tokens for each column in your connected datasets. You can add aliases to any or all of these columns as needed.

System Tokens

System tokens cannot be edited and are available throughout your application with self-explanatory names. The list of supported system tokens is as follows:

- {{CURRENT_DATE}}
- {{CURRENT_TIME}}
- {{CURRENT_TIMEZONE}}
- {{CURRENT_MONTH}}
- {{CURRENT_MONTH_NAME}}
- {{CURRENT_MONTH_START}}
- {{CURRENT_MONTH_END}}
- {{LAST_MONTH}}
- {{LAST_MONTH_NAME}}
- {{LAST_MONTH_START}}
- {{LAST_MONTH_END}}
- {{CURRENT_WEEK}}

- {{CURRENT_WEEK_START}}
- {{CURRENT_WEEK_END}}
- {{LAST_WEEK}}
- {{LAST_WEEK_START}}
- {{LAST_WEEK_END}}
- {{CURRENT_QUARTER}}
- {{CURRENT_QUARTER_START}}
- {{CURRENT_QUARTER_END}}
- {{LAST_QUARTER}}
- {{LAST_QUARTER_START}}
- {{LAST_QUARTER_END}}
- {{CURRENT_YEAR}}
- {{CURRENT_YEAR_START}}
- {{LAST_YEAR}}
- {{LAST_YEAR_START}}
- {{LAST_YEAR_END}}
- {{DAY}}
- {{DAY_OF_WEEK}}
- {{DAY_OF_YEAR}}
- {{NOW}}
- {{TODAY}}
- {{TODAY-7}}
- {{TODAY-30}}
- {{TODAY-60}}
- {{TODAY-90}}
- {{TODAY-120}}
- {{TODAY-365}}
- {{YESTERDAY}}
- {{TOMORROW}}

Branding the End-User Portal

Producers can alter the appearance of their End-User Portal to fit their company's branding guidelines. This section discusses different End-User Portal customization approaches and explains how to use them to control how the End-User Portal appears to your company's customers.

Section	Description
About the Standard Branding Approach	Introduces the standard branding options producers can use to customize the appearance of their End-User Portal.
About the Advanced Branding Approach	Discusses the additional branding options available for producers who want greater control of End-User Portal branding.
Overview of Producer-Configurable Branding Options	Describes the End-User Portal configuration settings that are most commonly used for branding.
Changing End-User Portal Settings	Provides basic instructions for specifying configuration settings in the Producer Portal to control the appearance of the End-User Portal.
End-User Portal Page Structure	Includes graphics to illustrate the structure of End-User Portal pages.

About the Standard Branding Approach

The standard approach allows a producer to apply their account's branding to the End-User Portal without the need for HTML or CSS knowledge. Some of the changes a Producer Portal administrator can apply include

- Inserting your account's logo
- Choosing the page-position of the End-User Portal's primary navigation (top, left, or right)
- Setting the color for body text
- Setting the color for heading text

- Setting the color for anchor text (links)
- Setting primary color for buttons

For many producers, these configuration settings suffice to ensure your End-User Portal shows continuity with your account's branding guidelines. For greater control over the End-User Portal appearance, Producer Portal administrators can take advantage of more advanced branding capabilities.

About the Advanced Branding Approach

The advanced approach allows for a high degree of customization. With enough effort, most producers can mirror the appearance of their account's other online properties. Taking advantage of these advanced branding capabilities requires HTML and CSS skills to achieve the desired result, whether those skills come from your account's personnel or a Revenera services engagement.

The advanced branding approach leverages all the standard branding options, plus the ability to

- Replace header/footer with branded HTML content
- Inject custom CSS

For more details about available system configuration settings related to End-User Portal appearance and behavior as well as page structure guidelines, see the next section, [End-User Portal Page Structure](#).

Overview of Producer-Configurable Branding Options

Producer Portal administrators can access these End-User Portal configuration features via the **System** menu. (In the Producer Portal, click **System** > **Configure** > **End-User Portal Setup**.) From a branding perspective, there are a few key options to work with. They are broken down by section below.

- [Branding-Specific Settings](#)
- [Sample CSS, Header, and Footer Files](#)
- [General Navigation Settings](#)

Branding-Specific Settings

The configuration settings for the End-User Portal that exclusively support branding of the portal are collected into a group called **Custom Branding**.

Table 9-1 ▪ End-User Portal: Custom Branding Configurations

Name	Possible Values	Description
Upload Company Logo	Specify	<p>Choose an image file (PNG or JPG format) to serve as your account's logo in the End-User Portal and upload it. Use the controls to choose a file from your local machine to upload.</p> <p>After an image file is uploaded, a reset button is available to enable you to clear the uploaded image.</p> <p>Maximum file size: 40KB</p> <p>Recommended image height: 30 pixels</p>

Table 9-1 ▪ End-User Portal: Custom Branding Configurations

Name	Possible Values	Description
Upload CSS	Specify	<p>Choose a CSS file to override any of the style settings used by default for the End-User Portal. This custom CSS file only needs to include CSS styles for those you want to override.</p> <hr/> <p>Note ▪ <i>Uploading a customized CSS file allows for a broader range of style changes consolidated into a single place. For smaller changes such as changing the colors used in the End User Portal, it may be simpler to use the Configurator, as described in Configure Portal Colors.</i></p> <p>Use the controls to choose a CSS file from your local machine to upload.</p> <hr/> <p>Note ▪ <i>When no custom CSS file is present, the End-User Portal uses its default CSS.</i></p> <p>Viewing Previously Uploaded CSS File</p> <p>If a custom CSS file has previously been uploaded, a Last Update date will be listed. To view the contents of this file, enter the following URL:</p> <p><code>https://<siteID>.flexnetoperations.com/flexnet/staticfiles/operationsportal/custom.css</code></p> <hr/> <p>Note ▪ <i>When you upload a CSS file to the Upload CSS field, it will overwrite any existing custom CSS file that was previously uploaded. Also, when you upload a custom CSS file, it will always be renamed to <code>custom.css</code>, even if that was not its original name.</i></p> <hr/> <p>Note ▪ <i>For an example of a custom CSS file, see Sample CSS, Header, and Footer Files.</i></p>

Table 9-1 ▪ End-User Portal: Custom Branding Configurations




Name	Possible Values	Description
Upload Header	Specify	<p>Choose an HTML file to replace the default header content for the End-User Portal.</p> <p>Use the controls to choose a file from your local machine to upload.</p>  <hr/> <p>Note ▪ When no custom header HTML is present, the End-User Portal uses its default header content.</p> <p>Viewing Previously Uploaded Header File</p> <p>If a custom header file has previously been uploaded, a Last Update date will be listed. To view the contents of this file, enter the following URL:</p> <p><code>https://<siteID>.flexnetoperations.com/flexnet/staticfiles/operationsportal/header.html</code></p>  <hr/> <p>Note ▪ When you upload a header file to the Upload Header field, it will overwrite any existing custom header file that was previously uploaded. Also, when you upload a custom header file, it will always be renamed to <code>header.html</code>, even if that was not its original name.</p>  <hr/> <p>Note ▪ For an example of a header file, see Sample CSS, Header, and Footer Files.</p>

Table 9-1 ▪ End-User Portal: Custom Branding Configurations




Name	Possible Values	Description
Upload Footer	Specify	<p>Choose an HTML file to replace the default footer content for the End-User Portal.</p> <p>Use the controls to choose a file from your local machine to upload.</p>  <hr/> <p>Note ▪ When no custom footer HTML is present, the End-User Portal uses its default footer content.</p> <p>Viewing Previously Uploaded Footer File</p> <p>If a custom footer file has previously been uploaded, a Last Update date will be listed. To view the contents of this file, enter the following URL:</p> <p><code>https://<siteID>.flexnetoperations.com/flexnet/staticfiles/operationsportal/footer.html</code></p>  <hr/> <p>Note ▪ When you upload a footer file to the Upload Footer field, it will overwrite any existing custom footer file that was previously uploaded. Also, when you upload a custom footer file, it will always be renamed to <code>footer.html</code>, even if that was not its original name.</p>  <hr/> <p>Note ▪ For an example of a footer file, see Sample CSS, Header, and Footer Files.</p>
Primary Navigation Position	Top, Left, or Right	<p>Specify where to show the high-level navigation menu for the End-User Portal.</p> <p>Default: Top.</p>

Table 9-1 ■ End-User Portal: Custom Branding Configurations

Name	Possible Values	Description
Configure Portal Colors	Color in hexadecimal format	<p>Click Open Configurator to show the Color Configurator panel. The Color Configurator allows you to set the colors to use in your End-User Portal pages for the following content:</p> <ul style="list-style-type: none"> ● Default button label color ● Default button color ● Background color ● Title color ● Link color ● Primary navigation ● Primary navigation open ● Primary navigation text <p>Specify all colors using hexadecimal format. For example, #000000 for black, #ffffff for white, or #228B22 for forest green.</p> <p>The content that you can customize in the Color Configurator is described in more detail in the remaining rows in this table.</p> <p>Click Preview to show a sample of your color settings within the Color Configurator.</p> <p>Click Undo to revert any changes that have not yet been saved.</p> <p>Click Use Defaults to restore color settings to the FlexNet Operations default colors.</p> <p>Click Save to store your changes to these color settings.</p>
Default Button Label Color	Color in hexadecimal format	<p>Change the color of default button label in the End-User Portal. This option is set within the Color Configurator.</p> <p>Use a color that ensures enough contrast with default button color. White (#FFFFFF) or black (#000000) are usually safe alternatives. (Hex values accepted.)</p>
Default Button Color	Color in hexadecimal format	<p>Change the color of default action buttons in the End-User Portal. This option is set within the Color Configurator.</p> <p>Buttons generally represent page-level commands—Save, Submit, Activate, for example. (Hex values accepted.)</p>
Background Color	Color in hexadecimal format	<p>Change the background color of pages in the End-User Portal. This option is set within the Color Configurator.</p> <p>This setting is applied to the <body/> element of every page. (Hex values accepted.)</p>

Table 9-1 ▪ End-User Portal: Custom Branding Configurations

Name	Possible Values	Description
Title Color	Color in hexadecimal format	Change the color of page headings and sub-headings in the End-User Portal. This option is set within the Color Configurator . (Hex values accepted.)
Link Color	Color in hexadecimal format	Change the color of text links (anchors) in the End-User Portal. This option is set within the Color Configurator . (Hex values accepted.)
Primary Navigation	Color in hexadecimal format	Change the background color the primary navigation menus in the End-User Portal. This option is set within the Color Configurator . (Hex values accepted.)
Primary Navigation Open	Color in hexadecimal format	Change the background color open (active) primary navigation menus in the End-User Portal. This option is set within the Color Configurator . (Hex values accepted.)
Primary Navigation Text	Color in hexadecimal format	Change the color of all text in the End-User Portal's primary navigation menus. This option is set within the Color Configurator . (Hex values accepted.)

Sample CSS, Header, and Footer Files

To help you create a custom CSS, header, or footer file, examples are provided.

- [Sample Custom CSS File](#)
- [Sample Header File](#)
- [Sample Footer File](#)

Sample Custom CSS File

You can create a custom CSS file to override any of the style settings used by default for the End-User Portal. You can also add classes to the custom CSS file to format a custom header or footer, should you want to use those.

The custom CSS file only needs to include CSS classes for those you want to override and for any classes you use in a custom header or footer.

CSS for Custom Header and Footer

The following is an example of CSS classes that could be added to format a custom header and footer (as described in [Sample Header File](#) and [Sample Footer File](#)):

```
div.myheader {
  background-color: #FFFFFF;
  width: 100%;
  height: 75px;
  padding: 0;
}

div.myfooter {
  width: 100%;
  height: 75px;
  display: flex;
  align-items: center;
  font-family: Calibri;
  padding-left: 12px;
  border-top: 1px solid #969696;
  border-bottom: 1px solid #969696;
  background-color: #f5f5f5;
}

div.myfooter .mysupport {
  font-family: Calibri;
  font-size: 16px;
}
```

CSS to Override Default Class

You may want to override a default style used in the End-User Portal, such as the appearance of the widgets on the Home page.




Figure 9-1: Default appearance of Your Downloads widget on Home page

If you wanted, for example, to make the heading of this widget bold and change the background color, your first step would be to determine what CSS is currently being applied to that element on the page. To do this, you would use your browser's Inspect tool. Then you would add classes to the custom CSS file corresponding to those classes.



Important - Adding a custom CSS to your End-User Portal site could have site-wide consequences. Therefore, only users with advanced CSS knowledge should attempt to override the default CSS classes.



Note - The following instructions are for the Chrome browser, but other browsers have similar functionality.



Task To identify existing CSS classes and overriding them in a custom CSS file

1. In the End-User Portal, put your cursor on the area of the screen that you want to change, right-click and then select **Inspect** from the context menu. The Inspect panel opens on the right side of the screen, displaying the underlying HTML code:



2. Identify the HTML code that is applicable to the element you want to change. In this example, the widget itself is defined by the following div tag:

```
<div class="widget-col-2 widget-card">
```

The title of the widget is defined by this element:

```
<h4>Your Downloads</h4>
```


3. Enter CSS overrides into a custom.css file that makes the changes that you want to see. To change the background color of all widgets on the Home page, enter something like this:

```
.widget-card {
    background-color: #ADD8E6!important;
}
```

To change the font weight of the title of all of the widgets on the Home page, enter something like this:

```
.widget-card h4 {
    font-weight: 700!important;
}
```

4. Upload the custom CSS file. The Home page widgets should now look like this:



5. The final step is to test your entire site to see if these changes have resulted in any unwanted results. If you find that these changes have been applied to areas of the site that you did not intend, you have to change the CSS classes in the custom CSS file to be more specific to exactly what you wanted to change.

Sample Header File

The default header for the End-User Portal includes the FlexNet Operations logo with a green bar above it;



Figure 9-2: Default Header

The header also includes the name of the logged-in user and a dropdown menu that enables the user to open the **User Profile** page and to **Logout**:




Figure 9-3: User Name and Profile/Logout menu

If all you wanted to do was to change the logo, you could choose to use the [Upload Company Logo](#) control. To change the color of the green bar, you could use the [Configure Portal Colors](#) control.

However, if you wanted to, for example, remove the green bar and add a background image to the header that used your company's branding, you could create a custom header file similar to this:

```
<div class="myheader">
  
</div>
```

The resulting header would look something like this:




Figure 9-4: Custom header with **Profile/Logout** menu in new location

Note that when you upload a custom header file (as in the example header.html file), the name of the logged-in user and its associated dropdown menu is automatically moved down on the page, outside of the header area.

Sample Footer File

The default footer for the End-User Portal includes the copyright information inside a gray box:




Figure 9-5: Default footer

However, if you wanted to, for example, change the background color of the footer and add a link to an internal Support site, you could create a custom footer file:

```
<div class="myfooter">
  <p class="mysupport"><strong>Technical Support</strong>:
    <a href="mailto:support@mycompany.com">support@mycompany.com</a> | 800-555-5555</p>
</div>
```

The resulting footer would look similar to this:



Figure 9-6: Custom footer

You will notice that the text in your custom footer replaces the copyright information that previously appeared.

General Navigation Settings

Many End-User Portal configuration settings control the appearance or behavior of the portal without being branding-specific. Often these settings correspond to the functionality your account wants to provide in its End-User Portal.

The following settings pertaining to navigation can be specified in the **Portal Navigation** section of the **End-User Portal Setup** page in **System > Configure**. However, this is only a subset of available options. For a complete list of navigation settings, refer to [Portal Navigation](#) under [Configuring End-User Portal Settings](#).

Table 9-2 ▪ Non-branding-specific configuration settings

Option	Description
Hide Top-level Navigation	Select to hide the top-level navigation portal-wide. Use this option with caution; hiding the primary navigation restricts access to all but the initial landing page. This may be appropriate for some embedded implementations—for example, included via an iframe in another application page.
Hide Header	Select to hide header on each page. The header is the area above the primary navigation. This setting is useful when the End-User Portal is to be embedded in your own online property. When configured this way, the End-User Portal shows the user menu and system help in the main content area.

Changing End-User Portal Settings

Whether producers use a standard or advanced branding approach, their choices are stored in the Producer Portal's End-User Portal-related system configuration settings. These settings apply resources, like your account's graphics and style sheets, combined with your design choices to govern the appearance of your account's End-User Portal.

Follow the instructions, below, to configure the End-User Portal.



Important ▪ A user must be assigned a role with the **View and Manage Configurations** permission to modify configuration settings for the End-User Portal through the Producer Portal.



Tip ▪ Before changing any configuration settings in a working FlexNet Operations instance, it is advisable to export the working configuration settings. If there is a problem with the new settings, you have a backup of working settings to restore.



Task To configure the End-User Portal

1. In the Producer Portal, click **System > Configure**.
2. Click **End-User Portal Setup** to open the configuration page for the End-User Portal.

Initially, the **General Options** group is expanded. Click on the name of a group to expand the settings list for that group. For example, click **Custom Branding** to show all branding-specific system configuration settings for the End-User Portal.



Note - The settings in the **Custom Branding** group apply expressly to branding. However, other settings also have an impact on the appearance of portal to your end users. (Many of these non-branding-specific settings pertain more to the behavior and included functionality rather than branding.)

3. Make any setting changes that suit your configuration needs.

Refer to the following sections for additional information:

- For administrators performing standard branding pertaining to the End-User Portal's appearance, refer to [Branding-Specific Settings](#).
- For administrators performing advanced branding, also review the [End-User Portal Page Structure](#) section.
- For administrators performing extensive branding that also encompasses changing the menus and functionality available in the End-User Portal, consult the system configuration setting tables in [Configuring End-User Portal Settings](#).

4. Click **Save Configs** to save changes.

The Producer Portal saves your configuration changes.


End-User Portal Page Structure

The following graphics illustrate the general page structure as well as specific page structure for scenarios where a custom header and footer have been applied and also where a custom header and footer have been applied with navigation left-aligned.

- [General Page Structure](#)
- [Page Structure with Custom Header and Footer](#)
- [Page Structure with Custom Header and Footer, and Navigation Aligned Left](#)


General Page Structure

The following is a graphic illustrating the general page structure of an End-User Portal page.




Page Structure with Custom Header and Footer

The following graphics illustrate a specific page structure for a scenario where a custom header and footer have been applied.



Page Structure with Custom Header and Footer, and Navigation Aligned Left

The following graphics illustrate a specific page structure for a scenario where a custom header and footer have been applied with navigation left-aligned.



Part 2

Getting Started

This part of the FlexNet Operations User Guide includes the following sections:

- [Getting Started with FlexNet Embedded Licensing](#)
- [Getting Started with FlexNet Publisher Trusted Storage-Based Licensing](#)
- [Getting Started with FlexNet Publisher License File-Based Licensing](#)
- [Getting Started with Non-FlexNet Licensing Technologies](#)
- [Getting Started with Cloud Licensing Service](#)
- [Getting Started with Entitlement Management](#)
- [Getting Started with Electronic Software Delivery](#)
- [Getting Started with Usage Management](#)
- [Getting Started with Updates and Insights](#)
- [Getting Started with FlexNet Customer Growth](#)
- [Getting Started with Advanced Organization Management](#)

Getting Started with FlexNet Embedded Licensing

This section *Getting Started with FlexNet Embedded Licensing* presents fundamental FlexNet Operations concepts and uses exercises to guide you through basic FlexNet Embedded licensing setup, and creation of FlexNet Embedded devices. The intended audience for this getting started section is the first-time Producer Portal user, or one without FlexNet Operations training or experience. This getting started section is organized into the following topics.

Topic	Content
Introduction	Overview of this getting started section, exercise prerequisites, summary of the FlexNet Operations license lifecycle, and FlexNet Operations embedded licensing concepts.
Setup	FlexNet Operations publisher and product concepts and exercises that demonstrate how to set up a publisher account and products, then entitle a customer to those products. Brief descriptions of advanced topics with references for more information.
Devices	FlexNet Operations embedded device concepts and exercises that demonstrate how to create FlexNet Embedded standalone devices and generate pre-installed product licenses for them. End-User Portal exercises that demonstrate how to map an entitlement to a device; claim a device and map an entitlement to it; then automatically create a device, claim it for a customer account, and activate its licenses. Brief descriptions of advanced topics with references for more information.
License Servers	FlexNet Operations embedded license server concepts, and exercises that demonstrate how to create a FlexNet Embedded license server and map an entitlement to it. Brief descriptions of advanced topics with references for more information.

To view a brief, informative video that walks you through the exercises in the *Getting Started with FlexNet Embedded Licensing*, click [here](#). We recommend that you read this getting started section in full, to gain an understanding of the concepts it covers, before you view the video.

Introduction

This section lists the exercise prerequisites, a summary of the FlexNet Operations license lifecycle, and FlexNet Operations embedded licensing concepts.

- [Exercise Prerequisites](#)
- [The License Lifecycle: FlexNet Embedded](#)
- [FlexNet Embedded Licensing Key Concepts](#)
- [FlexNet Embedded Licensing: Advanced Topics](#)

Exercise Prerequisites

Before you begin the exercises in this getting started section:

- Demonstration data must be loaded in your environment.



Important - Contact *Reverera Support* if demonstration data is not loaded.

- You must have access to the FlexNet Operations Advanced Lifecycle Management module.
- The FlexNet Embedded SDK must be properly installed and configured.
- The FlexNet Operations email templates must be set up (verify that the Entitlement Certificate email template is set to active).
- You must have a FlexNet Operations Producer Portal login and a System Administrator role.
- You must complete the exercises in the section [Getting Started with Entitlement Management](#).

The License Lifecycle: FlexNet Embedded

The FlexNet Operations license lifecycle is a repeating process of producer and customer activities, as depicted in the figure and described below.



Figure 10-1: FlexNet Operations License Lifecycle

The delivery/installation and activation stages of the FlexNet Embedded license lifecycle are covered in this getting started section.

- **Create Products** – Create product definitions that are used to generate licenses.
- **Order/Entitle** – Define an customer’s rights to obtain licenses for your products.
- **Deliver/Install** – Deliver the application software to the customer and install that software.
- **Activate** – Deliver licenses to the customer.
- **Return/Rehost** – Manage license transfers from one user or system to another.
- **Maintain/Update** – Deliver software and license updates to the customer.
- **Upsell/Renew** – Renew customer licenses, or sell the customer additional product functionality.

FlexNet Embedded Licensing Key Concepts

FlexNet Embedded Licensing

Software on a device controls the product feature set expressed on that particular device. If the device has Internet connectivity, it can connect directly to FlexNet Operations and receive the license for its particular product feature set. A device can also be activated offline or using a FlexNet Embedded license server.

FlexNet Embedded license technology can also be integrated with a producer's software to make it capable of enforcing perpetual, subscription, or demo software license models.

FlexNet Embedded licenses are of two types:

- An *uncounted* license allows a customer to deploy an unlimited number of licenses.
- A *counted* license restricts deployment to a limited number of licenses. The count is specified during the entitlement process.

Linking multiple license models to a single product is permitted. If multiple license models are linked to a product, it must be specified, when an entitlement line is created, which license model applies to the entitlement line. If only a single license model is linked to a product, then it is used by default.

FlexNet Embedded SDK

To use FlexNet Embedded, FlexNet Operations works in conjunction with the FlexNet Embedded SDK, a licensing library. Before you continue, ensure that you have access to the following:

- FlexNet Operations Producer Portal
- FlexNet Embedded SDK

Installing and Configuring the FlexNet Embedded SDK

Install and configure the FlexNet Embedded SDK as explained in your FlexNet Embedded documentation. Consult the user guide and getting started guide for your FlexNet Embedded SDK. For example, if you are using the FlexNet Embedded C SDK, consult the *FlexNet Embedded C SDK Getting Started Guide* and the *FlexNet Embedded C SDK User Guide*.

Building Product Binaries

Using the FlexNet Embedded SDK, your development team must create Flex-enabled product binaries that are able to take advantage of the FlexNet licensing technology. Some sample license-enabled code is included in your FlexNet Embedded SDK. Consult the user guide for your FlexNet Embedded SDK for details.

Configuring the Device Servlet

The device request servlet handles incoming binary HTTP requests (capability requests) from FlexNet Embedded devices. The servlet URL is `http://<fnoServer>:<httpPort>/flexnet/deviceservices/`. This URL must be accessible to networked devices to obtain their licenses from FlexNet Operations. Your development team must configure the connection method using the device servlet.

Using the Capability Request Command Line Utility

The `caprequestutil` capability request utility, located in `<FlexNet_Embedded_install_dir>\bin\tools`, enables you to manually generate a capability request and save it as a file or send it to a back office server. This utility is intended for quick testing involving capability requests. It is implemented using Java, and uses a text file as a substitute for trusted storage. This command line utility works for all platforms.

Embedded Activation

A FlexNet Embedded entitlement can be activated online or offline.

- **Online activation** – The Flex-enabled application generates a capability request for entitled features, then sends the request to FlexNet Operations via the Internet. FlexNet Operations sends a capability response to the device, which processes the response and places the license into trusted storage.
- **Offline activation** – The Flex-enabled application generates a capability request file, which is manually transferred to a connected system from which it can be uploaded to FlexNet Operations. The capability response is downloaded from FlexNet Operations and transferred to the Flex-enabled application for processing.

Embedded License Support

The license lifecycle extends beyond activation; support is also an important part of the lifecycle. Embedded licenses can easily be added, deleted, or re-allocated in response to customer demands, maintenance, or market conditions.

Next Steps


This topic introduced fundamental FlexNet Operations Embedded licensing concepts. In the next topic, you are introduced to FlexNet Embedded licensing setup.

FlexNet Embedded Licensing: Advanced Topics

For more information about this topic, refer to [Administering License Models](#).

License Formats

FlexNet Embedded supports different ways of representing license rights on a system. A producer can create customized license models by combining the two different ways to store licenses:



- **Trusted Storage:** License rights can be fulfilled or upgraded by a back office server, either online or offline. This type of license is kept in trusted storage, a secure location bound to a particular device, and which supports verifiable returns to the back office server and subsequent transfer to a different device.
- **Binary License:** License can be stored as an array of bytes, either imported by license-enabled code during execution or compiled into the executable code. This type of license is typically locked to a particular device, and may contain an expiration date.

When a device model is created in FlexNet Operations, one of three license formats must be selected:

- **Pre-installed license in file, additional licenses in trusted storage:** The pre-installed license is stored in a binary file, and additional licenses are stored in trusted storage.

- **Pre-installed license and additional licenses in file:** The pre-installed license and additional licenses are stored in a binary file.
- **Pre-installed license and additional licenses in trusted storage:** The pre-installed license and additional licenses are stored in trusted storage.

Setup

This topic introduces FlexNet Embedded licensing and its setup. Setup tasks include adding a publisher and publisher identity; deploying the Embedded Counted license model; adding product features, a product, and deploying the product; and entitling the customer account to the product. For more information, refer to [Administering License Models](#).

The exercises in this topic guide you through the basic FlexNet Embedded licensing setup work flow.

- [Setup: Key Concepts](#)
- [Setup: Exercises](#)
- [Setup: Next Steps](#)
- [Setup: Advanced Topics](#)

Setup: Key Concepts

Publishers and Publisher Identities

Before FlexNet Embedded can be used, a publisher and identity must be set up on the FlexNet Operations Producer Portal. A publisher identity is binary data that contains a publisher or producer name and encryption data. The publisher owns the license and validates it; the identity secures communication between the back office and the device.

Reverera supplies each publisher with a unique name and a series of five publisher keys. The keys cannot be regenerated or duplicated.

The publisher can create any number of identities, each providing a different level of security for different classes of devices or licenses. For example, a line of high-end devices may require higher security than a line of low-end devices. When an identity is created, a digital signature algorithm is selected to prevent forgery and tampering on the device.

Products and Features

Products—hardware or software—are packages of features that can be sold by a producer. A feature is a software functionality or set of functionalities. Feature definitions are created in the FlexNet Operations Producer Portal that correspond to product features defined in the code. For more information about products and features, refer to [Getting Started with Entitlement Management](#).

Entitling a Customer Account

You entitle a customer account to a product linked to one or more FlexNet Embedded license models, then you license the product. For more information about entitlements, refer to [Getting Started with Entitlement Management](#).

Setup: Exercises

These exercises use examples to guide you through the following FlexNet Embedded setup tasks:

Exercise	Description
Adding a Publisher and a Publisher Identity	Add publisher demo and publisher identity ABCNetworks.
Deploy the Embedded Counted License Model	Deploy the FlexNet Licensing technology's Embedded Counted license model.
Adding Product Features	Add product features SimultaneousUsers, Encryption_Throughput, and Redundancy.
Adding a Product	Add the VPN5050 and 10MbpsVPN5000 additional encryption throughput products and link them to the Embedded Counted license model.
Deploying a Product	Deploy the VPN5050 and 10MbpsVPN5000 products.
Entitling a Customer Account to a Product	Entitle the Barry Photography Studio customer account to the VPN5050 and 10MbpsVPN5000 products.

Adding a Publisher and a Publisher Identity

In this exercise, you add publisher demo and publisher identity ABCNetworks.



Task

To add the demo publisher

1. Log in to the FlexNet Operations Producer Portal. The **Producer Portal Home** page appears.
2. Click **Administer > Publishers**. The **List Publishers** page appears.
3. Click **Create Publisher**. The **Create A Publisher** page appears.
4. In the **Publisher Name** field, type `demo`
5. In the **Notes** field, type `FlexNet Embedded Demo Publisher`.
6. In the **Publisher Keys** fields, type `0x9ddcd080 0x99aa8309 0x33995896 0x271213a5 0x0b165dcb` and click **Save**. The **Create Identity** page appears with this message: The publisher was created successfully.



Task

To add the ABCNetworks identity to the demo publisher

1. On the **Create Identity** page, enter the publisher identity's attributes:
 - **Identity Name:** Type `ABCNetworks`
 - **Signature Algorithm:** Select any algorithm



Note - The **Custom IdentityBackOffice.bin** field is not mandatory. For this exercise, leave it blank.

2. Click **Save**. The **List Identities** page appears with publisher identity name ABCNetworks and the message The identity was created successfully.

Deploy the Embedded Counted License Model

In this exercise, you deploy the FlexNet Licensing technology's Embedded Counted license model. You deployed FlexNet Licensing and the Nodelocked Uncounted license model in section [Getting Started with Entitlement Management](#). The Embedded Counted license model deployment procedure is similar to the one you performed for Nodelocked Uncounted.



Note - If the Embedded Counted license model is already deployed in your FlexNet Operations instance, you can skip this task and continue with [To add the Encryption_Throughput, SimultaneousUsers, and Redundancy features](#).



Task **To deploy the Embedded Counted license model**

1. In the Producer Portal, click **Administer > License Models**. The **Package Products – License Models** page appears.
2. Search for and select the **Embedded Counted** license model, click **Change State ?**, then select **Deploy** from the menu.
3. Click **OK** in the verification message. This message appears: Deployed the following License Model(s) successfully: Embedded Counted. In the **License Models** table, **Embedded Counted** has a state of deployed.

Adding Product Features

In this exercise, you add product features SimultaneousUsers, Encryption_Throughput, and Redundancy. Features SimultaneousUsers and Encryption_Throughput are counted, and feature Redundancy is uncounted (enabled or disabled).



Task **To add the Encryption_Throughput, SimultaneousUsers, and Redundancy features**

1. In the Producer Portal, click **Products > Features**. The **Package Products** page appears.
2. Click **Add New Feature**.
3. Under **Create A Feature**, enter the first feature's attributes:
 - **Feature Name:** Type Encryption_Throughput
 - **Version:** Type 1.0
 - **Description:** Type Encryption throughput in Mbps

4. Click **Add New Feature**. The first feature is saved and this message appears: Feature Encryption_Throughput successfully added.
5. Under **Create a Feature**, enter the second feature's attributes:
 - **Feature Name:** Type SimultaneousUsers
 - **Version:** Type 1.0
 - **Description:** Type Number of simultaneous users
6. Click **Add New Feature**. The second feature is saved and this message appears: Feature SimultaneousUsers successfully added.
7. Under **Create a Feature**, enter the third feature's attributes:
 - **Feature Name:** Type Redundancy
 - **Version:** Type 1.0
 - **Description:** Type Redundancy
 - Under **Feature Overrides**, from the **Counted** list, select **No** (Redundancy is enabled or disabled)
8. Click **Save**. The third feature is saved and this message appears: Feature Redundancy successfully added. Note that the three new features are listed in the table on the right side of the **Package Products** page.

Adding a Product

In this exercise, you add the VPN5050 and 10MbpsVPN5000 additional encryption throughput products and link them to the Embedded Counted license model. The procedure is similar to the one you used to create PhotoPrint in the section [Getting Started with Entitlement Management](#).



Task To add product ABC VPN 5050

1. In the Producer Portal, click **Products > Products**. The **Package Products** page appears.
2. Click **Add New Product**.
3. Under **Create A Product**, enter the product attributes:
 - **Product Name:** Type VPN5050
 - **Description:** Type ABC VPN 5050 Basic Features
 - **Version:** Type 1.0
 - **License Technology:** Select **FlexNet Licensing**
 - **Can be used on a device:** Select **Yes**
 - **License Generator:** Select **demo**
4. Click **Add Features**. The **Add Features To Product** window opens.
5. In the **Add Features To Product** window, under **Available Features**, search for and select Encryption_Throughput,1.0, SimultaneousUsers,1.0, and Redundancy,1.0.

- Click **Add ?** to move Encryption_Throughput,1.0, SimultaneousUsers,1.0, and Redundancy,1.0 to **Selected Features**, then click **Add**. The features are added to product VPN5050 and the window closes.
- In the feature table, enter a number in the **Quantity** field for each feature:

Feature	Quantity
Encryption_Throughput	5
SimultaneousUsers	5
Redundancy	1

- Click **Next**. Under **Link License Models To Product**, click **Link License Models**. The **Select License Models** window opens.
- Under **Available License Models**, select **Embedded Counted** then click **Add ?** to move it to **Selected License Models**.
- Click **Add** to add the license model and close the window. On the **Package Products** page, the **Embedded Counted** license model is shown.
- Click **Save** to save the product. This message appears: License models linked successfully. Note that the new VPN5050 product is listed in the table on the right side of the **Package Products** page.



Task *To add product ABC VPN 5000 Encryption Throughput (10 Mbps)*

- On the **Package Products** page, click **Add New Product**.
- Under **Create A Product**, enter the product attributes:
 - Product Name:** Type 10MbpsVPN5000
 - Description:** Type ABC VPN 5000 Encryption Throughput (10 Mbps)
 - Version:** Type 1.0
 - License Technology:** Select **FlexNet Licensing**
 - Can be used on a device:** Select **Yes**
 - License Generator:** Select **demo**
- Click **Add Features**. The **Add Features To Product** window opens.
- In the **Add Features To Product** window, under **Available Features**, search for and select Encryption_Throughput,1.0.
- Click **Add ?** to move Encryption_Throughput,1.0 to **Selected Features**, then click **Add**. The feature is added to product 10MbpsVPN5000 and the window closes.
- In the feature table, on the Encryption_Throughput line, type **10** in the **Quantity** field.
- Click **Next**. Under **Link License Models To Product**, click **Link License Models**. The **Select License Models** window opens.

- Under **Available License Models**, select **Embedded Counted** then click **Add ?** to move it to **Selected License Models**.
- Click **Add** to add the license model and close the window. On the **Package Products** page, the **Embedded Counted** license model is shown.
- Click **Save** to save the product. This message appears: License models linked successfully. Note that the new 10MbpsVPN5000 product is listed in the table on the right side of the **Package Products** page.

Deploying a Product

In this exercise, you deploy the VPN5050 and 10MbpsVPN5000 products. The procedure is similar to the one you used to deploy PhotoPrint in [Getting Started with Entitlement Management](#).



Task To deploy products VPN5050 and 10MbpsVPN5000

- In the Producer Portal, click **Products > Products**. The **Package Products** appears.
- Under **Recently Accessed Products**, search for and select products VPN5050 and 10MbpsVPN5000.
- Click **Change State ?** and select **Deploy** from the menu. Click **OK** in the verification message. Deployment information for the VPN5050 and 10MbpsVPN5000 products is shown under **Deploy Products** and **Following Features Will Also Be Deployed**.
- Click **Deploy**. This message appears: Products deployed successfully.

Entitling a Customer Account to a Product

In this exercise, you entitle the BarryPhoto customer account and customer end user Lisa Barry to the VPN5050 and 10MbpsVPN5000 products. The procedure is similar to the one you used to entitle BarryPhoto to product PhotoPrint in [Getting Started with Entitlement Management](#).



Task To entitle customer account BarryPhoto to product VPN5050

- In the Producer Portal, click **Entitlements > Create**. The **Entitle Customers to Licenses** page appears.
- Under **Create An Entitlement**, on the **Entitlement ID** list, select **Specify** and type ENT-VPN5050 in the field that appears next to it.
- Under **End Customer And Channel Partners**, click **Add**. The **End Customer And Channel Partners | Accounts** window opens.
- On the **Customers** tab under **Accounts**, select Account from the **Search For** menu, search for and select BarryPhoto, then click **Next**. The **End Customer And Channel Partners | Contacts** window opens.
- Under **Contacts**, search for and select Lisa Barry, then click **Save**. The window closes. On the **Entitle Customers to Licenses** page, under **End Customer And Channel Partners**, the end customer's account name, contact, and email address are populated.
- On the **Line Items** tab, click **New Line Item**. The **Configure Line Item** wizard opens. Search for and select the VPN5050 product.

7. At the bottom of the wizard, click **Next** twice to advance to the **Configure Product** step. Enter the VPN5050 line item attributes:
 - **Qty:** Type 5
 - **Start Date:** Select Use First Activation Date
 - **Expiration:** Select Specify Duration, type 1, then select Years
 - Keep the default values for all other attributes.

Click **Save**.

8. On the **Line Items** tab, review the draft VPN5050 line item, then click **Save & Deploy**. The line item is deployed and this message appears: Entitlement deployed successfully.
9. Click the VPN5050 line item's **Activation ID**, review the **Line Item Details** window, then click **Cancel** to close it.
10. At the bottom of the **Entitle Customers to Licenses** page, click **View** and select **View History** from the menu. The **Change History** window opens for the ENT-VPN5050 entitlement.
11. Review the change history of the ENT-VPN5050 entitlement, then click **OK** to close the window.
12. On the **Entitle Customers to Licenses** page, click **Email** to send entitlement notification email to Lisa Barry at Barry Photography Studio. The **Entitle Customers to Licenses** page appears with the customer's address in the **Ship To Email** field.



Note ▪ To include additional recipients, type their email addresses into the **Ship To Email** field separated by commas.

13. Add your email address to the recipients list so you receive a copy of the entitlement email.
14. Click **Send**. The **Entitle Customers to Licenses** page appears with the message Email sent to the recipients <address list>.
15. Review the entitlement notification email you receive.



Task **To entitle customer account BarryPhoto to product 10MbpsVPN5000**

Repeat [Step 1](#) through [Step 15](#) of task [To entitle customer account BarryPhoto to product VPN5050](#) to entitle the customer to a product with these attributes:

- **Entitlement ID:** Type ENT-10MbpsVPN5000
 - **Product:** Type 10MbpsVPN5000
- Line item attributes:
- **Qty:** Type 10
 - **Start Date:** Select Use first activation date
 - **Expiration:** Select Specify duration, type 1, and select Years
 - **Customer:** Select Barry Photo
 - **Contact:** Select Lisa Barry

Log out of the Producer Portal or continue with [Devices](#).

Setup: Next Steps

This topic introduced FlexNet Embedded licensing setup. In the next topic, you are introduced to FlexNet Embedded devices and device management tasks.

Setup: Advanced Topics

Adding a FlexNet Embedded License Model

A FlexNet Embedded license model assigns default parameters for either a pre-installed license that is used for a device model, or licenses for additional products to which a customer account can be entitled. The license model specifies sources for the values of feature record properties in generated licenses. For more information, see [Creating a License Model](#).

Digital Signature Algorithms

The publisher can define any number of identities, each providing a different level of security for different classes of devices or licenses. For example, a line of high-end devices may require higher security than a line of low-end devices.

When an identity is created, a digital signature algorithm is selected to prevent forgery and tampering on the device. FlexNet Operations supports several digital signature algorithms. For more information, see [Creating a Publisher Identity](#).

Devices

This topic introduces FlexNet Embedded standalone devices and typical tasks performed for them. These tasks include creating a device, assigning a device to a customer account, mapping a product entitlement to a device, claiming a device, and activating a device's product licenses.

The exercises in this topic guide you through the basic FlexNet Embedded standalone device work flows.

- [Devices: Key Concepts](#)
- [Devices: Exercises](#)
- [Devices: Next Steps](#)
- [Devices: Advanced Topics](#)

Devices: Key Concepts

Devices

A device is a hardware or software component that uses FlexNet Embedded to license its products. FlexNet Embedded devices connect to FlexNet Operations to manage their ownership, state, features, and more. Examples of devices include high-end medical equipment, routers, and microchip ID scanners.

A device is identified by a device ID and its type. Device types are

- **Standalone Device**—FlexNet Embedded device that connects to FlexNet Operations, which manages the device.
- **Anonymous**—A type of standalone device that connects to FlexNet Operations but that is not assigned to an account. Anonymous devices are typically devices that are sold to a single end user, or those running software that is not licensed.
- **Server**—FlexNet Embedded server that communicates with FlexNet Operations to manage device ownership, state, and features for a collection of served devices. (When a FlexNet Embedded server is used, its served devices connect with the FlexNet Embedded server rather than connecting directly to FlexNet Operations.)
- **Served Device**—FlexNet Embedded device that is managed via a FlexNet Embedded server. In FlexNet Operations, served devices are essentially read-only entities.

Creating a Device

There are many ways to create a device. In the typical scenario, the device is claimed via the activation process in the End-User Portal. In another scenario, the producer creates a device and assigns an owner through the Producer Portal, then the customer accesses the device through their End-User Portal.

Adding Device Features

Applications running on devices use licensed product features to turn access to functionality on or off in the application or device. When a feature is created, it is configured as one of two types: counted or uncounted. This configuration indicates whether the feature is limited to a certain quantity or turns access to the functionality on or off.

An example of a counted feature is number of cell phone minutes you have, and an example of an uncounted feature is whether you have access to text messaging or not.

Pre-Installed Licenses

A device must be created before a pre-installed license can be generated for it. A pre-installed license defines the basic or default features of a device. Pre-installed license generation is a producer activity; a pre-installed license is typically loaded on the device by the producer before shipping.

On the Producer Portal, producer users can download a license response file for a pre-installed license after the pre-installed license is generated.

Additional Products

Additional products are capabilities that can be mapped to a device in addition to the basic, pre-installed product included with the device. Additional products can also be removed from a device.

Product Licenses

A product license grants additional capabilities or capacity for a device or an application. For example, a producer can create a camera with a pre-installed license for the basic product. Later, licenses for more advanced products can be added to the camera to reflect additional capabilities purchased by the customer. An application example is personal computer software with a pre-installed license for system security features. The software can also include product licenses for a system repair tool kit and junk file removal tool that the customer can purchase later.

Product licenses can be generated online (programmatically), or manually on the Producer Portal or End-User Portal. (Additional features on devices that cannot connect directly to FlexNet Operations can be activated via the manual process of offline activation.) A feature license can be generated manually with a request file (offline activation) or without one. A license response file for a feature license can be downloaded after the license is generated.

Devices: Exercises

These exercises use examples to guide you through the following FlexNet Embedded standalone devices tasks:

Exercise	Description
Creating a Device	Create standalone devices ABCVPN5050-1 and ABCVPN5050-2 for account BarryPhoto and generate VPN5050 pre-installed product license files for them.
Mapping an Additional Product Entitlement to a Device	Log in to the End-User Portal and map the 10MbpsVPN5000 product entitlement to device ABCVPN5050-1.
Claiming a Device and Mapping an Additional Product Entitlement	In the End-User Portal, claim device ABCVPN5050-2 and map the 10MbpsVPN5000 product entitlement to it.
Activating a Device's Pre-Installed and Additional Product Licenses	In the End-User Portal, automatically create standalone device ABCVPN5050-3 for customer account BarryPhoto, map the VPN5050 and 10MbpsVPN5000 products to it, and activate the licenses.

Creating a Device

In this exercise, you use the Producer Portal to create standalone devices ABCVPN5050-1 and ABCVPN5050-2 and generate VPN5050 pre-installed product license files for them.



Task **To create standalone device ABCVPN5050-1**

1. Log in to the FlexNet Operations Producer Portal if you have not already done so.
2. Click **Devices > Create Device**. The **Device | New Device** page appears.
3. Enter the device's attributes:
 - **Device name:** Type **ABCVPN5050-1**
 - **Model:** Select **FLX_CLIENT**
 - **ID:** Select **STRING** and type **ABCVPN5050-1** for **Primary ID**.
 - **Identity:** Select **ABCNetworks**
 - **Account:** Select **BarryPhoto**:

- a. Click the search icon next to **Account**. The **Assign Device Owner** pop-up window opens.
- b. On the **Customers** tab, search for and select **BarryPhoto**, then click **Select**. The **Account** window closes. On the **Device** page, **Account** is populated with device owner details.
- c. Click **Save**. The device's default view appears. Note that **Device Details** lists BarryPhoto as the **Account**, **Status** is ACTIVE, and **Pre-installed License Generated?** is No. **Model Details** is The device model does not include any pre-installed licenses. **Licenses** is No licenses have been mapped.



Task *To add a VPN5050 pre-installed product to device ABCVPN5050-1*

1. On the device's default view, click **Edit > Edit this Device**. The **Edit Device** page appears.
2. Under **Pre-installed Product**, click **Add Pre-installed Product**. The **Add Pre-installed Product** pop-up window opens.
3. Under **Product Details**, click **By Product**. In the **Select Product** window that opens, select product VPN5050 and click **OK** to close the **Select Product** window and populate the product name and version in the **Add Pre-installed Product** window.
4. In the **Add Pre-installed Product** window, enter the product details:
 - **License Model**: Select Embedded Counted
 - **Start Date**: Click the calendar icon, then click **Today** at the bottom of the calendar page that opens
 - **Expiration**: Select Specify Duration, type **1**, then select Years
5. Click **Add**. The **Edit Device** page appears with VPN5050 listed under **Pre-installed Product**.
6. Click **Save**. The device's default view page appears. Note that this device's **Status** is ACTIVE but **Pre-Installed License Generated?** is No.



Task *To generate a VPN5050 pre-installed product license file for device ABCVPN5050-1*

1. Click **Generate license file**. This message appears: License file successfully generated. Under **Device Details**, **Pre-installed License Generated?** is **Yes**.
2. On the device's default view, click **View** and select **View License File** from the menu. On the **View License File** page that appears, review the license file, which looks similar to:

```
MessageType="Buffer license"
MessageTime=(
  Timestamp=1440445832891
  TimestampUnits=Milliseconds
)
License=(
  Name=SimultaneousUsers
  Vendor=demo
  Version=1.0
  Expires=24-aug-2016
  Count=5
  HostID=(
    Type=String
    ID=ABCVPN5050-1
```



```

)
Issued=24-aug-2015
Start=23-aug-2015
Issuer="My Corporation"
)
License=(
  Name=Redundancy
  Vendor=demo
  Version=1.0
  Expires=24-aug-2016
  Uncounted
  HostID=(
    Type=String
    ID=ABCVPN5050-1 )
Issued=24-aug-2015
Start=23-aug-2015
Issuer="My Corporation"
)
License=(
  Name=Encryption_Throughput
  Vendor=demo
  Version=1.0
  Expires=24-aug-2016
  Count=5
  HostID=(
    Type=String
    ID=ABCVPN5050-1
)
Issued=24-aug-2015
Start=23-aug-2015
Issuer="My Corporation"
)

```



Task **To create standalone device ABCVPN5050-2**

Repeat [Step 2](#) through [Step 3](#) of task [To create standalone device ABCVPN5050-1](#) to create a device with these attributes:

- **ID:** Type ABCVPN5050-2
- **Device Model:** Select FLX_CLIENT
- **ID:** Select STRING and type ABCVPN5050-2 for **Primary ID**.
- **Identity:** Select ABCNetworks



Task **To add a VPN5050 pre-installed product to device ABCVPN5050-2**

Repeat [Step 1](#) through [Step 6](#) of task [To add a VPN5050 pre-installed product to device ABCVPN5050-1](#) to add a VPN5050 product license file to device ABCVPN5050-2.



Task **To generate a VPN5050 pre-installed product license for device ABCVPN5050-2**

Repeat [Step 1](#) through [Step 2](#) of task [To generate a VPN5050 pre-installed product license file for device ABCVPN5050-1](#) to generate a VPN5050 product license file for device ABCVPN5050-2. The license file looks similar to the device ABCVPN5050-1 license file.

Mapping an Additional Product Entitlement to a Device

In this exercise, you log in to the End-User Portal to map an additional 10 Mbps of encryption throughput to standalone device ABCVPN5050-1.



Task **To map the ABC VPN 5000 Encryption Throughput (10 Mbps) product entitlement to device ABCVPN5050-1**

1. Log in to the End-User Portal as Lisa Barry, the Barry Photography Studio end user you created in the exercise in the section [Getting Started with Entitlement Management](#).
2. In the End-User Portal, click **Devices > Devices**. The **Devices** page for Barry Photography Studio appears.
3. In the **Devices** page list, click the ABCVPN5050-1 link. The device's default view for ABCVPN5050-1 appears. Review the information under **Device Details**. Under **Model Details**, note that **Product Name** is VPN5050 and that no additional licenses are currently mapped to this device.
4. Click **Action** and select **Map Entitlements** from the menu. The **Map Entitlements** page appears.
5. In the 10MbpsVPN5000, Version 1.0 **Qty to Add** field, type 1 to represent 10 Mbps of additional encryption throughput.
6. Click **Save**. This message appears on the device's default view: Entitlements successfully mapped. Note that the **Status** of 10MbpsVPN5000, Version 1.0 is **License not generated**.
7. Click **Action > Download Capability Response** to generate the license. When asked if you want to open or save the binary license file, save it as <FlexNet_Embedded_install_dir>\bin\tools\ABCVPN5050-1.bin, where <FlexNet_Embedded_install_dir> is the directory in which your FlexNet Embedded licensing toolkit is installed. The exact behavior varies slightly, depending on your browser and operating system.
8. On the device's default view, click **View** and select **View History** from the menu. On the **Device History** page that appears, review the **Time**, **Event**, and **Additional Details** of each line in the list.
9. Click **Devices > Devices** and click the ABCVPN5050-1 link. On the device's default view, note that the **Status** of 10MbpsVPN5000, Version 1.0 is now **License generated**.
10. To use the FlexNet Embedded printbin tool to view the contents of the binary license file:
 - a. Open a command prompt window.
 - b. In the command prompt window, navigate to <FlexNet_Embedded_install_dir>\bin\tools, the directory in which you saved the binary license file in [Step 7](#).
 - c. At the prompt, type and enter the command
`printbin ABCVPN5050-1.bin`
where ABCVPN5050-1.bin is the name of the binary license file.
11. Review the license file, which looks similar to:

```

MessageType="Capability response"
ServerIDType=String
ServerID=BACK_OFFICE
SourceIds=BACK_OFFICE
Lifetime=86400
ResponseTime="Sep 18, 2015 10:57:19 AM"
RequestHostID=ABCVPN5050-1
RequestHostIDType=String
MachineType=Unknown
EnterpriseID=61135
License=(Name=Encryption_Throughput Vendor=demo Version=1.0
Expires=18-sep-2016 Count=10 HostID=ABCVPN5050-1 Issued=18-sep-2015
Start=17-sep-2015 Issuer="My Corporation")

```

Claiming a Device and Mapping an Additional Product Entitlement

In this exercise, you claim standalone device ABCVPN5050-2 on the End-User Portal and map an additional 10 Mbps of encryption throughput to it.



Task *To claim standalone device ABCVPN5050-2 and map the ABC VPN 5000 Encryption Throughput (10 Mbps) product entitlement to it*

1. In the End-User Portal, click **Activation & Entitlements** > **List Entitlements**. The **List Entitlements** page for Barry Photography Studio appears.
2. Copy the activation ID for the 10MbpsVPN5000 product.
3. Click **Devices** > **Claim and Activate**. The **Claim and Activate** page for Barry Photography Studio appears.
4. In the **Device ID** field, type ABCVPN5050-2.
5. In the **Activation IDs** field, paste the activation ID you copied in [Step 2](#) and click **Validate**. The entitlement for 10MbpsVPN5000 is listed with **Available qty**, **Product**, and **Expiration** details.
6. In the **Qty to add** field, type 1 to represent 10 Mbps of additional encryption throughput.
7. Click **Save**. The device's default view appears with this message: Entitlements successfully mapped. Under **Licenses**, note that the **Status** of 10MbpsVPN5000, Version 1.0 is **License not generated**.
8. Click **Action** > **Download Capability Response** to generate the license. When asked if you want to open or save the binary license file, save it as <FlexNet_Installed_install_dir>\bin\tools\ABCVPN5050-2.bin. The exact behavior varies slightly, depending on your browser and operating system.
9. On the device's default view, click **View** and select **View History** from the menu. On the **Device History** page that appears, review the **Time**, **Event**, and **Additional Details** of each line in the list.
10. Click **Devices** > **Devices** and click the ABCVPN5050-2 link. On the device's default view, note that the **Status** of the 10MbpsVPN5000 product is now **License generated**.
11. In the command prompt window, type and enter the command

```
printbin ABCVPN5050-2.bin
```

 where ABCVPN5050-2.bin is the name of the binary license file you saved in [Step 8](#).
12. Review the license file, which looks similar to:

```
MessageType="Capability response"
ServerIDType=String
ServerID=BACK_OFFICE
SourceIds=BACK_OFFICE
Lifetime=86400
ResponseTime="Sep 18, 2015 1:11:29 PM"
RequestHostID=ABCVPN5050-2
RequestHostIDType=String
MachineType=Unknown
EnterpriseID=61135
License=(Name=Encryption_Throughput Vendor=demo Version=1.0
Expires=18-sep-2016 Count=10 HostID=ABCVPN5050-2 Issued=18-sep-2015
Start=17-sep-2015 Issuer="My Corporation")
```

Activating a Device's Pre-Installed and Additional Product Licenses

In this exercise, you use a capability request to automatically create standalone device ABCVPN5050-3, claim it for customer account BarryPhoto, map the VPN5050 and 10MbpsVPN5000 product entitlements to it, and activate the licenses.



Task **To activate the pre-installed product and additional product licenses of standalone device ABCVPN5050-3**

1. In the End-User Portal, click **Activation & Entitlements > List Entitlements**. The **List Entitlements** page appears.
2. In the table, note that **Available quantity** and **Total quantity** for pre-installed product VPN5050 are both 5. Also note the VPN5050 **Activation ID**; you will use it in [Step 4](#).
3. In the table, note that **Available quantity** is 8 and **Total quantity** is 10 for product 10MbpsVPN5000. Also note the 10MbpsVPN5000 **Activation ID**; you will use it in [Step 4](#).
4. In the command prompt window, type and enter the following command to create the activation request for pre-installed product VPN5050 and additional product 10MbpsVPN5000:

```
caprequestutil -id IdentityClient.bin -host ABCVPN5050-3 -type FLX_CLIENT
-activate activation_ID_A 1 -activate activation_ID_B 1 mycapabilityrequest.bin
```

where IdentityClient.bin contains publisher demo and publisher identity ABCNetworks you added in the [Setup](#) topic, *activation_ID_A* is the pre-installed product VPN5050 activation ID, *activation_ID_B* is the product 10MbpsVPN5000 activation ID, and *mycapabilityrequest.bin* is the activation request in binary format.

5. When the command prompt returns, type and enter the following command to print the activation request for pre-installed product VPN5050 and product 10MbpsVPN5000:

```
printbin mycapabilityrequest.bin
```

6. Review the activation capability request, which looks similar to:

```
MessageType="Capability request"
Vendor=demo
MessageTime="May 7, 2016 1:43:48 PM"
ResponseTime="Dec 31, 1969 6:00:00 PM"
SourceIds=ABCVPN5050-3
RequestHostIDType=String
RequestHostID=ABCVPN5050-3
```

```
MachineType=Unknown
HostType=FLX_CLIENT
IsServer=false
IdentityName=ABCNetworks
DesiredRights=(ActivationID=b890-f02f-b5f2-45e8-808a-86fd-3341-7d42:1
  ActivationID=a931-4c60-1080-4a92-8e8b-1e62-eebe-8a53:1)
RequestOperation="Normal request"
```

7. In the End-User Portal, click **Devices > Offline Device Management**. The **Offline Device Management** page appears.
8. For **Upload type**, select **Generate license**. Click **Browse** and select the mycapabilityrequest.bin activation request file in the <FlexNet_Embedded_install_dir>\bin\tools directory, then click **Upload**.
9. Download the capability response file using the link offered by the application and save the file as <FlexNet_Embedded_install_dir>\bin\tools\ABCVPN5050-3.bin. The exact behavior varies slightly, depending on your browser and operating system.
10. In the command prompt window, type the command


```
printbin ABCVPN5050-3.bin
```

 where ABCVPN5050-3.bin is the name of the capability response file you saved in [Step 9](#).
11. Review the capability response, which looks similar to:

```
MessageType="Capability response"
ServerIDType=String
ServerID=BACK_OFFICE
SourceIds=BACK_OFFICE
Lifetime=86400
ResponseTime="May 8, 2016 9:13:43 AM"
RequestHostID=ABCVPN5050-3
RequestHostIDType=String
MachineType=Unknown
EnterpriseID=61135
License=(Name=Encryption_Throughput Vendor=demo Version=1.0
  Expires=8-may-2017 Count=10 HostID=ABCVPN5050-3 Issued=8-may-2016
  Start=7-may-2016 Issuer="My Corporation")
License=(Name=SimultaneousUsers Vendor=demo Version=1.0 Expires=8-may-2017
  Count=5 HostID=ABCVPN5050-3 Issued=8-may-2016 Start=7-may-2016
  Issuer="My Corporation")
License=(Name=Redundancy Vendor=demo Version=1.0 Expires=8-may-2017
  Uncounted HostID=ABCVPN5050-3 Issued=8-may-2016 Start=7-may-2016
  Issuer="My Corporation")
License=(Name=Encryption_Throughput Vendor=demo Version=1.0
  Expires=8-may-2017 Count=5 HostID=ABCVPN5050-3 Issued=8-may-2016
  Start=7-may-2016 Issuer="My Corporation")
```

12. In the End-User Portal, click **Activation & Entitlements > List Entitlements**. The **List Entitlements** page appears.
13. On the **List Entitlements** page, note that VPN5050 **Available quantity** is 4 and **Total quantity** is 5, and that 10MbpsVPN5000 **Available quantity** is 7 and **Total quantity** is 10.
14. Log out of the End-User Portal or continue with [License Servers](#).

Devices: Next Steps

This topic introduced FlexNet Embedded standalone devices, device management, and activation of a device's licenses. In the next topic, you are introduced to FlexNet Embedded license servers and license server management.

Devices: Advanced Topics

For more information about these topics, refer to [Administering Device and License Server Setup](#).

Activations of Entitlements Across Multiple Accounts on a Single Device

Producers with the FlexNet Advanced Organization module that use FlexNet Embedded licensing technology can take greater advantage of their account hierarchies and channel partner sets during entitlement mapping operations. This capability also supports producers who want end users to be able to activate entitlements on any device.

FlexNet Operations enables accounts, other than the device owner, to map entitlements to a device. Producers can map entitlements from the device owner's sub-accounts to any device, and End-User Portal users can map entitlements from their account, or its sub-accounts, to any device visible to them.

Activate Remaining Available Copies of an Entitlement

The FlexNet Embedded client API has a "partial" option when specifying activation IDs for a capability request intended for the back office. It is now possible to request, if there are insufficient copies of the entitlement to satisfy the request, that the back office instead activate the remaining available copies. Without this option, such a request would fail with a message indicating that the number of copies requested exceeds the available copies. With the option, the request succeeds with a status message indicating that the request was only partially fulfilled.

This partial option can be added for each activation code requested. For example,

```
-activate activation-id [copies] [partial]
```



Note • The partial option does not take into consideration optional limits imposed by the device series.


Refer to your *FlexNet Embedded API documentation* for details.

Device Series and Device Models

A device series is a collection of device models that are physically identical but can be upgraded in the field through license changes and products that are added on. The device series sets the maximum limits for device capabilities.

A device model is a basic configuration for which a producer creates a pre-installed license defining a set of capabilities within the maximum limits for the device series. The device model with that particular pre-installed license represents a purchasable configuration for the device. The capability of the model can be increased to the maximum for the series.

In the following example, producer ABC Networks, Inc. has a VPN 5000 device series that includes three device models: VPN 5005, VPN 5020, and VPN 5050. Each model represents a different basic configuration.



In the VPN 5000 device series, all device models can have up to 10,000 simultaneous users, up to 100 Mbps of throughput, and redundancy enabled or disabled.

The VPN 5050, the device model in the series with the highest basic capabilities, has a basic configuration of 5,000 simultaneous users, 50 Mbps of throughput, and redundancy enabled.

Two VPN 5000 series products that can be added on are an additional 1,000 simultaneous users and an additional 10 Mbps of throughput. All device models in the series can be upgraded by a customer to the maximum limits for devices in the VPN 5000 series.

Claiming an Unknown Device

If unknown device support is enabled for their site, a customer can claim an unknown device—a device that was not created using the Producer Portal—in one of the following ways:

- The device makes a capability request to FlexNet Operations.
- The customer uses the device ID to claim the device through the End-User Portal. The device is no longer unknown because it is associated with an account.

Mapping an Entitlement to a Device Using an Activation ID

Devices often include pre-installed products, but also permit the optional addition of new products. When the current owner of a device is entitled to additional products, the additional products can be mapped programmatically to the device using an activation ID.

Viewing Device Details and History

Use the FlexNet Operations Producer Portal to view details about a device such as device ID, status, host type, as well as details about any pre-installed or additional products. You can also view the history specific to a single device. The device history page lists all the device events including device creation, changes, and activation requests.

Associating a Device with an End User

A FlexNet Operations device can be associated with an end user or contact called the Device User. Associating a device with a Device User allows an End-User Portal administrator to communicate with someone regarding the licenses on that device. For example, if the End-User Portal administrator needs a license for a new device but there are no licenses available, the administrator can search for all existing devices using that license and request that one of those Device Users return their license so it can be used on the new device.

With the proper combination of system configuration and user permission settings, a Device User can be added, edited, or deleted via capability request, sync request, the End-User Portal, the Producer Portal, or Web Services. The same Device User can be associated with multiple devices, but a device can only be associated with one Device User.

Removing Licenses from a Device

A license for a device's added-on product can be manually removed in the Producer Portal via the device's default view.

Moving a Device

A device that has not yet been assigned to a customer account can be moved to a related account in the Producer Portal via the device's default view. For example, a parent account can move a device from one of its child accounts (a regional division, for instance) to another child account.

When a device is moved, entitlements that belong to that device are moved as well. The result of such a move is to either create new entitlements for the receiving account or to increment the count of that account's existing (and matching) entitlements by the count on the device that was moved.

Returning a Device

A device can be returned in the Producer Portal via the device's default view. Returns are irreversible actions intended for devices that will no longer receive a capability response or license file.

When customer returns a malfunctioning device to a manufacturer or reseller, the customer has the option of moving all of that device's licenses to a replacement device. Licenses that are not moved are returned to the pool of unused licenses and can be allocated to another device later.

Upgrading a Device

An upgrade is defined as moving a customer from a specified version of a product to an improved version with new or expanded capabilities. First, in the Producer Portal, create a product with additional features, configure FlexNet licensing for that product, and create an entitlement to the product for the customer account.



Note - The customer must remove the device's previous licenses before mapping an entitlement for the new version of the product.

Managing Hardware Returns

When FlexNet Embedded is used to license hardware, the Return Material Authorization (RMA) process is used to return a malfunctioning device to a producer or reseller and replace it with a new one. Some or all of the licenses can be moved to the replacement device. If a license is not moved, it is returned to the pool of unused licenses and can be allocated to another device.

Making a Device Obsolete

An active device can be made obsolete from its default view on the Producer Portal. When a device is made obsolete, its licenses are removed and returned to the pool, and it becomes unable to acquire new license rights. Obsolete devices cannot be re-activated. Obsolete status is permanent.

Offline Activation

Some devices use an offline activation model in which the device generates a binary license request file for an additional product license. The request file can be manually uploaded on the FlexNet Operations End-User Portal.

FlexNet Operations processes the request file to generate a license. If the license request is for an existing device, FlexNet Operations generates a regenerative license. This means that each response contains the complete state of capabilities for the device and that calling the FlexNet Embedded library to process the response overwrites the existing state. Each capability response completely replaces the previous response.

If the request is made for a new device, FlexNet Operations enters the device into the system, adds the corresponding additional product, and generates a license for it.

Vendor Dictionary

The FlexNet Embedded capability request allows a device to send producer-specific information called a vendor dictionary. A vendor dictionary is a collection of name value parameters that are defined by the producer, such as GPS coordinates, time zone, and region. The vendor dictionary provides an interface for an implementer to send custom data in addition to the FlexNet Embedded-specific data from the device to server or vice versa. This data can be used in license-enabled code and the back office server to send information back and forth for any producer-defined purposes, as needed.

Rehosting a License

Rehosting licenses is defined as the process of transferring licenses from one device to another.



Note - The customer must remove a device's licenses before they can be transferred to another device.

Generating a Trial License

A trial license enables a customer to demonstrate a product for trial purposes. The license expires after a short period of time.

License Servers

This topic introduces FlexNet Embedded license servers and typical tasks performed for a license server. These tasks include creating a FlexNet Embedded license server and mapping an entitlement for an additional product to a license server.

The exercises in this topic guide you through the basic FlexNet Embedded license server work flows.

- [License Servers: Key Concepts](#)
- [License Server: Exercises](#)
- [License Server: Advanced Topics](#)


License Servers: Key Concepts

FlexNet Embedded License Servers

The FlexNet Embedded license server communicates with FlexNet Operations to manage devices and product features for a collection of served devices. If a FlexNet Embedded license server is used, served devices connect to this server rather than connecting directly to FlexNet Operations.

The FlexNet Embedded license server provides functionality for serving and monitoring a counted pool of licenses for intelligent device or software clients. The license server application administers licenses, enforces usage count, and provides served license status information in conjunction with client code that incorporates FlexNet Embedded licensing.

FlexNet Embedded license servers can be hosted in the Revenera cloud (Revenera’s Cloud License Service must be purchased separately) or locally deployed in a customer’s enterprise; the hosting approach depends on the account’s deployment needs. The following figure shows the FlexNet Embedded license server’s role in the FlexNet Embedded architecture.



Mapping Additional Product Entitlements to a License Server

Additional product entitlements are mapped to a FlexNet Embedded license server the same way they are mapped to a FlexNet Embedded standalone device. When the server activates with FlexNet Operations, its additional product entitlements can be served to local devices. Licenses for additional products can also be removed from a license server.

Viewing Served Devices

Served devices refers to FlexNet Embedded devices that are managed by a FlexNet Embedded license server. In FlexNet Operations, served devices are read-only entities.

For a FlexNet Embedded license server deployed in the customer’s enterprise, served device data is only available when the server is syncing with the FlexNet Operations back office. License servers hosted in the Revenera cloud automatically sync with the back office.

License Server: Exercises

These exercises use examples to guide you through the following FlexNet Embedded license server tasks:

Exercise	Description
Creating a FlexNet Embedded License Server	In the End-User Portal, create the ABCVPN_Server license server for FlexNet Embedded devices.
Mapping Additional Product Entitlements to a License Server	In the End-User Portal, map 3 copies of product 10MbpsVPN5000 to the ABCVPN_Server license server.

Creating a FlexNet Embedded License Server

In this exercise, you use the End-User Portal to create the ABCVPN_Server local license server for FlexNet Embedded devices. The ABCVPN_Server local license server can also be created in the Producer Portal.



Task *To create FlexNet Embedded license server ABCVPN_Server*

1. If you have not already done so, log in to the End-User Portal as Lisa Barry, the Barry Photography Studio end user you created in the exercise in the section [Getting Started with Entitlement Management](#).
2. Click **Devices > Create Device**. The **Device | New Device** page appears.
3. In the **Name** field, type ABCVPN_Server.
4. Select the **Runs license server?** check box.
5. For Server **deployment**, select **Local**.
6. On the **ID** drop-down menu, select **ETHERNET**. In the **Primary ID** field, type ABCVPN_Server.
7. Click **Save**. On the **View Server** page that appears, review the server details. Under **Model Details**, note that this server does not include any pre-installed product and that no additional product entitlements are currently mapped.

Mapping Additional Product Entitlements to a License Server

In this exercise, you use the End-User Portal to map 3 copies of product 10MbpsVPN5000 to the ABCVPN_Server server.



Note - If you just completed the *Creating a FlexNet Embedded License Server* exercise, you can start with *Step 3* of this exercise.



Task *To map 3 copies of product 10MbpsVPN5000 to license server ABCVPN_Server*

1. In the End-User Portal, click **Devices > Devices**. The **Devices** page appears.
2. In the devices list, click the ABCVPN_Server link. The **View Server** page appears with the server details.
3. Click **Action** and select **Map Entitlements** from the menu. The **Map Entitlements** page appears with server details and additional products available.
4. On the 10MbpsVPN5000, Version 1.0 line of the table, type 3 in the **Qty to add** field.
5. Click **Save**. The **View Server** page appears with this message: Entitlements successfully mapped. Note that the **Status** of the 10MbpsVPN5000, Version 1.0 product is **License not generated**.
6. Click **Action > Download Capability Response** to generate the license. When asked if you want to open or save the binary license file, save it as <FlexNet_Embedded_install_dir>\bin\tools\ABCVPN_Server.bin, where <FlexNet_Embedded_install_dir> is the directory in which your FlexNet Embedded licensing toolkit is installed. The exact behavior varies slightly, depending on your browser and operating system.
7. Under **View Server**, click **View** and select **View History** from the menu. On the **Server History** page that appears, review the **Time**, **Event**, and **Additional Details** of each line in the list.
8. Click **Devices > Devices** and click the ABCVPN_Server link. On the **View Server** page, note that the server does not include any pre-installed product and the **Status** of the 10MbpsVPN5000 product is now **License generated**.
9. To use the FlexNet Embedded printbin tool to view the contents of the binary license file:
 - a. Open a command prompt window.
 - b. In the command prompt window, navigate to navigate to <FlexNet_Embedded_install_dir>\bin\tools, the directory in which you saved the license file in [Step 6](#).
 - c. At the prompt, type the command
printbin ABCVPN_Server.bin
where ABCVPN_Server.bin is the name of the binary license file.

10. Review the license file, which looks similar to:

```
MessageType="Capability response"
ServerIDType=String
ServerID=BACK_OFFICE
SourceIds=BACK_OFFICE
Lifetime=86400
ResponseTime="Sep 18, 2015 5:22:51 PM"
RequestHostID=ABCVPN_Server
RequestHostIDType=Ethernet
MachineType=Unknown
EnterpriseID=61135
License=(Name=Encryption_Throughput Vendor=demo Version=1.0
Expires=18-sep-2016 Count=30 ServerHostID=ABCVPN_Server/Ethernet HostID=ANY
BorrowInterval="1 week(s)" RenewInterval=20 Issued=18-sep-2015
Start=17-sep-2015 Issuer="My Corporation")
```

11. In the End-User Portal, click **Activation & Entitlements > List Entitlements**. The **List Entitlements** page appears.
12. On the **List Entitlements** page, note that VPN5050 **Available quantity** is 4 and **Total quantity** is 5, and that 10MbpsVPN5000 **Available quantity** is 4 and **Total quantity** is 10.
13. Log out of the End-User and Producer Portals.

License Server: Advanced Topics

Activations of Entitlements Across Multiple Accounts on a Single Device

Producers with the FlexNet Advanced Organization module that use FlexNet Embedded licensing technology can take greater advantage of their account hierarchies and channel partner sets during entitlement mapping operations. This capability also supports producers who want end users to be able to activate entitlements on any device.

FlexNet Operations enables accounts, other than the device owner, to map entitlements to a device. Producers can map entitlements from the device owner's sub-accounts to any device, and End-User Portal users can map entitlements from their account, or its sub-accounts, to any device visible to them.

Activate Remaining Available Copies of an Entitlement

The FlexNet Embedded client API has a “partial” option when specifying activation IDs for a capability request intended for the back office. It is now possible to request, if there are insufficient copies of the entitlement to satisfy the request, that the back office instead activate the remaining available copies. Without this option, such a request would fail with a message indicating that the number of copies requested exceeds the available copies. With the option, the request succeeds with a status message indicating that the request was only partially fulfilled.

This partial option can be added for each activation code requested. For example,

```
-activate activation-id [copies] [partial]
```



Note - The partial option does not take into consideration optional limits imposed by the device series.

Refer to your *FlexNet Embedded API documentation* for details.

Associating a Server with an End User

A FlexNet Operations server can be associated with an end user or contact called the Device User. Associating a server with a Device User allows an End-User Portal administrator to communicate with someone regarding the licenses on that server. For example, if the End-User Portal administrator needs a license for a new device but there are no licenses available, the administrator can search for all existing devices using that license and request that one of those Device Users return their license so it can be used on the new device.

With the proper combination of system configuration and user permission settings, a Device User can be added, edited, or deleted via capability request, sync request, the End-User Portal, the Producer Portal, or Web Services. The same Device User can be associated with multiple devices, but a device can only be associated with one Device User.

Mapping a Product to a License Server Using an Activation ID

License servers often include pre-installed products but also permit the optional addition of new products. When the current owner of a license server is entitled to additional products, those products can be mapped programmatically to the license server using an activation ID.

Removing Product Licenses from a License Server

Licenses for additional products that are mapped to a license server can be manually removed via the Producer Portal's **View Server** page.

The following table lists limitations for removing licenses from a license server:

Server Type	Limitation
Local License Server	Only concurrent licenses that are not in use can be removed from a local license server. To remove used licenses, you must unmap the licenses before deleting them. Licenses that are currently in use cannot be removed.
CLS Instance	<ul style="list-style-type: none">• Licenses for counted features that are currently in use cannot be removed. You must unmap used licenses first before deleting them. (Only licenses for uncounted features that are currently in use can be removed.)• At any one time, you can remove licenses from a total of five activation IDs.
Auto-Provisioned License Server	Only unused licenses for metered features can be removed using Licenses > Remove Licenses. Refer to Auto-Provisioning for more information.

Moving a License Server

A license server can be moved from an account to a related account via the Producer Portal's **View Server** page.



Note - Auto-provisioned license servers that have entitlements mapped for metered features cannot be moved to another account. Refer to [Auto-Provisioning](#) for more information.

Returning a License Server

A license server can be returned via the Producer Portal's **View Server** page. Returns are irreversible actions intended for server hosts that will no longer receive a capability response or license file.

Making a License Server Obsolete

An active license server can be made obsolete from its **View Server** page on the Producer Portal. When a license server is made obsolete, its licenses are removed and returned to the pool of unused licenses, and it becomes unable to acquire new license rights. Obsolete license servers cannot be re-activated. Obsolete status is permanent.



Note • Making an auto-provisioned license server obsolete that has entitlements mapped for metered features will remove all licenses mapped to the server. However, this is not recommended, because future line items will not be mapped automatically to the auto-provisioned license server. Refer to [Auto-Provisioning](#) for more information.

Activating an Unclaimed FlexNet Embedded License Server

A FlexNet Embedded license server can be created in the Producer Portal, but an unclaimed license server can be created by submitting an activation request to the FlexNet Operations back office. The request must include an activation code and host information. When it receives such a request, FlexNet Operations creates the license server and maps the activation code to that license server with the requested quantity.



Note • A site can be configured so that an activation code is not required to create an unclaimed license server.

FlexNet Operations processes activation requests from an unclaimed license server using the default server host type FLX_SERVER, then assigns the FLX_SERVER server host type to each license server created through this process—thereby defining the server’s identity.



Note • The pre-defined server host type, FLX_SERVER, is associated, by default, with the first identity a producer creates.

Viewing License Server Request History

You can view the history of all license server requests and filter the history by ID and date range.

Using Server Sync to Send License Transaction Data to FlexNet Operations

As transactions occur between a FlexNet Embedded server and its FlexNet Embedded devices, the license server incrementally updates the device status and activation data it stores. When syncing is enabled, the license server syncs with FlexNet Operations, providing the back office with information about how customers use served devices and what features they use. Sync data transmission to FlexNet Operations is configured by the device producer when the FlexNet Embedded license server is configured.



Note • Sync messages can be viewed by viewing the device’s history. The history of a FlexNet Embedded license server shows sync messages related to all its served devices, while the history of a served device shows only the messages specific to that served device.

Usage

Refer to [Getting Started with Usage Management](#) for information about FlexNet usage management concepts, exercises, and advanced activities.

Getting Started with FlexNet Publisher Trusted Storage-Based Licensing

This section *Getting Started with FlexNet Publisher Trusted Storage-Based Licensing* introduces fundamental FlexNet Operations concepts and uses exercises to guide a Producer Portal user through basic trusted storage license activation and support. The intended audience for this getting started section is the first-time Producer Portal user, or one without FlexNet Operations training or experience.

Topic	Description
Introduction	Overview of this getting started section, exercise prerequisites, summary of the FlexNet Operations license lifecycle, description of the FlexNet Publisher Licensing Toolkit, and how to configure your machine for trusted storage.
Trusted Storage License Activation	FlexNet Operations trusted storage licensing concepts and exercises that demonstrate how to generate a trusted storage license. Brief descriptions of advanced trusted storage license activation topics and cross references to documents that contain more information.
Trusted Storage License Support	FlexNet Operations trusted storage licensing concepts and exercises that demonstrate how to return a trusted storage license. Brief descriptions of advanced trusted storage license activation topics and cross references to documents that contain more information.

Introduction

This section lists exercise prerequisites, provides a summary of the FlexNet Operations license lifecycle, describes the FlexNet Publisher Licensing Toolkit, and explains how to configure your machine for trusted storage.

- [Exercise Prerequisites](#)
- [The License Lifecycle: FlexNet Publisher Trusted Storage-Based Licensing](#)

- [FlexNet Publisher Licensing Toolkit](#)
- [Configuring Your Machine for Trusted Storage](#)
- [Next Steps](#)

Exercise Prerequisites

Before you begin the exercises in this getting started section:

- FlexNet Operations seed data and demonstration database must be loaded



Important - These exercises require a FlexNet Operations database populated with demonstration data. Contact Reverera Support if demonstration data is not loaded.

- You must have a FlexNet Operations Producer Portal login and a role with permission to view and manage accounts and users, such as System Administrator
- You must complete the exercises in the section [Getting Started with Entitlement Management](#)
- The FlexNet Publisher Licensing Toolkit must be properly installed and configured



Important - Refer to the instructions in the FlexNet Publisher Installation Guide to download and install the licensing toolkit, and to the FlexNet Publisher document “Getting Started with Trusted Storage-Based Licensing” for using the example files provided in the licensing toolkit.

The License Lifecycle: FlexNet Publisher Trusted Storage-Based Licensing

The FlexNet Operations license lifecycle is a repeating process of producer and customer activities, as depicted in the figure and described below.



Figure 11-1: FlexNet Operations License Lifecycle

- **Create Products** – Create product definitions that are used to generate licenses.
- **Order/Entitle** – Define a customer account's rights to obtain licenses for your products.
- **Deliver/Install** – Deliver the application software to the customer and install that software.
- **Activate** – Deliver licenses to the customer.
- **Return/Rehost** – Manage license transfers from one user or system to another.
- **Maintain/Update** – Deliver software and license updates to the customer.
- **Upsell/Renew** – Renew customer licenses, or sell the customer additional product functionality.

FlexNet Publisher Licensing Toolkit

Windows Platform

The exercises in this getting started section require a FlexNet Publisher Licensing Toolkit installed on a Windows platform (either the i86_n3 or x64_n6 toolkit). Each exercise uses sample utilities and executables included in the Windows toolkit. The same components are included in UNIX toolkits. However, to perform the exercises on a UNIX machine, you must adjust the path and file name syntax for the UNIX environment.

Activation Utilities

FlexNet Publisher Licensing activation utilities are designed so that the end user can enter required input via explicit command line arguments. The exercises in this getting started section use command line arguments to issue activation commands. These arguments represent one way of supplying input to the utilities; this method can differ from your specific requirements as a publisher.

Commands are issued in relation to the platform directory under the FlexNet Publisher Licensing Toolkit installation directory. For example, if the Windows 64-bit toolkit is installed, commands are issued from a command prompt in the x64_n6 directory.

License Server Manager

The license server manager forwards connections from a FlexEnabled application to the correct vendor daemon, which is the part of the license server that authenticates requests and serves licenses. When an exercise requires a license server manager, `lmadmin` is used.



Note • If necessary, you can use the alternative license server manager, `lmgrd`, in place of `lmadmin`.

The exercises use the sample vendor daemon, called `demo`, included in the licensing toolkit.

Toolkit Directories

It is assumed, for exercises in this getting started section, that FlexNet Operations is installed on a Windows machine. The table below lists the toolkit directories, with their shortcut names, referenced in the exercises.

Shortcut Name	Location
<code><install_dir></code>	No default. Path is defined at toolkit installation time.
<code><platform_dir></code>	<code><install_dir>\i86_n3</code> (or <code><install_dir>\x_64_n6</code>)
<code><publisher></code>	<code><install_dir>\i86_n3\publisher</code> (or <code><install_dir>\x64_n6\publisher</code>)

Become familiar with the FlexNet Publisher Licensing Toolkit directory structure for your installation before proceeding; these shortcuts are used throughout the getting started section.

Configuring Your Machine for Trusted Storage

Before starting the license activation and support exercises, configure your machine to use trusted storage. The configuration type depends on your machine's platform:

- [Installing the Licensing Service \(on Windows\)](#)
- [Initializing the Trusted Storage Directory \(on UNIX\)](#)

Normally, for a licensed product, configuration occurs as part of product installation and is performed only once on a given machine.

Installing the Licensing Service (on Windows)

On a Windows machine, configuration for trusted storage requires installing the FlexNet Publisher Licensing Service and registering the product that is using the service. This procedure uses the example executable `installanchorservice.exe`.



Task **To install FlexNet Publisher Licensing Service**

1. On the **Start Menu** of your machine, right-click the Windows **Command Prompt** and select **Run as administrator**.
2. To install the FlexNet Publisher Licensing Service and register product PhotoPrint-client that is supplied by publisher demo, at a command prompt in the `<platform_dir>`, enter

```
installanchorservice demo PhotoPrint-client
```

The output is

```
Successfully installed anchor service for publisher demo, product PhotoPrint-client
```

For product PhotoPrint-server that is supplied by publisher demo, at a command prompt in the `<platform_dir>`, enter

```
installanchorservice demo PhotoPrint-server
```

The output is

```
Successfully installed anchor service for publisher demo, product PhotoPrint-server
```

Initializing the Trusted Storage Directory (on UNIX)

On a UNIX machine, configuration for trusted storage requires initializing the trusted storage directory. Additionally, for OS X and Linux machines, configuration also requires installing the FlexNet Publisher Licensing Service. This procedure uses the example script `installfnp.sh`.



Note • On OS X platforms, your user account must have sudo privileges to perform this procedure. On all other UNIX platforms, you must have root permission to perform this procedure.



Task **To initialize the trusted storage directory (and install the FlexNet Publisher Licensing Service, if required)**

Perform the appropriate step at a command prompt in the `<publisher>` directory:

- On a UNIX machine, enter the command:

```
sh install_fnp.sh
```
- On an OS X machine, enter the command:

```
sudo sh install_fnp.sh
```

The output is

Configuration completed successfully.

Resetting Trusted Storage

If this is your first time through the trusted storage exercises, proceed to [Starting the FlexNet License Server](#). Otherwise, use this procedure to remove any client-side and server-side trusted storage files from previous exercises.



Important • The utilities `tsreset_app` and `tsreset_svr` are provided for use with exercises and are not intended to be shipped to an end-user site.



Task To reset trusted storage

1. To shut down all license servers that might be running, in the `<platform_dir>`, enter

```
lmdown -all
```
2. To delete any client-side trusted-storage files, at a command prompt in the `<platform_dir>`, enter

```
tsreset_app -delete all
```

The output is

```
Performing reset operation, please wait...  
Trusted Storage Contents have been reset...
```
3. To delete any server-side trusted-storage files, at a command prompt in the `<platform_dir>`, enter

```
tsreset_svr -delete all
```

The output is

```
Performing reset operation, please wait...  
Trusted Storage Contents have been reset...
```

Starting the FlexNet License Server

Use this procedure to import the vendor daemon `demo` and start the license server that uses it.



Task To start the license server and import the vendor daemon `demo`

1. Copy files `<platform_dir>\demo.exe` and `<platform_dir>\demo_libFNP.dll` to the `<platform_dir>\lmdadmin\demo` directory.



Note • On UNIX platforms, copy files `<platform_dir>/demo` and `<platform_dir>/demo_libFNP.so` to the `<platform_dir>/lmdadmin/demo` directory. On AIX, copy `demo` and `demo_server_libFNP_notr.so`.

2. To import the vendor daemon `demo` and use the `demo.lic` license file, at a command prompt in the `<platform_dir>\lmdadmin` directory, enter

```
lmdadmin -import demo\demo.lic -force
```

The output is

```
Configured new vendor daemon, demo.
```

3. To start the license server in the background, from a command prompt in the <platform_dir>\lmadmin directory, enter

```
lmadmin -allowRemoteStopServer yes
```

Next Steps

The next topic introduces trusted storage licenses and their activation, the stage of the FlexNet Operations license lifecycle that follows delivery of the product's activation IDs to the customer.

Trusted Storage License Activation

This topic introduces trusted storage licenses and their activation, the stage of the FlexNet Operations license lifecycle that follows delivery of the product's activation IDs to the customer. Activation is the process of requesting, generating, delivering, and installing license rights.

The exercises in this topic getting started section you through basic FlexNet Operations trusted storage license activation.



Note - To use the exercises in this topic, you must be familiar with the FlexNet Publisher Licensing Toolkit. For more information, refer to the FlexNet Publisher document "Getting Started with Trusted Storage-Based Licensing".

Trusted Storage License Activation Key Concepts

After a product purchase has been registered with FlexNet Operations as an entitlement, a customer can obtain a license for the product. The license enables use of some or all of the product's features, and contains information about the computers on which the software is to run, the expiration date, and the count of the entitlement's available quantity that have been activated. Before the license can be generated, the entitlement must be validated (marked as deployed) in FlexNet Operations.

Trusted Storage License Models

Trusted storage models enable *programmatic activation*, that is, activation of license rights on a machine using a process that is completely hands-free and transparent to the user.

Trusted storage license models include these types:

- A *retail activation* license model is used in a retail scenario for activation of license rights in trusted storage on a standalone end-user machine. Unlimited instances of the licensed application can be run on that machine. You create a product that uses a retail activation model as one of the [Client-Side Online Activation](#) exercise prerequisites.
- A *floating transferable* license model allows license rights to be written to the trusted storage of a license server. The license server can then transfer these rights to another server, or allow them to float over a network from which end users check them out. These license rights cannot be activated directly on end-user machines.

- A *floating borrowable* license is first activated on a license server. It can be transferred to another license server, served as a floating license, or activated on an end-user machine for use when it is no longer connected to a license server.
- An *enterprise activation* license model is used to activate license rights on an enterprise server, from which the license rights can be transferred to another server or activated on an end-user machine. These licenses cannot float over a network. You create a product that uses an enterprise activation model as one of the [Server-Side Online Activation](#) exercise prerequisites.

License rights data in trusted storage is encrypted and authenticated to prevent tampering.

Transaction Keys

Products that use a trusted storage license model require at least one transaction key. A transaction key consists of a publisher ID, a set of transaction key seeds, binding, and anchors. Binding ensures that license rights held in trusted storage are not copied to another system, while anchors detect whether trusted storage has been tampered with, deleted, or restored.

A transaction key is linked with a product only if the product uses a trusted storage license model. The transaction key is linked with the product when the first trusted storage license model is linked with the product, and can be changed later or overridden. You must create at least one transaction key before linking a trusted storage license model with a product. Unlike license models, it is not necessary to deploy transaction keys.

You create a transaction key as one of the [Client-Side Online Activation](#) exercise prerequisites.

Generating Trusted Storage Licenses

Trusted storage is a technology, used by FlexEnabled applications to store license rights, that allows hands-free activation. Users can obtain trusted storage licenses without downloading them from a web portal; instead, license rights are stored in an encrypted file on the local host's drive.

The process of placing license rights in client trusted storage, also called activating an application, requires a utility on the customer's system that communicates with FlexNet Operations. The utility sends a request for a particular product with particular terms. FlexNet Operations processes the request to determine if the system is entitled to the software, and if so, sends a response containing the corresponding license rights. The utility processes the response, which results in the license rights being stored in trusted storage.

The two types of trusted storage are:

- *client-side* – license rights stored on an end-user system that are checked out by a licensed application
- *server-side* – counted license rights stored on a license server system that are served in a corporate network

Activation Utilities

The FlexNet Publisher Licensing Toolkit component that communicates with FlexNet Operations to activate software is called an activation utility. An activation utility that activates software on a client system is called an application activation utility. An activation utility that activates software to be served by a license server is called a server activation utility.

Composite Transaction and Single Transaction Activation Utilities

FlexNet Operations provides sample client-side and server-side activation utilities that operate from the command line, as listed in the following table. Later releases include composite transaction activation utilities, which facilitate more efficient activation operations by bundling multiple transactions into a single communication exchange between the client or server utility and FlexNet Operations. The older, single transaction activation utilities are still supported for legacy purposes.

Activation Utility Type	Composite Transaction	Legacy, Single Transaction
Application (client side)	appcomptranutil	appactutil
Server (server side)	servercomptranutil	serveractutil



Important • The sample utilities shown in the table are provided for use with the exercises in this getting started section. They are not suitable for use in a production environment.

Using Sample Activation Utilities

The sample client-side application activation utilities, `appcomptranutil` and `appactutil`, are command-line tools for adding license rights to client-side trusted storage. These executables are located in the `<platform_dir>` of the FlexNet Publisher Licensing Toolkit, where `platform_dir` is the name of the platform on which the toolkit is installed.

To use a sample application activation utility, open a command prompt or console window and set the `<platform_dir>` to be the current directory. For example, to verify that no license rights are currently available on the client system, enter the command

```
appcomptranutil -view
```

or

```
appactutil -view
```

This command displays the current contents of client trusted storage, which should initially report that there are no fulfillment records in trusted storage.

Similar sample utilities, `servercomptranutil` and `serveractutil`, are supplied for server-side activation, and are located in the same directory as the application activation utilities.

FlexNet Operations supports three types of trusted storage license activation:

- **Online Activation**
- **Short Code Activation** (also called phone-based activation)
- **Manual Activation** (also called email-based activation)

Online Activation

Trusted activations are normally done programmatically as transactions between a client or server activation utility and the FlexNet Operations server. The activation utility generates a request that is submitted programmatically and the FlexNet Operations server generates a response that is used to complete the activation.

The following sections describe the client and server utilities used to perform online trusted storage license activation. For syntax and options, type the utility name in the FlexNet Publisher Licensing Toolkit <platform_dir> command window.



Note - The exercises in this getting started section are based on a Windows platform installation of the FlexNet Publisher Licensing Toolkit. To do the exercises on a UNIX machine, adjust the path and file name syntax for the UNIX environment.

Client-Side Online Activation

The client-side online activation utilities are `appcomptranutil` (composite transaction) and `appactutil` (single transaction). These utilities are run, in a command window on the client, with command-line parameters that indicate the FlexNet Operations server host and port, and the activation ID.

Client-side activation requires a product linked to a retail activation license model.

Composite Transaction

For the composite transaction activation utility, `appcomptranutil`, the command to perform a retail activation looks similar to

```
appcomptranutil -t http://<hostname:port>/flexnet/services/ActivationService -a <act_ID>
```

where

- <hostname> is `localhost`, the name of the system on which the license server is running
- <port> is `8888`
- <act_ID> is the activation ID displayed by FlexNet Operations



Note - For sample commands shown in this getting started section, it is assumed that FlexNet Operations and the activation utilities are running on the same system. If not, replace `localhost:8888` with the appropriate host and port values.

Progress messages are displayed at the command line.

Multiple transactions can be invoked in a single command with `appcomptranutil`. To perform multiple activations in a single command, append additional activations to the command with `-a <act_ID>`. For example,

```
appcomptranutil -t http://<hostname:port>/flexnet/services/ActivationService  
-a <act_ID1> -a <act_ID2> -a <act_ID3>
```



Note - To successfully perform multiple activations in a single command, all entitlements must belong to the same account, use the same license type (client or server), and be performed on the same machine.

Legacy, Single Transaction

For the single transaction activation utility, `appactutil`, the command to perform a retail activation looks like

```
appactutil -served -comm soap -commServer http://<hostname:port>/flexnet/services/ActivationService
          -entitlementID <ent_ID>
```

where `<ent_ID>` is the entitlement ID.

Progress messages are displayed at the command line.

New license rights for the products and features you defined in FlexNet Operations are visible in client-side trusted storage when you run the command

```
appcomptranutil -view
```

or

```
appactutil -view
```

Output is similar to

```
Trust Flags: FULLY TRUSTED
Fulfillment Type: PUBLISHER ACTIVATION
Status: ENABLED
Fulfillment ID: FID__111ff222_333445555__666e
Entitlement ID: ent_ID
Product ID: NAME=Sample App;VERSION=1.0
Expiration date: 31-dec-2015
Feature line(s):
INCREMENT F1 demo 1.0 31-dec-2015 1 ISSUER="Sample Co." \
          ISSUED=1-jan-2015 START=1-jan-2015 SIGN="..."
INCREMENT F2 demo 1.0 31-dec-2015 1 ISSUER="Sample Co." \
          ISSUED=1-jan-2015 START=1-jan-2015 SIGN="..."
```

Server-Side Online Activation

Server-side activation is performed in a manner similar to client-side activation, and can be performed using a server activation utility such as `servercomptranutil` or `serveractutil`.

Server-side activation requires a product linked to one of the following license model types:

- Enterprise activation
- Floating borrowable
- Floating transferable

Composite Transaction

Server-side commands using `servercomptranutil` are similar to client-side commands using `appcomptranutil`. For a composite transaction server activation utility, a sample command is

```
servercomptranutil -t http://<hostname:port>/flexnet/services/ActivationService -a <act_ID> count=1
```

Multiple transactions can be invoked in a single command with `servercomptranutil`. To perform multiple activations in the same command, append additional activations to the command with `-a <act_ID> count=n`, where `n` is the number of products being activated. For example,

```
servercomptranutil -t http://<hostname:port>/flexnet/services/ActivationService  
-a <act_ID1> count=x -a <act_ID2> count=y -a <act_ID3> count=z
```



Note - To successfully perform multiple activations in a single command, all entitlements must belong to the same account, use the same license type (client or server), and be performed on the same machine.

Legacy, Single Transaction

Legacy, server-side commands using `serveractutil` are similar to client-side commands using `appactutil`. For a single transaction server activation utility, a sample command is

```
serveractutil -served -comm soap -commServer http://<hostname:port>/flexnet/services/ActivationService -  
entitlementID <ent_ID> -expiration 1-jan-2018 -licensemodeltype <count>
```

where

- `<ent_ID>` is the entitlement ID
- `licensemodeltype` is one of the following:
 - `activatable` for an enterprise activation model
 - `hybrid` for a floating borrowable model
 - `concurrent` for a floating transferable model
- `<count>` is the number of products, using `licensemodeltype`, that are being activated

Trusted Storage License Activation Exercises

These exercises use examples to guide you through the following trusted storage license activation tasks:

Exercise	Description
Client-Side Online Activation	Perform a client-side online activation of a PhotoPrint-client product license.
Server-Side Online Activation	Perform a server-side online activation of a PhotoPrint-server product license.
Local Online Activation	Perform a local online activation of a PhotoPrint-server product license on the client.



Important - This getting started section describes operations that are performed on the server side (referring to the FlexNet license server) and on the client side (referring to the machine on which the FlexEnabled application

is installed). The exercises use the same machine for both types of operations. However, a real enterprise environment typically has one or more dedicated license servers that are distinct from the client machines.

Client-Side Online Activation

In this exercise, you perform a client-side online activation of the PhotoPrint-client product license.

Prerequisites

Log in to the FlexNet Operations Producer Portal to:

- Create a transaction key called TS-DemoTransKey:
 - a. Click **Administer > Transaction Keys**
 - b. Click **Add a Transaction Key**
 - c. Under **Create a Transaction Key**, enter these attributes:
 - **Name:** Type TS-DemoTransKey
 - **Description:** Type Demo trans key for trusted storage licensing exercises
 - **Publisher ID:** Select 256-demo
 - **Transaction Key Seeds:** Type eight sets of eight hexadecimal digits each:

00000000 aaaaaaaaa 11111111 bbbbbbbb
22222222 cccccccc 33333333 dddddddd
 - **Binding Type:** Select Default Fingerprint
 - **Do you want to use Anchoring?** Select Yes
 - d. Click **Save**

If necessary, refer to the section [Getting Started with Entitlement Management](#) to:

- Deploy the Retail Activation license model ([Deploying a License Technology and Model](#))
- Copy product PhotoPrint and save it as PhotoPrint-client ([Creating a Product](#))
 - a. Click **Products > Products**
 - b. Search for and select the PhotoPrint check box, then click **Copy**
 - c. Under **Create a Product**, in the **Product Name** field, type PhotoPrint-client and click **Save**
- Link PhotoPrint-client to the Retail Activation license model and select **Transaction Key** TS-DemoTransKey from the **Default** menu ([Linking a License Model to a Product](#)). Remove (unlink) the Nodelocked Uncounted license model and save PhotoPrint-client.
- Deploy the PhotoPrint-client product ([Deploying a Product](#))
- Create and configure an entitlement called ENT-PhotoPrint-client ([Creating and Configuring an Entitlement](#)):
 - for end customer Lisa Barry of BarryPhoto

- with a product PhotoPrint-client line item for a quantity of 1 copy and a license that starts at the first activation date and has a duration of 1 year
- Save and deploy the ENT-PhotoPrint-client entitlement ([Deploying an Entitlement](#))
- If this is not your first time through the trusted storage license exercises, perform the steps in [Resetting Trusted Storage](#) to remove any client-side and server-side trusted storage files that might exist from previous exercises.



Task *To activate a license using* appcomptranutil

1. In the FlexNet Operations Producer Portal, click **Entitlements > List Entitlements**. The **List Entitlements** page appears.
2. On the **Activatable Line Items** list, search for entitlement ID ENT-PhotoPrint-client and review the line item details. Note that available quantity and total quantity are 1 for product PhotoPrint-client. Expiration is in 1 year.
3. At a command prompt in the <platform_dir>, enter the following, where <hostname:port> is localhost:8888 and <act_ID> is the FlexNet Operations PhotoPrint-client activation ID:



Important - Exercises are based on the assumption that FlexNet Operations and the activation utilities are running on the same system. If not, replace localhost:8888 in the appcomptranutil command with the appropriate host and port values.

```
appcomptranutil -t http://<hostname:port>/flexnet/services/ActivationService -a <act_ID>
```

Output is similar to

```
Server http://localhost:8888/flexnet/services/ActivationService, comms type SOAP
Status: 4, Creating request
Status: 5, Request created
Status: 6, Context created
Status: 7, Connected to remote server
Status: 8, Request Sent
Status: 9, Polling for response
Status: 10, Waiting for response
Status: 9, Polling for response
Status: 11, Done
Response processed successfully. Actions were:
    Configuration   TrustedId "13"
    Create           fulfillment "FID_d7a83787_46d6_43b1_a65b_ad85e135aa60"
```

4. At a command prompt in the <platform_dir>, to view the new license rights in client-side trusted storage, enter

```
appactutil -view
```

Output is similar to

```
-----
Trust Flags: FULLY TRUSTED
Fulfillment Type: PUBLISHER ACTIVATION
Status: ENABLED
Fulfillment ID: FID_d7a83787_46d6_43b1_a65b_ad85e135aa60
```

Entitlement ID: ff6a-cf25-7c72-4b15-9d49-945e-4b2f-519f
Product ID: NAME=PhotoPrint-client;VERSION=12.0
Suite ID: NONE
Expiration date: 29-Nov-2016
Feature line(s):

```
INCREMENT PrintToPDF demo 12.3 29-nov-2016 1 ISSUER="My Corporation" \  
ISSUED=29-nov-2015 START=28-nov-2015 SIGN="003F 469C FAA0 F579 \  
2035 9632 BDAB B500 67F2 72CE 68BA FF86 4FC8 4123 FF47" \  
INCREMENT Print demo 12.3 29-nov-2016 1 ISSUER="My Corporation" \  
ISSUED=29-nov-2015 START=28-nov-2015 SIGN="0072 6DC3 2310 9577 \  
9B9D 781E 36BC 0900 0E73 A2B7 C4A3 99FF BCA0 F23F 1D94" \  
INCREMENT PrintHighQualityColor demo 12.3 29-nov-2016 1 ISSUER="My \  
Corporation" ISSUED=29-nov-2015 START=28-nov-2015 SIGN="0080 \  
7DCA A76B 32CD 539C D4D2 F8C5 E900 8A05 0830 DEC5 8686 FB52 \  
2E64 B961" \  
-----
```

Review the license rights output, noting the information on these lines: Trust Flags, Fulfillment Type, Status, Product ID, Expiration date, and Feature line(s).

5. In FlexNet Operations, click **Licenses > Licenses**. The **Support Licenses And Maintenance** page appears.
6. On the list, search for product PhotoPrint-client and review the license details. Note that count is 1 because 1 PhotoPrint-client license is activated. Note the fulfillment date and expiration.

Server-Side Online Activation

In this exercise, you perform a server-side online activation of the PhotoPrint-server product license.

Prerequisites

If necessary, refer to the section [Getting Started with Entitlement Management](#) to:

- Deploy the Enterprise Activation license model ([Deploying a License Technology and Model](#))
- Copy product PhotoPrint-client and save it as PhotoPrint-server ([Creating a Product](#))
 - a. Click **Products > Products**
 - b. Search for and select the PhotoPrint-client check box, then click **Copy**
 - c. Under **Create a Product**, in the **Product Name** field, type PhotoPrint-server and click **Save**
- Link PhotoPrint-server to the Enterprise Activation license model ([Linking a License Model to a Product](#)). Remove (unlink) the Retail Activation license model and save PhotoPrint-server.
- Deploy the PhotoPrint-server product ([Deploying a Product](#))
- Create and configure an entitlement called ENT-PhotoPrint-server ([Creating and Configuring an Entitlement](#)):
 - for end customer Lisa Barry of BarryPhoto
 - with a product PhotoPrint-server line item for a quantity of 3 copies and a license that starts at the first activation date and has a duration of 1 year
- Save and deploy the ENT-PhotoPrint-server entitlement ([Deploying an Entitlement](#))



Task *To activate a license using servercomptranutil*

1. In FlexNet Operations, click **Entitlements > List Entitlements**. The **List Entitlements** page appears.
2. On the **Activatable Line Items** list, search for entitlement ID ENT-PhotoPrint-server and review the line item details. Note that available quantity and total quantity are 3 for product PhotoPrint-server. Expiration is in 1 year.
3. At a command prompt in the <platform_dir>, enter the following for a count of 2, where <act_ID> is the FlexNet Operations PhotoPrint-server activation ID:

```
servercomptranutil -t http://<hostname:port>/flexnet/services/ActivationService -a <act_ID> count=2
```

Output is similar to

```
Server http://localhost:8888/flexnet/services/ActivationService, comms type SOAP
Status: 4, Creating request
Status: 5, Request created
Status: 6, Context created
Status: 7, Connected to remote server
Status: 8, Request Sent
Status: 9, Polling for response
Status: 10, Waiting for response
Status: 9, Polling for response
Status: 11, Done
Response processed successfully. Actions were:
    Configuration TrustedId "13"
    Create fulfillment "FID_c40614fd_1489_4e28_9bb6_c5872fadb51b"
```

4. At a command prompt in the <platform_dir>, to view the new license rights in server-side trusted storage, enter

```
serveractutil -view
```

Output is similar to

```
-----
Trust Flags: FULLY TRUSTED
Fulfillment Type: PUBLISHER ACTIVATION
Status: ENABLED
Fulfillment ID: FID_c40614fd_1489_4e28_9bb6_c5872fadb51b
Entitlement ID: 4dff-ff10-c75a-432e-8dbf-8bc3-066b-ff1c
Product ID: NAME=PhotoPrint-server;VERSION=12.0
Suite ID: NONE
Expiration date: 29-Nov-2016
Concurrent: 0
Concurrent overdraft:0
Hybrid: 0
Hybrid overdraft: 0
Activatable: 2
Activatable overdraft: 0
Repairs: 0
Feature line(s):

INCREMENT PrintToPDF demo 12.3 29-nov-2016 1 ISSUER="My Corporation" \
ISSUED=29-nov-2015 START=28-nov-2015 SIGN="003F 469C FAA0 F579 \
2035 9632 BDAB B500 67F2 72CE 68BA FF86 4FC8 4123 FF47"
```



```
INCREMENT Print demo 12.3 29-nov-2016 1 ISSUER="My Corporation" \
ISSUED=29-nov-2015 START=28-nov-2015 SIGN="0072 6DC3 2310 9577 \
9B9D 781E 36BC 0900 0E73 A2B7 C4A3 99FF BCA0 F23F 1D94"
INCREMENT PrintHighQualityColor demo 12.3 29-nov-2016 1 ISSUER="My \
Corporation" ISSUED=29-nov-2015 START=28-nov-2015 SIGN="0080 \
7DCA A76B 32CD 539C D4D2 F8C5 E900 8A05 0830 DEC5 8686 FB52 \
2E64 B961"
```

Review the license rights output, noting the information on these lines: Trust Flags, Fulfillment Type, Status, Product ID, Expiration date, Activatable, and Feature line(s).

5. Record the Entitlement ID for later use in [Step 1](#) of the [To activate a local license using appactutil](#) task in the [Local Online Activation](#) exercise.
6. In FlexNet Operations, click **Licenses > Licenses**. The **Support Licenses and Maintenance** page appears.
7. On the licenses list, search for product PhotoPrint-server and review the license details. Note that the count is 2 because 1 PhotoPrint-server license is activated. Note the fulfillment date and expiration.
8. Click **Entitlements > List Entitlements**. The **List Entitlements** page appears. On the **Activatable Line Items** list, search for entitlement ID ENT-PhotoPrint-server and review the line item details. Note that available quantity is reduced to 1 and total quantity is 3 for product PhotoPrint-server. Note the expiration.

Local Online Activation

In this exercise, you activate a PhotoPrint-server license from the FlexNet license server's trusted storage on the client.



Task **To activate a local license using** appactutil

1. At a command prompt in the <platform_dir>, to activate a server-side license in client-side trusted storage, enter

```
appactutil -served -commServer <port@hostname> -entitlementID <ent_ID>
```

where

- <port@hostname> is 27000@localhost, the license server



Note - For purposes of this exercise, the default port number 27000 is used. If 27000 is not the port assigned to the license server, specify the correct one in the command.

- <ent_ID> is the Entitlement ID you recorded in [Step 5](#) of the [Server-Side Online Activation](#) exercise

This command does the following:

- Creates an activation request that contains the entitlement ID
- Sends the activation request to the license server



Note - In your production environment, best practice is not to assign a default port for the license server. Instead, for security purposes, assign a port number outside of the range 27000 through 27009.

- Places one fulfillment record from the license server's trusted storage into the client machine's trusted storage

Output is similar to

Generating activation request using:

```
Entitlement ID = 4dff-ff10-c75a-432e-8dbf-8bc3-066b-ff1c
Expiration = 29-Nov-2016
```

ACTIVATION REQUEST SUCCESSFULLY PROCESSED

ProductID NAME=PPrint-server;VERSION=12.0, FulfillmentID FID-1448810769

2. At a command prompt in the <platform_dir>, to view the new license rights in client-side trusted storage, enter

appactutil -view

Output is similar to

```
-----
Trust Flags: FULLY TRUSTED
Fulfillment Type: PUBLISHER ACTIVATION
Status: ENABLED
Fulfillment ID: FID_d7a83787_46d6_43b1_a65b_ad85e135aa60
Entitlement ID: ff6a-cf25-7c72-4b15-9d49-945e-4b2f-519f
Product ID: NAME=PhotoPrint-client;VERSION=12.0
Suite ID: NONE
Expiration date: 29-Nov-2016
Feature line(s):

INCREMENT PrintToPDF demo 12.3 29-nov-2016 1 ISSUER="My Corporation" \
    ISSUED=29-nov-2015 START=28-nov-2015 SIGN="003F 469C FAA0 F579 \
    2035 9632 BDAB B500 67F2 72CE 68BA FF86 4FC8 4123 FF47"
INCREMENT Print demo 12.3 29-nov-2016 1 ISSUER="My Corporation" \
    ISSUED=29-nov-2015 START=28-nov-2015 SIGN="0072 6DC3 2310 9577 \
    9B9D 781E 36BC 0900 0E73 A2B7 C4A3 99FF BCA0 F23F 1D94"
INCREMENT PrintHighQualityColor demo 12.3 29-nov-2016 1 ISSUER="My \
    Corporation" ISSUED=29-nov-2015 START=28-nov-2015 SIGN="0080 \
    7DCA A76B 32CD 539C D4D2 F8C5 E900 8A05 0830 DEC5 8686 FB52 \
    2E64 B961"
```

```
-----
Trust Flags: FULLY TRUSTED
Fulfillment Type: SERVED ACTIVATION
Status: ENABLED
Fulfillment ID: FID-1448810769
Entitlement ID: 4dff-ff10-c75a-432e-8dbf-8bc3-066b-ff1c
Product ID: NAME=PhotoPrint-server;VERSION=12.0
Suite ID: NONE
Expiration date: 29-Nov-2016
Feature line(s):

INCREMENT PrintToPDF demo 12.3 29-nov-2016 1 ISSUER="My Corporation" \
    ISSUED=29-nov-2015 START=28-nov-2015 SIGN="003F 469C FAA0 F579 \
```

```
2035 9632 BDAB B500 67F2 72CE 68BA FF86 4FC8 4123 FF47"  
INCREMENT Print demo 12.3 29-nov-2016 1 ISSUER="My Corporation" \  
ISSUED=29-nov-2015 START=28-nov-2015 SIGN="0072 6DC3 2310 9577 \  
9B9D 781E 36BC 0900 0E73 A2B7 C4A3 99FF BCA0 F23F 1D94"  
INCREMENT PrintHighQualityColor demo 12.3 29-nov-2016 1 ISSUER="My \  
Corporation" ISSUED=29-nov-2015 START=28-nov-2015 SIGN="0080 \  
7DCA A76B 32CD 539C D4D2 F8C5 E900 8A05 0830 DEC5 8686 FB52 \  
2E64 B961"
```

Review the two sets of license rights output, noting the information on these lines: Trust Flags, Fulfillment Type, Status, Product ID, Expiration date, and Feature line(s). Compare the fulfillment types of the two sets—for PhotoPrint-client the type is PUBLISHER ACTIVATION and for PhotoPrint-server the type is SERVED ACTIVATION.

Trusted Storage License Activation Next Steps

License support is the stage of the FlexNet Operations license lifecycle that follows license activation. Support includes return of licenses. The exercises in the next topic use products PhotoPrint-client and PhotoPrint-server to guide you through basic FlexNet Operations trusted storage license support tasks.

Trusted Storage License Activation Advanced Topics

Short Code Activation

Short code (keyboard) activation is intended for customers who do not have the network connection resources needed for typical activation transactions, and must activate a product manually, such as over the telephone. This is typically done for machines not connected to a network. Short code activation of a local license server is also supported.

License rights are loaded from an Activation Specification Record (ASR) file using an activation transaction that requires a specific code, called a short code because it is not the prohibitively long code used in typical activations. Using a short code ASR, a customer provides a short request code and receives a short response code, over the telephone, that can be typed into the application interface. For more information, see [Short Code Activations](#).

Manual Activation

Manual activation is useful when there is no Internet connectivity directly on the host. The activation request is generated and written to a file by a FlexNet Publisher activation utility running on the machine where the license is to be activated, then the request is emailed to the publisher. The publisher uses FlexNet Operations to generate the response XML file. Alternatively, the customer can use the End-User Portal to submit and receive the response XML file. For more information, see [Manual Activations](#).

Trusted Storage License Support

This topic introduces trusted storage license support, the stage of the FlexNet Operations license lifecycle that follows license activation. Trusted storage license support includes returning licenses.

The exercise in this topic guides you through basic FlexNet Operations trusted storage license support.



Note ▪ To use the exercise in this topic, you must be familiar with the FlexNet Publisher Licensing Toolkit. For more information, refer to the FlexNet Publisher document “Getting Started with Trusted Storage-Based Licensing”.

Trusted Storage Key Concepts

After a license is activated, support becomes an important part of the license lifecycle. Changes resulting from business decisions such as the repackaging of products or introduction of maintenance, and end user events such as purchase of a new machine affect the license lifecycle.

Many types of license change management for trusted storage-based licenses—including returns, repairs, rehosts, upgrades, upsells, and renewals—are supported by FlexNet Operations.

Returning a Trusted Storage License

FlexNet Operations supports three types of trusted storage license return:

- **Online Return**
- **Short Code Return** (also called phone-based return)
- **Manual Return** (also called email-based return)



Note ▪ The commands and exercises in this getting started section are based on a Windows platform installation of the FlexNet Publisher Licensing toolkit. To do the exercises on a UNIX machine, you must adjust the path and file name syntax for the UNIX environment.



Note ▪ For sample commands shown in this getting started section, it is assumed that FlexNet Operations and the activation utilities are running on the same system. If not, replace `localhost:8888` with the appropriate host and port values.

Online Return

If an end user’s machine has Internet access, the end user can return a license using an activation utility. Unlike license file-based licenses, return of a trusted storage license is a secure operation; the user can no longer use the license after it is returned.

Composite Transaction

Online returns can be performed using the composite transaction activation utilities `appcomptranutil` and `servercomptranutil`. To perform multiple returns in the same command, append each additional return to the command with `-r <fulfill_ID>` and `reason=<reason_code>`. For example,

```
appcomptranutil -t http://localhost:8888/flexnet/services/ActivationService  
-r <fulfill_ID1> reason=0 -r <fulfill_ID2> reason=0 -r <fulfill_ID3> reason=0
```



Note - To successfully perform multiple returns in a single command, all fulfillments must belong to the same account, use the same license type (client or server), and be performed on the same machine.

Legacy, Single Transaction

For legacy versions of FlexNet Operations, `appactutil` and `serveractutil` are still supported to perform license lifecycle operations.

Trusted Storage Exercises

This exercise uses examples to guide you through the following trusted storage license support task:

Exercise	Description
Client-Side Online Return	Perform a client-side online return of a PhotoPrint-client product license.

Client-Side Online Return

In this exercise, you perform a client-side online return of the PhotoPrint-client product license.



Task To return a license using `appcompranutil`

- To view the PhotoPrint-client and PhotoPrint-server license rights in client-side trusted storage, at a command prompt in the `<platform_dir>`, enter

```
appcompranutil -view
```

Output is similar to

Viewing application trusted storage.

```
U if untrusted
. D if disabled
. . fulfillmentType
. . . Expiry    Count FulfillmentId                ProductId

. . 6 29-Nov-2016  1 FID_d7a83787_46d6_43b1_a65b_ad85e135aa60 NAME=PhotoPrint-client
;VERSION=12.0
. . 4 29-Nov-2016  1 FID-1448810769                                NAME=PhotoPrint-server;VERSION=
12.0
```

Viewed 2 of 2 fulfillment records.

- From its fulfillment record, record the fulfillment ID of the PhotoPrint-client license to be returned.
- In the `<platform_dir>` on the client, enter this command, where `<Fulfill_ID>` is the PhotoPrint-client fulfillment ID:

```
appcompranutil -t http://localhost:8888/flexnet/services/ActivationService
-r <Fulfill_ID> reason=0
```

Output is similar to

```
Server http://localhost:8888/flexnet/services/ActivationService, comms type SOAP
Status: 4, Creating request
Status: 5, Request created
Status: 6, Context created
Status: 7, Connected to remote server
Status: 8, Request Sent
Status: 9, Polling for response
Status: 10, Waiting for response
Status: 9, Polling for response
Status: 11, Done
Response processed successfully. Actions were:
Delete      fulfillment "FID_d7a83787_46d6_43b1_a65b_ad85e135aa60"
```

4. Enter one of the following commands in the <platform_dir> and note that the PhotoPrint-client fulfillment was deleted from trusted storage:

```
appcomptranutil -view
```

or

```
appactutil -view
```

In FlexNet Operations, click **Entitlements > List Entitlements** and note that the PhotoPrint-client copy was returned to the FlexNet Operations **List Entitlements** list (**Available Quantity** is 1, **Total Quantity** is 1). Click **Licenses > Licenses** and note that the PhotoPrint-client fulfillment was deleted from the list on the **Support Licenses And Maintenance** page.

Trusted Storage Advanced Topics

Online Repair

A trusted storage license repair is necessary when the license becomes invalid because the machine hardware configuration changed enough to exceed the tolerance for the machine bindings, or the anchor is broken.

Most trusted repairs are done programmatically but they can also be done through the FlexNet Operations Producer Portal or the End-User Portal. The number of allowed license repairs per unit time per line item is governed by a policy on the license model or the line item.

Reason Codes

Certain FlexNet Operations activation and return requests include reason codes to identify the nature of the request. Reason codes are supported only for activation and change management requests coming from server activation utilities; reason codes are not supported for retail activation models.

The meanings of these reason codes depend, in part, on whether the request is an activation or a return.

Note that while reason codes accompany certain activation and return requests, not all requests require or include reason codes. For example, normal activation requests do not include reason codes, nor do repair requests.

Short Code Return

As with short code (keyboard) activation, if an end user's machine has no Internet access, the end user can still return a license using a short code. Fulfillment records generated using online, manual, or short code activation can all be returned using short codes. Short code returns are not supported by composite transaction utilities.

Short Code Repair

As with short code (keyboard) activation, if an end user's machine has no Internet access, the end user can still repair a license using a short code. Fulfillment records generated using online, manual, or short code activation can all be repaired using short codes. Short code repairs are not supported by composite transaction utilities.

Manual Return

As with manual activation, if an end user's machine has no Internet access, the end user can still return a license using an XML file. Fulfillment records generated using online or manual activation can all be returned manually using XML files. Fulfillments generated using short code (keyboard) activation cannot be returned using this method.

Manual Repair

As with manual activation, if the end user machine has no Internet access, the end user can still repair a license using an XML file. Fulfillment records generated using online or manual activation can all be repaired manually using XML files. Fulfillments generated using short code (keyboard) activation cannot be repaired using this method.

Manual repairs can be performed using composite transaction utilities or single transaction utilities. Manual repairs executed with composite transaction utilities can perform multiple repairs in a single command. Append each additional repair to the command with `-e <fulfillment_ID>`.

Rehosting a License

Moving a license from one machine to another is called *rehosting* a license.

Upgrading a License

Changing from one version of a product to an improved version is called *upgrading* a license. For example, a customer can upgrade a license for Paint 4.0 software to one for Paint 5.1.

Upselling a License

Changing from one product to another with more capabilities is called *upselling* a license. For example, a customer who has a license for a four-function Basic Calculator can be upsold to the Scientific Calculator, which is designed for engineers and scientists.

Renewing a License

Extending an expiring license is called *renewing* a license. For example, a customer whose software license expires after one year can renew it for another year.

Reinstalling a License

Over time, an end customer may reinstall an operating system on the client machine or reinstall a FlexEnabled application. In this case, the customer usually wants to get the original license back without consuming an additional count from the entitlement. FlexNet Operations uses the Unique Machine Number (UMN) of the client machine to determine that the user is indeed reinstalling the application.

A reinstall works differently for a server activation request. Because it is common for a server to send an activation request for the same activation ID multiple times to activate a few copies each time, an additional parameter is added to the activation request to indicate that it is a reinstall. FlexNet Operations obsoletes all the existing fulfillment records for the given activation ID and UMN, and generates a new fulfillment record based on the parameters in the reinstall activation request.

For both client and server activations, when a fulfillment record is identified as a reinstall, fulfillment history on the line item is updated.

Getting Started with FlexNet Publisher License File-Based Licensing

This section *Getting Started with FlexNet Publisher License File-Based Licensing* presents fundamental FlexNet Operations concepts and uses exercises to lead a Producer Portal user through basic certificate license activation and support. The intended audience for this getting started section is the first-time Producer Portal user, or one without FlexNet Operations training or experience.

Topic	Description
Introduction	Overview of this getting started section, exercise prerequisites, and a summary of the FlexNet Operations license lifecycle.
Certificate License Activation	FlexNet Operations certificate licensing concepts and exercises that demonstrate how to generate a certificate license and review fulfillment history after activation. Brief descriptions of advanced certificate license activation topics with references for more information.
Certificate License Support	FlexNet Operations certificate licensing support concepts and exercises that demonstrate how to return a certificate license and review fulfillment history after the license is returned. Brief descriptions of advanced certificate license support topics with references for more information.

Introduction

To view a brief, informative video that walks you through the exercises in *Getting Started with FlexNet Publisher License File-Based Licensing*, click [here](#). We recommend that you read this getting started section in full, to gain an understanding of the concepts it covers, before you view the video.

Prerequisites

Before you begin the exercises in this getting started section:

- Demonstration data must be loaded in your environment



Important - Contact Reverera Support if demonstration data is not loaded.

- You must have a FlexNet Operations Producer Portal login and a System Administrator role
- You must complete the exercises in the section [Getting Started with Entitlement Management](#).

The License Lifecycle: FlexNet Publisher License File-Based Licensing

The FlexNet Operations license lifecycle is a repeating process of producer and customer activities, as depicted in the figure and described below.



Figure 12-1: FlexNet Operations License Lifecycle

- **Create Products** – Create product definitions that are used to generate licenses.
- **Order/Entitle** – Define an customer account's rights to obtain licenses for your products.
- **Deliver/Install** – Deliver the application software to the customer and install that software.
- **Activate** – Deliver licenses to the customer.
- **Return/Rehost** – Manage license transfers from one user or system to another.
- **Maintain/Update** – Deliver software and license updates to the customer.
- **Upsell/Renew** – Renew customer licenses, or sell the customer additional product functionality.

Certificate License Activation

This topic introduces certificate licenses and their activation, the stage of the FlexNet Operations license lifecycle that follows delivery of the product's activation IDs to the customer. Activation is the process of requesting, generating, delivering, and installing license rights.

The exercises in this topic guide you through basic FlexNet Operations certificate license activation.

- [Certificate License Activation Key Concepts](#)
- [Certificate License Activation Exercises](#)
- [Certificate License Activation Next Steps](#)
- [Certificate License Activation Advanced Topics](#)

Certificate License Activation Key Concepts

Certificate License Models

Certificate-based license model types include combinations of nodelocked or floating and counted or uncounted:

- A *nodelocked uncounted* license model enables a product to be used on a specific computer system, with or without terminal server privileges. The end user can open unlimited instances of the product, but only on the nodelocked machine. This license model requires a host ID that uniquely identifies the nodelocked machine.
- A *nodelocked counted* license model allows a fixed number of licenses to be accessed over a network by a specified list of computer systems. The specific host IDs are provided by the customer and put in the license certificate. This model requires a license server system.
- A *floating counted* license model requires a license server system and allows a maximum number of licenses to be used at any one time on a network. This model is also called networked or concurrent licensing.
- With a *floating uncounted* license model, any number of product licenses are available for checkout from a license server system over a network.

After a product purchase has been registered with FlexNet Operations as an entitlement, a customer can obtain a license for the product. The license enables use of some or all of the product's capabilities, and contains information about the computers on which the software is to run, the expiration date, and the count of the entitlement's total quantity that has been activated. Before the license can be generated, the entitlement must be deployed in FlexNet Operations.

Generating Certificate Licenses

After a customer receives an activation ID, it can be presented to a software publisher's order entry department, which uses FlexNet Operations to generate the certificate-based license. The license is then emailed or delivered to the customer by other means.

A customer could also use the activation ID to log in to the End-User Portal, enabled by FlexNet Operations, and generate a license. Similarly, an end user who has purchased software from a reseller could either call in to the software publisher with a Web register key, or use the key to log in to the End-User Portal to generate a license.

Licenses are generated for one entitlement line item at a time. FlexNet Operations generates a fulfillment ID for each activation.

Certificate License Activation Exercises

These exercises use examples to guide you through the following certificate license activation tasks:

Exercise	Description
Generating a Certificate License	Generate a certificate license for 3 of the 10 copies of the PhotoPrint-cert product to which the customer is entitled.
Reviewing Fulfillment History after Activation	Review the fulfillment history of the PhotoPrint-cert entitlement.

Generating a Certificate License

In this exercise, you generate a certificate license for 3 of the 10 copies of the PhotoPrint-cert product to which the customer is entitled.

Prerequisites

Log in to the FlexNet Operations Producer Portal and use the referenced procedures in the section [Getting Started with Entitlement Management](#) to:

- Deploy the Floating Counted certificate license model ([Deploying a License Technology and Model](#))
- Copy product PhotoPrint and save it as PhotoPrint-cert ([Creating a Product](#)):
 - a. Click **Products > Products**
 - b. Search for and select the PhotoPrint check box, then click **Copy**
 - c. In the **Product Name** field, type **PhotoPrint-cert** and click **Save**
- Link PhotoPrint-cert to the Floating Counted license model ([Linking a License Model to a Product](#))
- Deploy PhotoPrint-cert ([Deploying a Product](#))
- Create and configure an entitlement called ENT-PhotoPrint-cert ([Creating and Configuring an Entitlement](#)):
 - for end customer Lisa Barry of BarryPhoto
 - for 10 copies of product PhotoPrint-cert with a license that starts at the first activation date and has a duration of 1 year
- Deploy the ENT-PhotoPrint-cert entitlement ([Deploying an Entitlement](#))



Task *To generate a certificate license from an entitlement*

1. Log in to the FlexNet Operations Producer Portal, if you have not already done so.
2. Click **Entitlements > List Entitlements**. The **List Entitlements** page appears.
3. In the **Activatable Line Items** table, search for and click the **Activation ID** link for the PhotoPrint-cert product. The **Line Item Details** window opens.

4. Review the details of the line item, noting that **Qty** and **Qty Remaining** are both 10, **Start Date Option** is Use First Activation Date, and **License Model** is Floating Counted. Click **Cancel** at the bottom to close the window.
5. In the **Activatable Line Items** table, select the PhotoPrint-cert line item check box and click **Activate**. The **List Entitlements** page for the line item appears.
6. To configure the host, click **Next**. Under **Generate Licenses**, click **Add New Host**. The **Create License Host** window opens.
7. On the **Server Hosts** drop-down list, select **ANY**. Click **OK** to add **ANY** to the host list and close the window.
8. Under **Generate Licenses**, select the **ANY** host check box, then click **Next**. The **List Entitlements | Configure Counts** page appears, listing the PhotoPrint-cert **Activation ID** and showing that **Qty** and **Unallocated Qty** are both 10.
9. Type 3 in the **Fulfill Count** field, then click **Next**. The **List Entitlements | Generate Licenses - Review** page appears.
10. Click **Verify** to verify the validity of the license, then click **Generate**. The **Generated Licenses** page appears, listing PhotoPrint-cert with **License Hosts** ANY and a **Count** of 3. Note the **Fulfill Date** and **Expiration**.
11. On the **Generated Licenses** page, click **Complete**. The **List Entitlements** page appears, listing PhotoPrint-cert with an **Available Quantity** of 7, **Total Quantity** of 10, and **Expiration** one year from the first activation date.
12. Click **Licenses > Licenses**. The **Support Licenses And Maintenance** page appears, listing PhotoPrint-cert with **License Hosts** ANY, and a **Count** of 3. Note the **Fulfill Date** and **Expiration**.
13. Click the PhotoPrint-cert **Fulfillment ID** link to review the information in the **Fulfillment Details** window, then click **Cancel** at the bottom to close the window.
14. On the **Support Licenses And Maintenance** page, select the check box next to the PhotoPrint-cert license, then click **Save to File**. When you are asked whether you want to open or save the license file, select **Open**.
15. Review the contents of the license file, which look similar to:

```
#Please Do not delete this comment line.
SERVER this_host ANY
VENDOR demo
USE_SERVER
INCREMENT PrintToPDF demo 12.3 7-jul-2016 3 ISSUER="My \
  Corporation" ISSUED=7-jul-2015 START=6-jul-2015 SIGN="0044 \
  55B7 BB28 9979 433E B0A6 66FB E600 2D54 F9A8 18CC F949 56FA \
  1E93 ADAE"
INCREMENT Print demo 12.3 7-jul-2016 3 ISSUER="My \
  Corporation" ISSUED=7-jul-2015 START=6-jul-2015 SIGN="0003 \
  5E3B 1F67 5DDE AB6C 69AA DA34 6600 4879 A4C9 C9CE ABE9 0F33 \
  2FC2 715B"
INCREMENT PrintHighQualityColor demo 12.3 7-jul-2016 3 \
  ISSUER="My Corporation" ISSUED=7-jul-2015 START=6-jul-2015 \
  SIGN="006D D640 5E71 98AD 21FB 32F4 7391 CD00 520F 044C 9578 \
  938A 1DCE FB14 5CCA"
```

Note that any host can be used, a license server is required, and note that the count is 3 in the licensing information of each of the three features in the product. Close the license file when you are done.

Reviewing Fulfillment History after Activation

In this exercise, you review the fulfillment history of the PhotoPrint-cert entitlement.



Task To review the fulfillment history of the entitlement

1. Click **Entitlements > List Entitlements by Order**. The **List Entitlements by Order** page appears.
2. In the **Entitlements** list, search for the PhotoPrint-cert product line item (the **Entitlement ID** is ENT-PhotoPrint-cert) and click the ENT-PhotoPrint-cert entitlement ID link. The **Entitle Customers to Licenses** page appears.
3. Under **Line Items**, in the list on the **Line Items** tab, search for the PhotoPrint-cert line item whose history you want to review.
4. Click the **Fulfill History** link under the PhotoPrint-cert line item's **Activation ID**. The **Fulfillment History** window opens for the line item.
5. Review the PhotoPrint-cert line item's fulfillment history, noting that a count of 3 of the entitlement's **Total Quantity** of 10 are activated, then click **OK** to close the window.
6. Log out of the FlexNet Operations Producer Portal or continue with [Certificate License Support](#).

Certificate License Activation Next Steps

License support is the stage of the FlexNet Operations license lifecycle that follows license activation. Support includes return of licenses. The exercises in the next topic use product PhotoPrint-cert to guide you through basic FlexNet Operations certificate license support tasks.

Certificate License Activation Advanced Topics

Batch Activation

Batch activation is the simultaneous activation of multiple entitlement line items under these conditions:

- All line items are sold to the same account.
- If the line items use FlexNet Licensing, they must all use the same license model type.
- If the line items use a custom license technology, they must all use the same license technology.

For more information, see [What is Batch Activation?](#)

License Consolidation

License consolidation is combining multiple license certificates into a single license file for convenience. License consolidation can be done during batch activation or post-activation.

For more information, see [What is License Consolidation?](#)

Certificate License Support

This topic introduces certificate license support, the stage of the FlexNet Operations license lifecycle that follows license activation. Certificate license support includes returning licenses.

The exercises in this topic guide you through basic FlexNet Operations certificate license support.

Certificate License Support Key Concepts

After license activation, support becomes an important part of the license lifecycle. Changes resulting from business decisions such as the repackaging of products or introduction of maintenance, and end user events such as purchase of a new machine affect the license lifecycle.

Many types of license change management for certificate licenses—including returns, repairs, rehosts, upgrades, upsells and renewals—are supported by FlexNet Operations.

Returning a Certificate License

Returning a license means moving license rights back to an entitlement. After receiving certificate license rights for a certain count, a customer can return some of that count to the software publisher for re-licensing at a later time. The product entitlement's available quantity is increased by the count returned.

Certificate License Support Exercises

These exercises use examples to guide you through the following certificate license support tasks:

Exercise	Description
Returning a Certificate License	Return 1 of the 3 copies of the PhotoPrint-cert product you activated.
Reviewing Fulfillment History after a Return	Review the fulfillment history of the PhotoPrint-cert product after you return 1 copy.

Returning a Certificate License

In this exercise, you return 1 of the 3 copies of the PhotoPrint-cert product you activated in [Certificate License Activation](#).

Prerequisite

- Complete the exercises in [Certificate License Activation](#)



Task *To return a certificate license*

1. Log in to the FlexNet Operations Producer Portal, if you have not already done so.
2. Click **Licenses > Licenses**. The **Support Licenses And Maintenance** page appears with a fulfillments list.
3. Search for the PhotoPrint-cert fulfillment and select its check box.
4. Click **Support Actions > Return**. The **Support Licenses And Maintenance | Return Licenses For Fulfillment** page appears for the PhotoPrint-cert fulfillment.
5. Under **Fulfillment Details**, type 1 in the **Return Count** field, click **Verify** to verify the validity of the license, then click **Return**. The **Generated Licenses** page appears, showing an activated **Count** of 2 for the PhotoPrint-cert fulfillment.
6. Select the PhotoPrint-cert fulfillment's check box, then click **Save to File**. When you are asked whether you want to open or save the license file, select **Open**.
7. Review the contents of the license file, which look similar to:

```
#Please Do not delete this comment line.
SERVER this_host ANY
VENDOR demo
USE_SERVER
INCREMENT PrintToPDF demo 12.3 7-jul-2016 2 ISSUER="My \
  Corporation" ISSUED=7-jul-2015 START=6-jul-2015 SIGN="0017 \
  1E37 A59A 3E07 D0B5 996F 97A2 A700 1EC6 01C8 5B6D 16A7 7A6E \
  E916 B726"
INCREMENT Print demo 12.3 7-jul-2016 2 ISSUER="My \
  Corporation" ISSUED=7-jul-2015 START=6-jul-2015 SIGN="00B4 \
  CA1F 332D 4BA9 6732 9BD7 E5F4 D900 5DF2 47B8 EC89 EB50 1134 \
  0338 411B"
INCREMENT PrintHighQualityColor demo 12.3 7-jul-2016 2 \
  ISSUER="My Corporation" ISSUED=7-jul-2015 START=6-jul-2015 \
  SIGN="003D 832D 8000 3D58 B750 9401 03BA 3A00 244C 0351 A6C0 \
  489B C36E 2DB2 DB7C"
```

Note that the count in the licensing info for each of the three PhotoPrint-cert features is now 2. Close the license file when you are done.

8. On the **Generated Licenses** page, click **Complete**. The **Support Licenses and Maintenance** page appears, showing that **Count** is 2.

Reviewing Fulfillment History after a Return

In this exercise, you review the fulfillment history of PhotoPrint-cert after you return 1 of the 3 copies.



Task *To review the fulfillment history after a certificate license is returned*

1. Click **Entitlements > List Entitlements by Order**. The **List Entitlements by Order** page appears.
2. In the **Entitlements** list, search for the PhotoPrint-cert product line item with the **Entitlement ID** of ENT-PhotoPrint-cert.

3. Click the ENT-PhotoPrint-cert **Entitlement ID** link. The **Entitle Customers to Licenses** page appears.
4. Scroll down to the **Line Items** tab. In the **Line Items** list, search for the PhotoPrint-cert line item whose fulfillment history you want to review.
5. Click the **Fulfill History** link under the PhotoPrint-cert line item's **Activation ID**. The **Fulfillment History** window opens for the PhotoPrint-cert line item.
6. Review the PhotoPrint-cert line item's fulfillment history, noting that 3 of 10 copies were activated, then 1 copy was returned, leaving a count of 2. Click **OK** to close the window.

Certificate License Support Advanced Topics

Repairing a License

A customer may require support for a license key. A support request for a certificate license is processed as a *repair*, and involves the change of a license parameter other than a host ID. For more information, see [Repairing a License](#).

Rehosting a License

Moving a license from one machine to another is called *rehosting*. *Batch rehosting* is moving groups of licenses from one server to others by:

- *Redistributing* – re-allocating licenses for a group of products among various license servers to change the license count of products on different servers
- *Transferring* – moving all of an account's licenses from one host to another, usually when a host machine crashes and the licenses on it must be moved to a new machine

For more information, see [Rehosting a License](#).

Upgrading a License

Changing a license for one version of a product to a license for an improved version of the product is called *upgrading*. For example, a customer can upgrade a license for Paint 4.0 to one for Paint 5.1. For more information, see [Upgrade, Upsell, or Renew a Fulfillment](#).

Upselling a License

Changing a license for one product to a license for another product with more capabilities is called *upselling*. For example, a customer who has a license for AntiMalware can be upsold to the Total PC Protection package, which includes AntiSpam and ParentalControl in addition to AntiMalware. For more information, see [Upgrade, Upsell, or Renew a Fulfillment](#).

Renewing a License

Extending an expiring license is called *renewing* a license. For example, a customer whose software license expires after one year can renew it for another year. For more information, see [Upgrade, Upsell, or Renew a Fulfillment](#).

Correcting a Producer Error

Regeneration of a license may be required because of a *producer error*, such as incorrect data entry. For more information, see [Correcting a Publisher Error in a License](#). For more information, see [Upgrade, Upsell, or Renew a Fulfillment](#).

Generating an Emergency License

An *emergency license* is a short term license generated for a customer who cannot use the unexpired license. For example, while a customer's main computer is being upgraded or repaired, the product must be used temporarily on another computer. For more information, see [Generating an Emergency License](#).

Generating a Stop-Gap License

A *stop-gap license* is a short term license generated for a customer whose expired license renewal is being processed. For more information, see [Generating a Stop Gap License](#).

Getting Started with Non-FlexNet Licensing Technologies

This section *Getting Started with Non-FlexNet Licensing Technologies* presents fundamental FlexNet Operations concepts and uses exercises to guide a Producer Portal user through basic setup, activation, and support for non-FlexNet licensing. The intended audience for this getting started section is the first-time Producer Portal user, or one without FlexNet Operations training or experience.

Topic	Description
Introduction	Overview of this getting started section, an overview of the FlexNet Operations license lifecycle, non-FlexNet licensing concepts, and exercise prerequisites.
External SOAP Service Technology	Introduction to external SOAP service licensing. Exercises that demonstrate how to set up an external SOAP service license technology and license model, and activate and support external SOAP service licenses.
Manual Technology	Introduction to manual licensing. Exercises that demonstrate how to set up a manual license technology and license model, and activate and support manual licenses.
Hands-Free Technology	Introduction to hands-free licensing.
Non-FlexNet Licensing Technologies: Advanced Topics	Brief descriptions of advanced non-FlexNet licensing activation and support topics with references for more information.

Introduction

This section provides an overview of the FlexNet Operations license lifecycle, non-FlexNet licensing concepts, and exercise prerequisites.

- [Non-FlexNet License Technologies](#)
- [The License Lifecycle: Non-FlexNet Licensing Technologies](#)

- Exercise Prerequisites

Non-FlexNet License Technologies

In addition to Revenera's FlexNet license technology, FlexNet Operations can be integrated with other license technologies to unify disparate licensing systems and manage fulfillments. A non-FlexNet licensing technology generally fits into one of the following categories:

- External SOAP Service Technology
- Manual Technology
- Hands-Free Technology
- Replacement/Regenerative Technology, covered below

Replacement/Regenerative Technology

When a replacement licensing technology is used, the most recent license file on a host overrides all earlier licenses. Each time a license is generated, the licensing system calculates the total fulfillment count for each product on the host and generates a license; the license is not generated based on the fulfillment count in a single transaction or on the fulfillment record.

FlexNet Operations stores a master copy of the host license. Whenever a new license is generated for the host, or is returned, the master copy is modified. When a user downloads a license for a fulfillment record belonging to this host, the user receives the entire host license, not the individual fulfillment count of the fulfillment record. FlexNet Operations supplies only the master copy of the host license.

License Activation

After a product purchase is registered with FlexNet Operations as an entitlement and the entitlement is deployed, a customer can obtain a license for the product. The license enables use of some or all of the product's capabilities, and contains information about the computers on which the software is to run, the expiration date, and the count of the entitlement's total quantity that has been activated.

License Support

After license activation, support becomes an important part of the license lifecycle. Changes resulting from business decisions such as the repackaging of products or introduction of maintenance, and end user events such as purchase of a new machine affect the license lifecycle. Support operations include:

- Repairing a License – Customers may require support for license keys. Requests for license support are processed as *repairs*.
- Returning a License – *Returning* a license means moving license rights back to an entitlement. After receiving licenses for copies of a product, a customer can return some of them to the software producer for re-licensing at a later time. The customer's entitlement for the product is increased by the number of copies returned.

The License Lifecycle: Non-FlexNet Licensing Technologies

The FlexNet Operations license lifecycle is a repeating process of producer and customer activities, as depicted in the figure and described below.



Figure 13-1: FlexNet Operations License Lifecycle

- **Create Products** – Create product definitions that are used to generate licenses.
- **Order/Entitle** – Define a customer account’s rights to obtain licenses for your products.
- **Deliver/Install** – Deliver the application software to the customer and install that software.
- **Activate** – Deliver licenses to the customer.
- **Return/Rehost** – Manage license transfers from one user or system to another.
- **Maintain/Update** – Deliver software and license updates to the customer.
- **Upsell/Renew** – Renew customer licenses, or sell the customer additional product functionality.

Exercise Prerequisites

Before you begin the exercises in this getting started section:

- Demonstration data must be loaded in your environment



Important - Contact Reverera Support if demonstration data is not loaded.

- You must have a FlexNet Operations Producer Portal login and a System Administrator role
- You must complete the exercises in the section [Getting Started with Entitlement Management](#).

License Technology-Specific Prerequisites


- The external SOAP service must be deployed
- If there is no manual technology license generator configured for FlexNet Operations, create a text file on your Desktop called `NonFlexManualLicenseFile.lic` that contains the line
`This is a sample non-FlexNet, manual technology license file.`

External SOAP Service Technology

This topic introduces FlexNet Operations external SOAP service licensing and includes exercises that guide you through basic licensing setup, activation, and support.

External SOAP Service Technology: Key Concepts

Licenses that use an external SOAP service license technology are generated by a service that implements the FlexNet Operations **LicenseGeneratorService** Web Services Description Language (WSDL), an XML-based interface definition language that is used for describing the functionality offered by a web service. The external service is deployed in an application server independent of FlexNet Operations, as shown in the figure below, and is accessed by FlexNet Operations at run time for operations such as product and license model validation and license generation. The URL to the external service is linked to the custom generator when the license technology is created in FlexNet Operations.



External SOAP Service Technology: License Technology Set-Up

The exercises in this section use examples to guide you through these external SOAP service license set-up tasks:

Exercise	Description
External SOAP Service Technology: Setting Up and Deploying the License Technology	Set up and deploy the SOAPTech license technology.
External SOAP Service Technology: Setting Up and Deploying the License Model	Set up and deploy the SOAPModel license model of the SOAPTech license technology.
External SOAP Service Technology: Creating and Deploying the Product	Create and deploy product PhotoPrint-soap, which uses the SOAPTech license technology and SOAPModel license model.


External SOAP Service Technology: Setting Up and Deploying the License Technology

In this exercise, you set up and deploy the SOAPTech license technology, an uncounted license technology.



Task *To set up the external SOAP service license technology*

1. Log in to the FlexNet Operations Producer Portal if you have not already done so. The **Producer Portal Home** page appears.
2. Click **Administer > License Technologies**. The **License Technologies** page appears.
3. Click **Add a License Technology**. The **Create A License Technology** page appears.
4. Under **Create A License Technology**, enter the license technology information.
 - **Name:** Type SOAPTech
 - **Description:** Type External SOAP Service technology
 - **State:** Note that this license technology is created in a **Draft** state.
 - **Type?:** Select **External SOAP Service**
 - **Generator Service End Point:** Type this path:
{CUSTOM_TECH_HOST}/flexnet-licgen/services/LicenseGeneratorService
 - **Authentication type for service:** Select **None**

5. Click  to test the connection. Click **OK** in the message that says you have successfully connected to the service.
6. Scroll down the page and click **Add File Definition**. The **Create File Definition** window opens.
7. In the **Create File Definition** window, enter the file definition information.
 - **Name:** Type `SOAP_FILE_Definition`
 - **File Type:** Select **TEXT**.
 - **Description:** Type `Custom generator interface technology file definition`
8. Click **OK**. The window closes and the file definition is added to the **Create A License Technology** page. Click **Save** to save the new license technology.



Task *To deploy the external SOAP service license technology*

1. Click **Administer > License Technologies**. The **License Technologies** page appears and lists **SOAPTech** in the **Draft** state.
2. Select the **SOAPTech** check box, then click **Change State ?** and select **Deploy** from the drop-down menu. Click **OK** in the verification message that appears. In the **License Technologies** table, **SOAPTech** is shown with a **State** of **Deployed**. This message appears: Deployed the following License Technologies successfully
SOAPTech

External SOAP Service Technology: Setting Up and Deploying the License Model

In this exercise, you set up and deploy the `SOAPModel` license model.



Task *To set up the external SOAP service license model*

1. On the **Administer** menu, click **License Models**. The **Package Products – License Models** page appears.
2. Click **Create New License Model**. The **Package Products – License Models** page refreshes.
3. Under **Select A License Technology**, select **SOAPTech** from the **License Technology** menu, then click **Next**. The **Package Products – License Models** page refreshes.
4. Under **Create A License Model**, enter the license model information.
 - **Name:** Type `SOAPModel`
 - **Description:** Type `SOAP license model`
 - **State:** Note that the license model is created in a **Draft** state.
 - **License Technology:** Note that this is set to **SOAPTech**.
 - **Expiration:** Use the default value of **None**.
5. Click **Save** to create the `SOAPModel` license model. This message appears: License Model successfully created.



Task *To deploy the external SOAP service license model*

1. On the **Administer** menu, click **License Models**. The **Package Products – License Models** page appears. Search for and select the SOAPModel check box.
2. Click **Change State ?** and select **Deploy** from the drop-down menu. Click **OK** in the verification message that appears. This message appears: Deployed the following License Model(s) successfully SOAPModel. In the **License Models** table, SOAPModel is shown with a **State** of **Deployed**.

External SOAP Service Technology: Creating and Deploying the Product

In this exercise, you create a product called PhotoPrint-soap that uses the SOAPTech license technology and SOAPModel license model, then you deploy the product.



Task *To create product PhotoPrint-soap*

1. Click **Products > Products**. The **Package Products** page appears.
2. Click **Add New Product**. The **Package Products | Create A Product** page appears.
3. Under **Create A Product**, enter the product information:
 - **Product Name:** Type PhotoPrint-soap
 - **Version:** Type 12.3
 - **State:** Note that the product is created in a **Draft** state.
 - **License Technology:** Select SOAPTech
4. Click **Add Features**. The **Add Features To Product** window opens.
5. In the **Add Features To Product** window, search for feature name equals Print. Feature Print is listed under **Available Features**.
6. In the **Add Features To Product** window, under **Available Features**, select Print,12.3.
7. Click **Add ?** to move feature Print,12.3 to **Selected Features**, then click **Add**. The window closes and the feature is added to product PhotoPrint-soap.
8. Click **Save**. Note that product PhotoPrint-soap and its version appear in the list on the right side of the **Package Products** page. This message appears: Product PhotoPrint-soap successfully added.
9. Click **Next**. The **Package Products | Link License Models To Product** page appears.
10. Click **Link License Models**. The **Select License Models** window opens. Search for and select SOAPModel from **Available License Models**, then click **Add ?** to move it to **Selected License Models**.
11. Click **Add**. Product PhotoPrint-soap is linked to the SOAPmodel license model and the window closes.
12. On the **Package Products** page, click **Save**. Note that product PhotoPrint-soap is now listed under **Products Linked To License Models**. This message appears: License models linked successfully.



Task *To deploy product* PhotoPrint-soap

1. Click **Products > Products**. The **Package Products** page appears. Search for product PhotoPrint-soap and select its check box.
2. Click **Change State ?** and select **Deploy** from the drop-down menu. Click **OK** in the verification message. The **Package Products | Deploy Products** page appears for product PhotoPrint-soap.
3. Click **Deploy**. The Package Products page shows that PhotoPrint-soap is deployed. This message appears: Products deployed successfully.

External SOAP Service Technology: License Activation

The exercises in this section use examples to guide you through these external SOAP service license activation tasks:

Exercise	Description
External SOAP Service Technology: Entitling the Customer to the Product	Create, configure, and deploy the product PhotoPrint-soap entitlement.
External SOAP Service Technology: Activating the License	Activate a product PhotoPrint-soap license.

External SOAP Service Technology: Entitling the Customer to the Product

In this exercise, you create, configure, and deploy an entitlement for 3 copies of product PhotoPrint-soap.



Task *To create the product* PhotoPrint-soap **entitlement**

1. Click **Entitlements > Create**. The **Entitle Customers to Licenses** page appears.
2. Under **Create An Entitlement**, from the **Entitlement ID** list, select **Specify** and type **ENTL-soap** in the box that appears next to it. Note that the entitlement is created in a **Draft** state.
3. Under **End Customer And Channel Partners**, click **Add**. The **End Customer And Channel Partners** window opens.
4. On the **Customers** tab, search for and select BarryPhoto as the account to receive the entitlement, then click **Save**. The **End Customer And Channel Partners** window closes, and the **Entitle Customers to Licenses** page shows Barry Photography Studio as the end customer.



Task *To configure the product PhotoPrint-soap entitlement*

1. On the **Line Items** tab near the bottom of the page, click **New Line Item**. The **Configure Line Item** wizard opens.
2. In wizard step 1, **Select Product**, search for and select product PhotoPrint-soap, then click **Next**.
3. In wizard step 2, **Select Part Number & License Model**, leave the default values as they are. Click **Next**.
4. In wizard step 3, **Configure Product**, enter these line item attributes:
 - **Qty**: Type 3 for the quantity of PhotoPrint-soap copies in this line item
 - **Start Date**: Select **Use First Activation Date** from the drop-down list
 - **Expiration**: Select **Permanent**
 - Keep the default values for all other attributes.Click **Next**.
5. In wizard step 4, **Custom Attributes**, click **Next**.
6. In wizard step 5, **Order Type**, keep the default value as it is. Click **Save** to save the line item and close the **Configure Line Item** wizard.
7. On the **Line Items** tab, note that the line item for product PhotoPrint-soap is PERMANENT, has a total quantity of 3, and is in the **Draft** state.



Task *To deploy the product PhotoPrint-soap entitlement*

1. At the bottom of the **Entitle Customers to Licenses** page, click **Save & Deploy**. The page is refreshed, the **Line Item State** of PhotoPrint-soap is now **Deployed**, and this message appears: Entitlement deployed successfully.
2. On the **Entitle Customers to Licenses** page, click **Email** to send entitlement notification email to Barry Photography Studio. Type your email address in the **Ship To Email** box so you receive the certificate.



Note ▪ To include additional recipients, type their email addresses into the **Ship To Email** box separated by commas.

3. Click **Send**. The email is sent and this message appears: Email sent to the recipients <address list>.

External SOAP Service Technology: Activating the License

In this exercise, you activate a license for 1 copy of product PhotoPrint-soap. An external SOAP service license technology is integrated with FlexNet Operations using your technology's API. After collecting fulfillment data from the user, FlexNet Operations invokes your custom generator Java class to generate the license.



Task **To activate the external SOAP service license**

1. On the **Entitle Customers to Licenses** page, select the PhotoPrint-soap line item's check box and click **Activate**. The **List Entitlements** page appears.
2. In the **Activatable Line Items** table, click the **Activation ID** link for the PhotoPrint-soap line item. The **Line Item Details** window opens.
3. Review the details of the line item, noting that **Qty** and **Qty Remaining** are both 3, **Start Date Option** is Use First Activation Date, **Permanent** is true, and **License Model** is SOAPModel, then click **Cancel** at the bottom to close the window.
4. In the **Activatable Line Items** table, select the PhotoPrint-soap line item check box and click **Activate**. The **List Entitlements | Generate Licenses** page for the line item appears.
5. Click **Verify** to verify the validity of the license. This message appears: License is Valid.
6. Click **Generate**. The **Generated Licenses** page appears, listing PhotoPrint-soap with a **Count** of 1.
7. On the **Generated Licenses** page, click **Complete**. The **List Entitlements** page appears, listing the PhotoPrint-soap line item with an **Available Quantity** of 2, **Total Quantity** of 3, and **Expiration** of PERMANENT.
8. Click **Licenses > Licenses**. The **Support Licenses And Maintenance** page appears, listing product PhotoPrint-soap with a **Count** of 1.
9. Click the product PhotoPrint-soap **Fulfillment ID** link. The **Fulfillment Details** window opens.
10. Review the fulfillment information, then click **Cancel** at the bottom to close the window.
11. On the **Support Licenses And Maintenance** page, put a check mark in the product PhotoPrint-soap license's check box, then click **Save to File**. When you are asked whether you want to open or save the license file, select **Open**.
12. Review the contents of the license file, which look similar to:

```
Fulfillment
  fulfilment Id: FID_a9a12791_78e1_4eba_98e3_513f5fe335ad
  Count: 1
  OverDraft : 0
  StartDate : 08-03-2015
  ShipToEmail:
  CustomHost
  RequestType : ACTIVATION
  isVerifyRequest : false
  FULFILMENT Custom License Attribute
ActivationRecord
  Activation ID: 1233-37c1-99af-465c-976f-2909-4407-bcfe
  LineItem Attribute
  ENTITLEMENT Custom License Attribute
Entitlement
  EntitlementId : ENTL-soap
  OrderId : null
  OrderLineNumber:
  OrganizationUnit
    DisplayName : Barry Photography Studio
  OrganizationUnit Attribute
```

```

SoldToUser
  DisplayName : Lisa Barry
  FirstName  : Lisa
  LastName   : Barry
User Attribute
  DisplayName : John Barry
  FirstName  : John
  LastName   : Barry
User Attribute
Entitlement Attribute
Product
  Name      : PhotoPrint-soap
  Version   : 12.3
  Quantity Per Copy : 1
Product Attribute
  TestCustomAttribute: SOAP_TCA,
Features
  Print : 1, version : 12.3, isDateBased : false

  Featur Overrides
    NOTICE : null
    VENDOR_STRING : null
    ISSUER : null
    SERIAL_NUMBER : null
    DUP_GROUP : null
    REUSABLE : null
License
  Model Name: SOAPModel
  MODEL Custom License Attribute
License Technology
  Name: SOAPTech
  License file definition Name : SOAP_File_Def
  License file definition Type : TEXT
  LicenseFileType : TEXT
Logged In User : YourFirstName YourLastName
LoggedIn User Attribute

```

13. Close the license file window when you are done.

External SOAP Service Technology: License Support

The exercises in this section use examples to guide you through these external SOAP service license support tasks:

Exercise	Description
External SOAP Service Technology: Repairing the License	Repair the product PhotoPrint-soap license that you activated.
External SOAP Service Technology: Returning the License	Return the product PhotoPrint-soap license.

External SOAP Service Technology: Repairing the License

In this exercise, you repair the PhotoPrint-soap license.



Task *To repair the external SOAP service license*

1. Click **Licenses > Licenses**. The **Support Licenses And Maintenance** page appears.
2. On the **Support Licenses And Maintenance** page, search for and select the check box next to the product PhotoPrint-soap fulfillment.
3. Click **Support Actions** and select **Repair** from the drop-down menu. The **Support Licenses And Maintenance** page refreshes with the PhotoPrint-soap fulfillment information.
4. Click **Verify** to verify the validity of the license. This message appears: License is valid.
5. Click **Repair**. The **Generated Licenses** page appears with updated PhotoPrint-soap fulfillment information.
6. On the **Generated Licenses** page, click **Complete**. The **Support Licenses And Maintenance** page appears.
7. Click **Entitlements > List Entitlements by Order**, search for the ENTL-soap entitlement, then click on the ENTL-soap **Entitlement ID** link. The **Entitle Customers to Licenses** page for the entitlement appears.
8. Under **Line Items**, on the **Line Items** tab, click the **Fulfill History** link of the PhotoPrint-soap line item. The **Fulfillment History** window opens.
9. Review the fulfillment history for the PhotoPrint-soap line item. Note when it was initially activated and when it was repaired and reactivated. Click **OK** when you are done to close the **Fulfillment History** window.

External SOAP Service Technology: Returning the License

In this exercise, you return the PhotoPrint-soap license.



Task *To return the external SOAP service license*

1. Click **Licenses > Licenses**. The **Support Licenses And Maintenance** page appears.
2. On the **Support Licenses And Maintenance** page, search for and select the check box next to the product PhotoPrint-soap fulfillment.
3. Click **Support Actions** and select **Return** from the drop-down menu. The **Support Licenses And Maintenance** page refreshes with the PhotoPrint-soap fulfillment information.
4. Click **Verify** to verify the validity of the license. This message appears: License is valid.
5. Click **Return**. The **Support Licenses And Maintenance** page is refreshed, and a message similar to this appears: Successfully returned licenses for fulfillment FID_2d0cea6e_e9b8_441b_949b_caa858c30843
6. Click **Entitlements > List Entitlements by Order**, search for the ENTL-soap entitlement, then click on the ENTL-soap **Entitlement ID** link. The **Entitle Customers to Licenses** page appears.
7. Under **Line Items**, on the **Line Items** tab, click the **Fulfill History** link of the PhotoPrint-soap line item. The **Fulfillment History** window opens.


- Review the fulfillment history for the PhotoPrint-soap line item. Note when it was returned. Click **OK** when you are done to close the **Fulfillment History** window.

Manual Technology

This topic introduces FlexNet Operations manual licensing and includes exercises that guide you through basic licensing setup, activation, and support.

Manual Technology: Key Concepts

Licenses that use manual technology are manually generated by a customer support representative using a third-party system. Because this license generator is not integrated into FlexNet Operations, when a user generates a license, the generated fulfillment is placed on hold and an email is sent to the administrator. The administrator logs in to the third-party system and generates the license, then returns to FlexNet Operations to set the license on the on-hold fulfillment record. The user can then download the license. FlexNet Operations tracks fulfillment and other data.



Manual Technology: License Technology Set-Up

The exercises in this section use examples to guide you through these manual license set-up tasks:

Exercise	Description
Manual Technology: Setting Up and Deploying the License Technology	Set up and deploy the ManualTech license technology.

Exercise	Description
Manual Technology: Setting Up and Deploying the License Model	Set up and deploy the ManualModel license model of the ManualTech license technology.
Manual Technology: Creating and Deploying the Product	Create and deploy product PhotoPrint-manual, which uses the ManualTech license technology and ManualModel license model.

Manual Technology: Setting Up and Deploying the License Technology

In this exercise, you set up and deploy the ManualTech license technology, an uncounted license technology.



Task *To set up a manual license technology*

1. Click **Administer > License Technologies**. The **License Technologies** page appears.
2. Click **Add a License Technology**. The **Create A License Technology** page appears.
3. Under **Create A License Technology**, enter the license technology information.
 - **Name:** Type ManualTech
 - **Description:** Type Manual technology
 - **State:** Note that this license technology is created in a **Draft** state.
 - **Type?:** Select **Manual**
4. Scroll down the page and click **Add File Definition**. The **Create File Definition** window opens.
5. In the **Create File Definition** window, enter the file definition information.
 - **Name:** Type Manual_FILE_Definition
 - **File Type:** Select **TEXT**.
 - **Description:** Type Manual technology file definition
6. Click **OK**. The window closes and the file definition is added to the **Create A License Technology** page. Click **Save** to save the new license technology.



Task *To deploy the manual license technology*

1. Click **Administer > License Technologies**. The **License Technologies** page appears and lists **ManualTech** in the **Draft** state.
2. Select the **ManualTech** check box, then click **Change State ?** and select **Deploy** from the drop-down menu. Click **OK** in the verification message that appears. In the **License Technologies** table, **ManualTech** is shown with a **State** of **Deployed**. This message appears: Deployed the following License Technologies successfully ManualTech

Manual Technology: Setting Up and Deploying the License Model

In this exercise, you set up and deploy the ManualModel license model.



Task *To set up the manual license model*

1. Click **Administer > License Models**. The **Package Products – License Models** page appears.
2. Click **Create New License Model**. The **Package Products – License Models** page refreshes.
3. Under **Select A License Technology**, select ManualTech from the **License Technology** menu, then click **Next**. The **Package Products – License Models** page refreshes.
4. Under **Create A License Model**, enter the license model information.
 - **Name:** Type ManualModel
 - **Description:** Type Manual license model
 - **State:** Note that the license model is created in a **Draft** state.
 - **License Technology:** Note that this is set to ManualTech.
 - **Expiration:** Use the default value of **None**.
5. Click **Save** to create the ManualModel license model. This message appears: License Model successfully created.



Task *To deploy the manual license model*

1. Click **Administer > License Models**. The **Package Products – License Models** page appears. Search for and select the ManualModel check box.
2. Click **Change State ?** and select **Deploy** from the drop-down menu. Click **OK** in the verification message that appears. In the **License Models** table, ManualModel is shown with a **State** of **Deployed**.

Manual Technology: Creating and Deploying the Product

In this exercise, you create a product called PhotoPrint-manual that uses the ManualTech license technology and ManualModel license model, then you deploy the product.



Task *To create product PhotoPrint-manual*

1. Click **Products > Products**. The **Package Products** page appears.
2. Click **Add New Product**. The **Package Products | Create A Product** page appears.
3. Under **Create A Product**, enter the product information:
 - **Product Name:** Type PhotoPrint-manual
 - **Version:** Type 12.3

- **State:** Note that the product is created in a **Draft** state.
 - **License Technology:** Select ManualTech
4. Click **Add Features**. The **Add Features To Product** window opens.
 5. In the **Add Features To Product** window, search for feature name equals Print. Feature Print is listed under **Available Features**.
 6. In the **Add Features To Product** window, under **Available Features**, select `Print,12.3`.
 7. Click **Add ?** to move feature `Print,12.3` to **Selected Features**, then click **Add**. The window closes and the feature is added to product `PhotoPrint-manual`.
 8. Click **Save**. Note that product `PhotoPrint-manual` and its version appear in the list on the right side of the **Package Products** page. This message appears: `Product PhotoPrint-manual successfully added`.
 9. Click **Next**. The **Package Products | Link License Models To Product** page appears.
 10. Click **Link License Models**. The **Select License Models** window opens. Search for and select `ManualModel` from **Available License Models**, then click **Add ?** to move it to **Selected License Models**.
 11. Click **Add**. Product `PhotoPrint-manual` is linked to the `ManualModel` license model and the window closes.
 12. On the **Package Products** page, click **Save**. Note that product `PhotoPrint-manual` is now listed under **Products Linked To License Models**. This message appears: `License models linked successfully`.



Task *To deploy product* `PhotoPrint-manual`

1. Click **Products > Products**. The **Package Products** page appears. Search for product `PhotoPrint-manual` and select its check box.
2. Click **Change State ?** and select **Deploy** from the drop-down menu. Click **OK** in the verification message. The **Package Products | Deploy Products** page appears for product `PhotoPrint-manual`.
3. Click **Deploy**. The **Package Products** page shows that `PhotoPrint-manual` is deployed. This message appears: `Products deployed successfully`.

Manual Technology: License Activation

The exercises in this section use examples to guide you through these manual license activation tasks:

Exercise	Description
Manual Technology: Entitling the Customer to the Product	Create, configure, and deploy the product <code>PhotoPrint-manual</code> entitlement.
Manual Technology: Activating the License	Activate a product <code>PhotoPrint-manual</code> license.

Manual Technology: Entitling the Customer to the Product

In this exercise, you create, configure, and deploy an entitlement for 3 copies of product PhotoPrint-manual.



Task *To entitle the customer to product* PhotoPrint-manual

1. Click **Entitlements > Create**. The **Entitle Customers to Licenses** page appears.
2. Under **Create An Entitlement**, from the **Entitlement ID** list, select **Specify** and type **ENTL-manual** in the box that appears next to it. Note that the entitlement is created in a **Draft** state.
3. Under **End Customer And Channel Partners**, click **Add**. The **End Customer And Channel Partners** window opens.
4. On the **Customers** tab, search for and select BarryPhoto as the account to receive the entitlement, then click **Save**. The **End Customer And Channel Partners** window closes, and the **Entitle Customers to Licenses** page shows Barry Photography Studio as the end customer.



Task *To configure the product* PhotoPrint-manual *entitlement*

1. On the **Line Items** tab near the bottom of the page, click **New Line Item**. The **Configure Line Item** wizard opens.
2. In wizard step 1, **Select Product**, search for and select product PhotoPrint-manual, then click **Next**.
3. In wizard step 2, **Select Part Number & License Model**, leave the default values as they are. Click **Next**.
4. In wizard step 3, **Configure Product**, enter these line item attributes:
 - **Qty**: Type 3 for the quantity of PhotoPrint-manual copies in this line item
 - **Start Date**: Select **Use First Activation Date** from the drop-down list
 - **Expiration**: Select **Permanent**
 - Keep the default values for all other attributes.Click **Next**.
5. In wizard step 4, **Custom Attributes**, click **Next**.
6. In wizard step 5, **Order Type**, keep the default value as it is. Click **Save** to save the line item and close the **Configure Line Item** wizard.
7. On the **Line Items** tab, note that the line item for product PhotoPrint-manual is PERMANENT, has a total quantity of 3, and is in the **Draft** state.



Task **To deploy the product** PhotoPrint-manual **entitlement**

1. At the bottom of the **Entitle Customers to Licenses** page, click **Save & Deploy**. The page is refreshed, the **Line Item State** of PhotoPrint-manual is now **Deployed**, and this message appears: Entitlement deployed successfully.
2. On the **Entitle Customers to Licenses** page, click **Email** to send entitlement notification email to Barry Photography Studio. Type your email address in the **Ship To Email** box so you receive the certificate.



Note - To include additional recipients, type their email addresses into the **Ship To Email** box separated by commas.

3. Click **Send**. The email is sent and this message appears: Email sent to the recipients <address list>.

Manual Technology: Activating the License

In this exercise, you activate a license for 1 copy of product PhotoPrint-manual. Your manual technology generates the license, while FlexNet Operations tracks fulfillment and other data. Because there is no programmatic link between them, your customer service staff must transfer license data from the manual technology to FlexNet Operations.

The manual technology licensing work flow is:

- **On-hold Fulfillment** – The end user initiates the fulfillment. FlexNet Operations collects the relevant information, then creates an on-hold fulfillment record.
- **Email Notification** – FlexNet Operations sends email to notify customer service to begin the licensing process using your manual technology, with information collected in FlexNet Operations.
- **License Generation** – Your customer service staff generates the license using your manual technology.
- **Manual Update** – Your customer service staff manually updates the fulfillment record in FlexNet Operations and sets the license, which activates the fulfillment record and allows the user to download the license.



Task **To activate the manual license**

1. On the **Entitle Customers to Licenses** page, click **Activate**. The **List Entitlements** page appears.
2. In the **Activatable Line Items** table, click the **Activation ID** link for the PhotoPrint-manual product. The **Line Item Details** window opens.
3. Review the details of the line item, noting that **Qty** and **Qty Remaining** are both 3, **Start Date Option** is Use First Activation Date, **Permanent** is true, and **License Model** is ManualModel, then click **Cancel** at the bottom to close the window.
4. In the **Activatable Line Items** table, select the PhotoPrint-manual line item check box and click **Activate**. The **List Entitlements | Generate Licenses** page for the PhotoPrint-manual line item appears.
5. Click **Verify** to verify the validity of the license. This message appears: License is Valid.

6. Click **Generate**. The **Generated Licenses** page appears, listing PhotoPrint-manual with a **Count** of 1. This message appears:

License text has not been set for some of the fulfillments generated. The administrator has been notified. You will receive an email when the license is ready to download.
7. On the **Generated Licenses** page, click **Complete**. The **List Entitlements** page appears, listing the PhotoPrint-manual line item with an **Available Quantity** of 2, **Total Quantity** of 3, and **Expiration** of PERMANENT.
8. Click **Licenses > Licenses**. The **Support Licenses And Maintenance** page appears, listing product PhotoPrint-manual with a **Count** of 1. The **Type** is ON HOLD (denoted by the N icon).
9. Click the product PhotoPrint-manual **Fulfillment ID** link. The **Fulfillment Details** window opens.
10. Review the fulfillment information, then click **Cancel** at the bottom to close the window.
11. On the **Support Licenses And Maintenance** page, put a check mark in the product PhotoPrint-manual license's check box, then click **Set License**. The **Set License For Fulfillment** window opens.
12. In the **Set License For Fulfillment** window, browse to and select the appropriate **License File** for your scenario:
 - The actual license file generated by your manual license generator, or
 - the NonFlexManualLicenseFile.lic sample if no manual technology license generator is configured.

Click **OK**. The **Set License For Fulfillment** window closes. On the **Support Licenses And Maintenance** page, **Type** changes from ON HOLD to Non-Flexnet (denoted by the NF icon).
13. On the **Support Licenses And Maintenance** page, put a check mark in the product PhotoPrint-manual license's check box, then click **Save to File**. When you are asked whether you want to open or save the license file, select **Open**.
14. Review the contents of the license file and close the window when you are done.

Manual Technology: License Support

The exercises in this section use examples to guide you through these manual license support tasks:

Exercise	Description
Manual Technology: Repairing the License	Repair the product PhotoPrint-manual license that you activated.
Manual Technology: Returning the License	Return the product PhotoPrint-manual license.

Manual Technology: Repairing the License

In this exercise, you repair the PhotoPrint-manual license.



Task

To repair the manual license

1. Click **Licenses > Licenses**. The **Support Licenses and Maintenance** page appears.
2. On the **Support Licenses and Maintenance** page, search for and select the check box next to the product PhotoPrint-manual fulfillment.
3. Click **Support Actions** and select **Repair** from the drop-down menu. The **Support Licenses And Maintenance** page refreshes with the PhotoPrint-manual fulfillment information.
4. Click **Verify** to verify the validity of the license. This message appears: License is valid.
5. Click **Repair**. The **Generated Licenses** page appears with updated PhotoPrint-manual fulfillment information. **Type** is ON-HOLD (denoted by the N icon). This message appears: License text has not been set for some of the fulfillments generated. The administrator has been notified. You will receive an email when the license is ready to download.
6. On the **Generated Licenses** page, click **Complete**. The **Support Licenses And Maintenance** page appears.
7. Search for and select the check box next to the on-hold product PhotoPrint-manual fulfillment, then click **Set License**. The **Set License For Fulfillment** window opens.
8. Browse to the PhotoPrint-manual license file, then click **OK**. The **Set License For Fulfillment** window closes. The **Support Licenses And Maintenance** page is refreshed and the PhotoPrint-manual fulfillment is no longer on hold.
9. Click **Entitlements > List Entitlements by Order**, search for the product ENTL-manual entitlement, then click on the ENTL-manual link. The **Entitle Customers to Licenses** page appears.
10. Under **Line Items**, on the **Line Items** tab, click the **Fulfill History** link of the PhotoPrint-manual line item. The **Fulfillment History** window opens.
11. Review the fulfillment history for the PhotoPrint-manual line item. Note that it was repaired, generated and put on hold, and reactivated. Click **OK** when you are done to close the **Fulfillment History** window.

Manual Technology: Returning the License

In this exercise, you return the PhotoPrint-manual license.



Task


To return the manual license

1. Click **Licenses > Licenses**. The **Support Licenses and Maintenance** page appears.
2. On the **Support Licenses and Maintenance** page, search for and select the check box next to the product PhotoPrint-manual fulfillment.
3. Click **Support Actions** and select **Return** from the drop-down menu. The **Support Licenses And Maintenance** page refreshes with the PhotoPrint-manual fulfillment information.
4. Click **Verify** to verify the validity of the license. This message appears: License is valid.
5. Click **Return**. The **Support Licenses And Maintenance** page is refreshed. A message similar to this appears: Successfully returned licenses for fulfillment FID_8fbd3105_8d5e_41b2_99a9_c867bca9ff8d

6. Click **Entitlements > List Entitlements by Order**, search for the ENTL-handsfree entitlement, then click on the ENTL-handsfree link. The **Entitle Customers to Licenses** page appears.
7. Under **Line Items**, on the **Line Items** tab, click the **Fulfill History** link of the PhotoPrint-manual line item. The **Fulfillment History** window opens.
8. Review the fulfillment history for the PhotoPrint-manual line item. Note when it was returned. Click **OK** when you are done to close the **Fulfillment History** window.

Hands-Free Technology

Licenses that use hands-free technology are generated programmatically between a client and the FlexNet Operations server using a third-party system. A license request, usually in XML format, is submitted to the license server, which processes the request and sends a response to the client. The server generates the license and stores the license information in FlexNet Operations, where it is tracked.



Non-FlexNet Licensing Technologies: Advanced Topics

Brief descriptions of more advanced activation and support topics for producers who use FlexNet Operations with a non-FlexNet license technology are provided below. For more information about these advanced topics, refer to the *FlexNet Operations Web Services Integration Guide* or the *FlexNet Operations SOAP Web Services Guide*.

License Activation

File Definitions

If the license technology uses multiple license files, multiple license file types can be defined for a fulfillment record. A license file type can be text or binary.

Generator Validator

Implement the license model validator and product validator through an external SOAP service.

License Consolidator

Implement the custom license consolidator through an external SOAP service.

File Name Generator

Implement the custom file name generator through an external SOAP service.

Custom HostID String

Implement the custom HostID string through an external SOAP service.

License Support

Rehosting a License

Moving a license from one machine to another is called *rehosting*. *Batch rehosting* is moving groups of licenses from one server to others by:

- *Redistributing* – re-allocating licenses for a group of products among various license servers to change the license count of products on different servers
- *Transferring* – moving all of an account's licenses from one host to another, usually when a host machine crashes and the licenses on it must be moved to a new machine

Upgrading a License

Changing a license for one version of a product to a license for an improved version of the product is called *upgrading*. For example, a customer can upgrade a license for Paint 4.0 to one for Paint 5.1.

Upselling a License

Changing a license for one product to a license for another product with more capabilities is called *upselling*. For example, a customer who has a license for AntiMalware can be upsold to the Total PC Protection package, which includes AntiSpam and ParentalControl in addition to AntiMalware.

Renewing a License

Extending an expiring license is called *renewing* a license. For example, a customer whose software license expires after one year can renew it for another year.

Correcting a Producer Error

Regeneration of a license may be required because of a *producer error*, such as incorrect data entry.

Generating an Emergency License

An *emergency license* is a short term license generated for a customer who cannot use the unexpired license. For example, while a customer's main computer is being upgraded or repaired, the product must be used temporarily on another computer.

Generating a Stop-Gap License

A *stop-gap license* is a short term license generated for a customer whose expired license renewal is being processed.

Getting Started with Cloud Licensing Service



Version - Cloud Licensing Service features are only available for producers who purchase the Cloud Licensing Service module.

The purpose of this section *Getting Started with Cloud Licensing Service* is to provide an overview on the use of FlexNet Operations and FlexNet Cloud Licensing Service (a feature of FlexNet Operations). For FlexNet Operations users who use FlexNet Embedded licensing, the FlexNet Cloud Licensing Service allows the rapid deployment of cloud-hosted license servers.

This getting started section primarily describes concepts and tasks related to FlexNet Operations with FlexNet Cloud Licensing Service. For information about implementing a FlexNet Embedded client that communicates with license servers, see the appropriate FlexNet Embedded documentation. For example, the *FlexNet Embedded Client C SDK User Guide* or the *FlexNet Embedded Client C XT SDK User Guide*.

This getting started section is organized into the following sections.

Topic	Content
FlexNet Cloud Licensing Service Concepts	Provides general information about FlexNet Embedded license server terminology and tasks.
FlexNet Cloud Licensing Service Exercises	Provides a walkthrough of creating a cloud-hosted license server in FlexNet Operations.

To view a brief, informative video that walks you through the exercises in *Getting Started with Cloud Licensing Service*, click [here](#). We recommend that you read this getting started section in full, to gain an understanding of the concepts it covers, before you view the video.

Additional Documentation

In addition to this manual, you can consult the Swagger documentation, which provides more detailed information.

Depending on your AWS instance, use one of the following URLs to access the online REST API reference documentation:

`https://<siteID>-uat.compliance.flexnetoperations.eu/GlobalLicensingService/documentation`

`https://<siteID>-uat.compliance.flexnetoperations.com/GlobalLicensingService/documentation`

where <siteID> is your organization's site ID which is supplied by Revenera. For production environments, omit "-uat". For more information on <siteID>, see [About Your Site ID](#).

FlexNet Cloud Licensing Service Concepts

This section describes general concepts involved in working with FlexNet Operations, FlexNet Embedded, and FlexNet Cloud Licensing Service. The following are some of the concepts and terminology used throughout this documentation.

FlexNet Embedded Licensing

FlexNet Embedded license technology is intended for use by software publishers and intelligent device manufacturers.

Licensing software on each client (such as a device or a workstation) controls the feature set expressed. If the device has network connectivity, it can connect directly to FlexNet Operations and receive the license for its feature set. A device can also be activated off line or using a FlexNet Embedded license server. This getting started section focuses on a licensing model in which one or more clients interact with a cloud-hosted FlexNet Embedded license server.

FlexNet Embedded license technology also enables the use of perpetual, subscription, and demonstration license models in traditional software applications.

Embedded licenses are of two types:

- An *uncounted* license model allows a customer to deploy an unlimited number of licenses.
- A *counted* license model restricts deployment to a limited number of licenses. The count is specified during the entitlement process.

License Servers

Your served clients send capability requests to a FlexNet Embedded license server. In this getting started section, the license server is a license server instance hosted in the FlexNet Cloud Licensing Service that holds license rights for use by its served clients.

Auto-Provisioning

License servers can be created manually or, when the license model permits auto-provisioning, automatically generated by FlexNet Operations.

When auto-provisioning is permitted, FlexNet Operations generates a new license server when an entitlement using such a license model and owned by an end customer account, is deployed. Also, line items included in the entitlement are automatically mapped to the license server.

When auto-provisioning is not permitted, producers can create the license server manually. In this scenario, the producer uses the **Create License Server** page to create a license server for the end customer and then manually maps the entitlement line items to that server.

The exercises in this getting started section make use of auto-provisioning in the license model to streamline license server creation and entitlement mapping.

Limitations

The following limitations exist for auto-provisioned license servers that have entitlements mapped for metered features:

- License servers cannot be moved to another account.
- Only unused licenses for metered features can be removed using **Licenses > Remove Licenses**.
- License servers can be made obsolete, which will remove all licenses mapped to the server. However, this is not recommended, because future line items will not be mapped automatically to the auto-provisioned license server.

Features

A *feature* represents a licensable capability defined in a software application, and is the basic building block for a product. A feature could represent any of the following:

- a product consisting of one or more components
- a specific version of a product
- a part of a product
- one or more pieces of data (restricted through the access routines)

An example of a feature would be the Add function in a calculator, or the Print function in a word processing program.

You define the feature or features that make up your products in FlexNet Operations. Licensing code checks for the availability of certain features to determine a product's functionality.

During execution, your licensing code uses FlexNet Embedded functions that attempt to *acquire* a license. The FlexNet Embedded libraries validate such conditions as the feature not having expired. If the license acquisition succeeds, your code would then enable the corresponding capability.

Capability Requests and Responses

When your licensing code communicates with FlexNet Operations, the communications involve *capability requests* and *capability responses*. A capability request is generated by the client (requesting features that it will acquire). The request data contains some combination of a host identifier, one or more desired features, and other optional data to pass to FlexNet Operations.

The license server instance then processes the request, reading the various identifiers, desired features, and custom data. If FlexNet Operations determines that the client requires a response, it generates a capability response. The response data contains current license rights available for the client. The capability response is then conveyed back to the client, which processes the response, after which the features in the response can be queried for the sake of detecting if a quota has been exceeded or for feature clipping.

Your licensing code specifies one or more *desired features*, which represent features desired in the capability request.

Your code also specifies an *operation* in the capability request, which indicates whether a response is expected. The “request” operation is used in feature-clipping scenarios, where a response is needed.

Publishers and Publisher Identities

Before you use a FlexNet Embedded license technology, you must set up a publisher and identity on the FlexNet Operations Producer Portal. A publisher identity is binary data that contains a publisher or producer name and encryption data. A publisher is necessary to identify who the license belongs to and who can validate the license. An identity is used to secure communication between the back office and device.

Reverera supplies you with a unique publisher name and a series of five publisher keys. You use this name and these keys to set up a publisher. The keys cannot be regenerated or duplicated.

The publisher can define any number of identities, each providing a different level of security for different classes of devices or licenses. For example, a line of high-end devices may require higher security than a line of low-end devices. When an identity is created, a digital signature algorithm is selected to prevent forgery and tampering on the device.

FlexNet Cloud Licensing Service Exercises

This section describes how to get started with FlexNet Operations and FlexNet Cloud Licensing Service. You will learn about setting up a license server in FlexNet Operations and connecting your clients to their license server instance in FlexNet Cloud Licensing Service.

The section is divided into the following subsections.

Section	Description
Prerequisites	Prerequisites for included exercises.
Preparing FlexNet Operations	Exercises to create a license server in FlexNet Operations. This section includes creating your license models, features, products, and so forth.
Cloud Licensing Service: Obtaining the License Server URL	Instructions for determining the URL for the license server instance with which your served clients communicate for license rights.
Cloud Licensing Service: Running a Served Client Example	Brief discussion of how to confirm that counts can be successfully mapped from the license server to its FlexNet Embedded clients.

Prerequisites

The following items are prerequisites for developing and deploying licensing code with the FlexNet Operations Producer Portal and your FlexNet Embedded toolkit.

FlexNet Embedded Client Implementation

It is assumed that you have downloaded your FlexNet Embedded platform for implementing an application to obtain license rights from a license server. You should already have implemented FlexNet Embedded C SDK or FlexNet Embedded XT code for a connected application running in a customer environment. See the corresponding FlexNet Embedded documentation for information about building the example code and implementing a served client.

To complete the exercises in this getting started section, users also must have received publisher keys from Revenera.



Note • The creation of a publisher and an identity are covered in the section [Getting Started with FlexNet Embedded Licensing](#).

FlexNet Operations Instance

It is also assumed that you have access to FlexNet Operations via the Producer Portal and the End-User Portal. Producers must have already activated their producer account and user account activated on the Producer Portal in which FlexNet Embedded and FlexNet Cloud Licensing Service features are enabled.

Client Registration

Additionally, the exercises in this getting started section assume that client registration—sometimes also referred to as device registration—is enabled.

Cloud license server registration is an optional configuration which can help protect against unwanted access to licenses on cloud license servers.

When client registration is enabled, the producer creates an additional registration entitlement for a product containing a licensed (registration) feature. No functionality needs to be tied to this registration feature. Clients use the activation ID from the registration entitlement to register with the target cloud-hosted license server. Once registered, clients are allowed to then request licensed features from the cloud license server pool. License requests from unregistered clients are denied.

By default, client registration is disabled for all cloud-hosted license servers. You can enable individual cloud-hosted license servers using the license server REST APIs. To enable client registration for your site, contact Revenera support.

For detailed information about client registration, refer to the training video [Cloud License Server Device Registration](#) that is available from the [Revenera Learning Center](#) (in section *FlexNet Operations > Cloud Licensing with FlexNet Operations and FlexNet Embedded*). You must be logged in at the Revenera Learning Center to view this content.

Preparing FlexNet Operations

To prepare FlexNet Operations to create a license server, you must create and associate several entities using the Producer Portal. Many of these steps are common to any use of FlexNet Operations with FlexNet Embedded.

This preparation includes the following exercises.

Exercise	Description
Cloud Licensing Service: Creating License Models	Shows how to create and deploy license models to use with the example products we plan to deliver through the license server.
Cloud Licensing Service: Creating Features	Explains how to create the example feature, scientific-operations, as well as a baseline feature with which served clients can be registered.
Cloud Licensing Service: Creating Products	Explains how to create the products necessary to create the entitlement line items to be delivered through the license server.
Cloud Licensing Service: Creating an Account and a User	Shows how to create a customer account and user to which the new product will be entitled.
Cloud Licensing Service: Entitling the Account	Describes how to create an entitlement, configure its line items with the new products, and entitle the customer account to those line items.
Cloud Licensing Service: Viewing the Auto-Provisioned License Server	Explains how to find the license server that was created when the entitlement was deployed.

After you verify that the new license server was created, the FlexNet Operations preparations are complete. Continue with [Cloud Licensing Service: Obtaining the License Server URL](#) and [Cloud Licensing Service: Running a Served Client Example](#).

If you have not previously used FlexNet Operations, see the section [Getting Started with FlexNet Embedded Licensing](#) for more information.

Cloud Licensing Service: Creating License Models

In this exercise, you create license models to use with the products to be created in later exercises. Two license models will be created: one for use with the counted product to be mapped to the license server and the other to serve as a baseline product to manage client registration (only applicable if client registration is enabled). You then deploy both these license models before proceeding to create features.

Creating a Counted License Model

For the product that will contain the counted feature, create a license model called **Example Embedded Counted**. Example Embedded Counted will be a copy of the Embedded Counted license model with auto-provisioning, but with additional license model policies set to Not Used.

Specify the following settings for the copied Embedded Counted license model:

Attribute	Value
Name	Example Embedded Counted
Auto Provision	Yes
Issuer	Not Used
Serial Number	Not Used
Vendor String	Not Used
Notice	Not Used

For any attributes not listed, above, keep the settings copied from the Embedded Counted license model



Task *To create the Example Embedded Counted license model*

1. In the Producer Portal, click **Administer > License Models**. The Producer Portal opens the **License Models** page.
2. On the **License Models** page, locate the built-in Embedded Counted license model, select its check box, and then click **Copy**. This button opens the **Create a License Model** page with attribute settings that match Embedded Counted.
3. Specify license model name and expiration setting. For this exercise, use the values specified in the table above: **Example Embedded Counted** and **None**.
4. Set the license model attribute values described in the table above, and click **Save**.

The Producer Portal creates the license model with the settings you specified.

Creating an Uncounted License Model for Client Registration



Note - The steps in this section only apply if client registration has been enabled. For more information, see [Client Registration](#).

For connected software client security, the client registration process requires an additional uncounted license model. For this purpose, create a second license model, called **Example Baseline LM**. Example Baseline LM will be a copy of the Embedded Uncounted license model with additional license model policies set to Not Used.

For the second part of this exercise, repeat the license model creation process but specify the following settings to the copied Embedded Uncounted license model:

Attribute	Value
Name	Example Baseline LM

Attribute	Value
Issuer	Not Used
Serial Number	Not Used
Vendor String	Not Used
Notice	Not Used

For any attributes not listed, above, keep the settings copied from the Embedded Uncounted license model



Task *To create the Example Baseline LM license model*

1. In the Producer Portal, click **Administer > License Models**. The Producer Portal opens the **License Models** page.
2. On the **License Models** page, locate the built-in Embedded Uncounted license model, select its check box, and then click **Copy**. This button opens the **Create a License Model** page with attribute settings that match Embedded Uncounted.
3. Specify license model name and expiration setting. For this exercise, use the values specified in the table above: **Example Baseline LM** and **None**.
4. Set the license model policy values described in the table above, and click **Save**.

The Producer Portal creates the license model with the settings you specified.

Deploying the License Models

The new license models must be deployed before they can be linked to products or used in entitlement line items.



Task *To deploy the Example Embedded Counted and Example Baseline LM license models*

1. In the Producer Portal, click **Administer > License Models**. The Producer Portal opens the **License Models** page.
2. On the **License Models** page, locate the license models: Example Embedded Counted and Example Baseline LM. If they do not immediately appear in the **License Models** list, try searching License Models for **Example**.
3. Select the check boxes for both license models, and then click **Change State > Deploy**.
4. Click **OK** to confirm the state-change operation.

The Producer Portal deploys the license model and refreshes the **License Models** page to show the new **Deployed** state.

Recently Accessed License Models

Name	License Technology	Date Modified	State	Description
<input type="checkbox"/> Example Embedded Counted	FlexNet Licensing	Mar 18, 2015	Deployed	Embedded counted model
<input type="checkbox"/> Example Baseline LM	FlexNet Licensing	Mar 18, 2015	Deployed	Embedded uncounted, unmetered model for use with baseline product and feature necessary to do client-registration for clients ru...

Figure 14-1: Example Embedded Counted and Example Baseline LM license models deployed

Cloud Licensing Service: Creating Features

In the Producer Portal, use the commands under the **Products** menu to add a feature called **scientific-operations**, version **1.0**. and a feature called **baseline-client-reg**, version **1.0**. When defining the features, use the following settings:

Attribute	Value
Feature Name	scientific-operations
Feature Version	1.0
Description	Example feature for cloud-hosted license server exercises.

Leave all other attribute settings on their default values.

Creating a Counted Feature to Map to the License Server

Use the instructions, below, to create the scientific-operations feature.



Task To create the scientific-operations feature

1. In the Producer Portal, click **Products > Features**. The Producer Portal opens the **Feature** page.
2. On the **Feature** page, click **Add New Feature**. This button opens the Create a Feature page.
3. On the **Create a Feature** page, set the feature attributes using the values in the table above.
4. Click **Save**.

The Producer Portal creates the scientific-operations feature and remains on the **Create a Feature** page.

Package Products

Feature scientific-operations successfully added.

Create A Feature

Feature Name : * scientific-operations ?

Version Format Type * Fixed ?

Version : * 1.0 ?

Description Example feature for cloud-hosted license server exercises. ?

Units : ?

Scale : ?

State: Draft

Figure 14-2: The **Create a Feature** page for the scientific-operations feature.

Creating an Uncounted Feature for Client Registration



Note • The steps in this section only apply if client registration has been enabled. For more information, see [Client Registration](#).

For security, the client registration process requires an additional uncounted feature. For this purpose, create a second feature called **baseline-client-reg**.

Repeat the feature creation process for the baseline feature. Use the settings shown in the table below.

Attribute	Value
Feature Name	baseline-client-reg
Feature Version	1.0
Description	Example feature to do client-registration for products to be run on served clients.

Leave all other attribute settings on their default values.

Cloud Licensing Service: Creating Products

Use commands under the **Products** menu to create two products: Example Calculator for the counted features and Example Baseline for the baseline-client-reg feature

Creating the Example Calculator Product

The Example Calculator product includes the counted feature you defined in the previous exercise: scientific-operations. Use the following settings when creating Example Calculator:

Attribute	Value
Product Name	Example Calculator
Description	An example counted product used with the exercises in the section Getting Started with Cloud Licensing Service
Version	1.0
Licensing Technology	FlexNet Licensing
Can Be Used on a Device	Yes
Feature	scientific-operations
Feature Quantity	1
License Model	Example Embedded Counted



Task To create Example Calculator

1. In the Producer Portal, click **Products > Products**. The Producer Portal opens the **Products** page.
2. On the **Products** page, click **Add New Product**. This button opens the **Create a Product** page.
3. On the **Create a Product** page, set **Product Name**, **Version**, **License Technology**, and **Can Be Used on a Device** as shown in the table above.
4. Click **Add Features**. The Producer Portal opens the **Add Features to Product** page in a pop-up window.
 - a. Locate the feature, **scientific-operations, 1.0.**, and click **Add**. This selects the feature and moves it to the **Selected Features** list.
 - b. Click **Add**. The Producer Portal closes the **Add Features to Product** window.
5. On the **Create a Product** page, set the **Quantity** for the scientific-operations feature to **1**, and click **Next**. (For a counted feature, this is the feature count per copy of the product ordered.) The Producer Portal opens the **Link License Models to Product** page.
6. Click **Link License Models** to open the **Select License Models** page in a pop-up window.
 - a. Locate the license model, **Example Embedded Counted**, and click **Add**. This selects the license model and moves it to the **Selected License Models** list.
 - b. Click **Add**. The Producer Portal closes the **Select License Models** window.
7. Click **Save**.

The Producer Portal saves Example Calculator and remains on the **Map Product to Product Line** page.

Creating the Example Baseline Product



Note - The steps in this section only apply if client registration has been enabled. For more information, see [Client Registration](#).

Next, repeat the steps, creating a product for the uncounted baseline-client-reg feature and uncounted license model used in client registration. Use the following settings for the Example Baseline product.

Attribute	Value
Product Name	Example Baseline
Description	A product to contain the uncounted, baseline feature to be used for client registration on served clients.
Version	1.0
Licensing Technology	FlexNet Licensing
Can Be Used on a Device	Yes
Feature	baseline-client-reg,1.0
Feature Quantity	1
License Model	Example Baseline LM



Important - Before these new products can be used in an entitlement, you must deploy them. (Deploying a product changes its state, and the state of its features, from draft to deployed.) Select the check boxes for the Example Calculator and Example Baseline products, click **Change State > Deploy**, and follow the on screen instructions to confirm the change.

Recently Accessed Products

Add New Product Copy Delete Change State ▾ Print Export ▾

Name	Version	Product Line	Type	Date Modified	Part Number	State	Description
<input type="checkbox"/> Example Calculator	1.0	Uncategorized Products	Product	Mar 18, 2015		Deployed	An example counted product use with the exercises in the Getting Started Guide for Cloud Licensing Service
<input type="checkbox"/> Example Baseline	1.0	Example Product Line	Product	Mar 18, 2015		Deployed	A product to contain the uncounted, baseline feature to be used for client registration on served clients.

Figure 14-3: Example Baseline and Example Calculator products deployed

Cloud Licensing Service: Creating an Account and a User

In the FlexNet Operations Producer Portal, use the commands under the **Accounts & Users** menu to create an account that represents a customer enterprise. For this example, create an account called **Demo Customer Org**.




Note - The creation of this customer account and end user is also part of other FlexNet Operations getting started sections. If the account and user already exist in the Producer Portal, you can skip this exercise.

If you already have a test end user in a customer account you can entitle to these products, you can opt use that user instead of creating the user described here. Otherwise, follow the instructions, below, to create the customer account (Demo Customer Org), the end user account (Demo Customer) and entitle it to the Example Calculator and Example Baseline products.



Task To create the customer account and end user

1. In the Producer Portal, click **Accounts & Users > Create Account**. The Producer Portal opens the **Create an Account** page.
2. On the **Create an Account** page, type the following values for the **Account ID** and **Account Name** attributes.

Attribute	Value
Account ID	DemoCustOrg
Account Name	Demo Customer Org 

Important - Do not enter a colon (:) character in the **Account Name** field.

Keep the default values for all other attributes.

3. Click **Create a User**. The Producer Portal saves the Demo Customer Org account and opens the **Create a User** page to add a new user to it.
4. On the **Create a User** page, type the following values for the new user's Contact Details:

Attribute	Value
First Name	Demo
Last Name	Customer
Email Address	An email address you control. This email account is where FlexNet Operations will send the initial login credentials and entitlements.

Keep the default values for all other **User Details** and **Contact Details** attributes.

5. In **Accounts**, select the check box for **Portal User Role**. This gives Demo Customer the standard permissions for portal users.

6. Click **Save**.

The Producer Portal creates Demo Customer as a new user and sends a welcome message to the email address you provided. Use the credentials in that email to log in to the End User Portal and verify the Demo Customer account is functional.

Cloud Licensing Service: Entitling the Account

Use the commands in the **Entitlements** menu to create an entitlement to the Example Calculator and Example Baseline products for Demo Customer Org.

In this exercise, you will create a new entitlement, add Demo Customer Org as the end customer, configure a line item for the uncounted product for client-registration, Example Baseline, and configure another line item for the counted product, Example Calculator.



Task *To create the entitlement ENTL-SCI-OPS*

1. In the Producer Portal, click **Entitlements > Create**. The Producer Portal opens the **Create an Entitlement** page.
2. For **Entitlement ID**, select **Specify** and type ENTL-SCI-OPS.
3. For End Customer and Channel Partners, click **Add**. The Producer Portal opens the **End Customer and Channel Partners** page in a pop-up window.
 - a. Click the **DemoCustOrg** option to select the Demo Customer Org as the customer account to receive the entitlement.
 - b. Click **Next**. The Producer Portal shows the **End Customer and Channel Partners: Contacts** page in the pop-up window.
 - c. Click the **Demo Customer** option to select Demo Customer as the end user who will receive the entitlement message.
 - d. Click **Save**.

The Producer Portal closes the pop-up window and shows Demo Customer Org and Demo Customer as the end customer.

4. Click **New Line Item** to begin configuring a line item for the Example Baseline product. The Producer Portal opens the **Configure Line Item** page in a pop-up window.




Figure 14-4: Starting the line item configuration process for the Example Baseline product.

- a. Locate and select the **Example Baseline** product, and then click **Next**.
 - b. Select the license model, **Example Baseline LM**, and click **Next**.
 - c. Specify the following settings for product configuration:
 - **Qty: 1**
 - **Start Date: Use First Activation Date**
 - **Expiration: 01/01/2020**
 - d. Click **Next**.
 - e. Click **Save**.
5. Click **New Line Item** to begin configuring a line item for the Example Calculator product. The Producer Portal opens the **Configure Line Item** page in a pop-up window.
- a. Locate and select the **Example Calculator** product, and then click **Next**.
 - b. Select the license model, **Example Embedded Counted**, and click **Next**.
 - c. Specify the following settings for product configuration:
 - **Qty: 30**
 - **Start Date: Use First Activation Date**
 - **Expiration: 01/01/2020**
 - d. Click **Next**.
 - e. Click **Save**.
6. Click **Save & Deploy**.

The Producer Portal saves ENT-SCI-OPS with line items for Example Baseline and Example Calculator.

The screenshot shows a web interface for 'Maintenance Line Items'. At the top, there are tabs for 'Line Items' and 'Maintenance Line Items'. Below the tabs is a search bar with 'Search For' set to 'Activation ID' and 'Contains'. There are several action buttons: 'New Line Item', 'Configure', 'Change State', 'Export', 'Link Maintenance Line Items', and 'Delete'. The main area contains a table with the following data:

Type	Activation ID	Product	Part Number	Expiration	Total Qty	Line Item State	Maintenance
<input type="checkbox"/> E	b108-b523-5d19-4e21-ef9d-ef2b	Example Calculator Ver 1.0, Qty/Copy 1		Jan 1, 2020	30	Deployed	
<input type="checkbox"/> E	8d87-cc54-83f9-4ef1-b938-a51d-92ea-c323	Example Baseline Ver 1.0, Qty/Copy 1		Jan 1, 2020	1	Deployed	

At the bottom left, it says 'Page 1 of 1' and at the bottom right, 'Total number of rows 2'.

Figure 14-5: The entitlement line items for Example Calculator and Example Baseline in ENTL-SCI-OPS

FlexNet Operations also generates the license server and maps the Example Calculator line item to the new server.



Tip - Make a note of the resulting activation ID for Example Baseline. (Yours will be different than the activation ID depicted in the figure above.) When you run a connected client, you will use the activation ID as the rights ID during the client registration process.

Cloud Licensing Service: Viewing the Auto-Provisioned License Server

Once you deploy the entitlement, ENTL-SCI-OPS, FlexNet Operations automatically generates the license server from which served clients in the end customer account acquire their license rights. In this exercise, you will locate the auto-provisioned license server in the Producer Portal.



Task To view the auto-provisioned license server

1. In the Producer Portal, click **Devices > Devices**. The Producer Portal opens the **Devices** page.
2. On the **Devices** page, locate the new license server by its account name.
 - a. In the search controls, select **Account name** from the drop-down list.
 - b. Type **DemoCustOrg** in the search field and then click **Search**.
3. On the **Devices** search results page, click the **Name** of DemoCustOrg's license server. The Producer Portal opens the **View Server** page.

Notice that the **View Server** page shows a number of important attributes of the license server. In particular, make a note of the license server ID. The license server ID, in this case 3VH8MNZESMSP, is also the instance ID value for the server URL. This instance ID value is used in the endpoint URL where the served clients connect to make capability requests. (See [Cloud Licensing Service: Obtaining the License Server URL](#).)

Notice also, that the license server's **View Server** page also shows the product licenses that are served by it. In this case, the license server includes the Example Calculator line item from the ENTL-SCI-OPS entitlement. (The Example Baseline line item is not served by the license server. Instead, it is present in the entitlement to support the registration of its served clients.)



Tip - When auto-provisioning is used, you can also find a customer account's default license server instance on customer account's **Create an Account** page. There, click the license server ID link, labeled **Cloud Licensing Service instance (Auto Provisioned)**, to open the **View Server** page.

Cloud Licensing Service: Obtaining the License Server URL

The URL for the license server identifies the location where your FlexNet Embedded client communicates with its cloud-hosted license server. For a connected software client using the FlexNet Embedded C SDK or FlexNet Embedded XT, the URL is:

```
https://<siteID>-uat.compliance.flexnetoperations.com/instances/<CLS instance ID>/request
```

In the URL, above, <siteID> is the site ID for your account and <CLS instance ID> is the license server ID of the license server with the license rights to the Example Calculator product. (For more information about the site ID, see [FlexNet Operations Environments](#).) The <CLS instance ID> value based on the license server created in the exercises in this section would be 3VH8MNZESMSP.

For instance, a URL for a producer account with the site ID *example* might appear as:

```
https://example-uat.compliance.flexnetoperations.com/instances/3VH8MNZESMSP/request
```



Tip - This getting started section uses the FlexNet Operations User Acceptance Testing (UAT) site for demonstration purposes. Any URLs mentioned must be adjusted when used in production.

Cloud Licensing Service: Running a Served Client Example

At this point, you can put the pieces together and run a served client from your FlexNet Embedded client toolkit.

Use FlexNet Embedded C SDK or FlexNet Embedded XT to implement a served client that is configured with the correct endpoint URL for the license server.

In these implementations, you first send a capability request that specifies the Example Baseline activation ID as a rights ID, to claim the client, and then send a capability request containing the desired feature, scientific-operations, to request counts from the license server.

See your FlexNet Embedded user guide for other served client and license server implementation details and examples.

Getting Started with Entitlement Management

This section *Getting Started with Entitlement Management* presents fundamental FlexNet Operations concepts and uses exercises to guide you through creation of a product entitlement, including the supporting tasks. Topics and exercises are presented in the order that a Producer Portal user would perform them when setting up a new customer account, customer user, and product, and then creating an entitlement.

The intended audience for *Getting Started with Entitlement Management* is the first-time Producer Portal user, or one without FlexNet Operations training or experience. This getting started section is organized into the following topics.

Topic	Content
Introduction	Overview of this getting started section, exercise prerequisites, and a summary of the FlexNet Operations license lifecycle.
Account and User Creation	Customer account, customer user, and producer account concepts with exercises that demonstrate how to create each of them. Brief descriptions of advanced account topics with references for more information.
Product Creation	Product packaging concepts with exercises that demonstrate how to create, link a license model to, and deploy a product. Brief descriptions of advanced product packaging topics with references for more information.
Entitlement Creation	Entitlement concepts with exercises that demonstrate how to create, configure, and deploy an entitlement, and how to review it on the End-User Portal. Brief descriptions of advanced entitlement topics with references for more information.

To view a brief, informative video that walks you through the exercises in *Getting Started with Entitlement Management*, click [here](#). We recommend that you read this getting started section in full, to gain an understanding of the concepts it covers, before you view the video.

Introduction

This section lists exercise prerequisites, and provides a summary of the FlexNet Operations license lifecycle.

- [Exercise Prerequisites](#)
- [The License Lifecycle: Entitlement Management](#)

Exercise Prerequisites

Before you begin the exercises in this getting started section:

- FlexNet Operations seed data and demonstration database must be loaded
- FlexNet Operations email templates must be set up
- You must have a FlexNet Operations Producer Portal login and a role with permission to view and manage accounts and users, such as System Administrator

The License Lifecycle: Entitlement Management

The FlexNet Operations license lifecycle is a repeating process of producer and customer activities, as depicted in the figure and described below.



Figure 15-1: FlexNet Operations License Lifecycle

Product creation and entitlement, the first two stages of the license lifecycle, are covered in this getting started section.

- **Create Products** – Create product definitions that are used to generate licenses.
- **Order/Entitle** – Define a customer’s rights to obtain licenses for your products.
- **Deliver/Install** – Deliver the application software to the customer and install that software.
- **Activate** – Deliver licenses to the customer.
- **Return/Rehost** – Manage license transfers from one user or system to another.
- **Maintain/Update** – Deliver software and license updates to the customer.
- **Upsell/Renew** – Renew customer licenses, or sell the customer additional product functionality.

Account and User Creation

This topic introduces fundamental FlexNet Operations account and user concepts, and guides you through customer account and customer user setup tasks in preparation for entitlement creation.

- [Account and User Creation Key Concepts](#)
- [Account and User Creation Exercise Scenario](#)
- [Account and User Creation Exercises](#)
- [Account and User Creation Next Steps](#)
- [Account and User Creation Advanced Topics](#)

Account and User Creation Key Concepts

Accounts

To be associated with an entitlement, a company must be entered as one of the FlexNet Operations account types. [Account and User Creation Key Concepts](#) touches only on the account types relevant to this section’s entitlement creation exercises:

- **Producer** – software producer or intelligent device manufacturer
- **Customer** – end user of the software or device

User Roles

A FlexNet Operations user must belong to one of the FlexNet Operations account types, and a user name and password are required to log in. Revenera creates the initial user account for a producer’s FlexNet Operations System Administrator, then the System Administrator creates any additional users required for the producer’s account and for the producer’s customers (end users).

The activities a user can perform are based on the permissions that user has. However, permissions are not assigned to users directly. Instead, permissions are grouped into roles and FlexNet Operations users are assigned one or more roles. [Account and User Creation Key Concepts](#) touches only on the user roles relevant to this section’s entitlement creation exercises; these roles, and others, are provided as seed data:

- **System Administrator** – a producer FlexNet Operations administrator who has the ability to create new roles for producer personnel and end users by assigning specific permissions
- **Portal Administrative User** – a customer user who has End-User Portal administrative privileges
- **Portal User** – an End-User Portal customer user

Account and User Creation Exercise Scenario

GraphicsPrint is a producer offering specialized printing services for its customers, who can pre-purchase these services. GraphicsPrint's **LargeFormat** product line includes the **PhotoPrint**, **SignPrint**, and **CADPrint** products.

In [Account and User Creation Exercises](#), you set up GraphicsPrint's customer account **Barry Photography Studio** and customer end-user **Lisa Barry**.

In [Product Creation Exercises](#), you set up GraphicsPrint's **LargeFormat** product line and the **PhotoPrint** product, which includes FlexNet Operations demonstration data features **PrintToPDF**, **Print**, and **PrintHighQualityColor**.

In [Product Creation Exercises](#), you entitle customer account **Barry Photography Studio** to use the **PhotoPrint** product.

Account and User Creation Exercises

The following exercises use examples to guide you through the customer account and end user setup tasks:

Exercise	Description
Creating a Customer Account	Create customer account Barry Photography Studio.
Creating a Customer End User	Create customer end user Lisa Barry.

Creating a Producer User

One of the first tasks you perform as a Producer Portal administrator is creating producer users and assigning them roles. The procedure for creating a producer user is similar to the one below for creating a customer user. For more information on creating different types of users, refer to [Creating a User](#).



Note - In these exercises, FlexNet Operations default producer My Organization (MYORG) represents GraphicsPrint.

Creating a Customer Account

In this exercise, you create customer account Barry Photography Studio.



Task **To create a customer account**

1. Log in to the FlexNet Operations Producer Portal.
2. Click **Accounts & Users > Create Account**. The **Create An Account** page appears. Note that **Account Type** is CUSTOMER.
3. On the **Create An Account** page, enter the customer account attributes:
 - **Account ID:** Type BarryPhoto
 - **Account Name:** Type Barry Photography Studio



Important - Do not enter a colon (:) character in the **Account Name** field.

- Keep the default values for all other attributes.
4. Click **Save**. The Barry Photography Studio account is saved and this message appears: Account BarryPhoto has been successfully added.

Creating a Customer End User

In this exercise, you create end user Lisa Barry.



Task **To create a customer end user**

1. On the same **Create An Account** page, click **Create a User**. The **Create A User** page appears.
2. Under **Contact Details**, enter the new customer user's attributes:
 - **First Name:** Type Lisa
 - **Last Name:** Type Barry
 - **Email Address:** Type an email address you control. This is the customer's End-User Portal login user name.



Note - This is also the email account to which FlexNet Operations sends the customer's initial credentials and entitlements.

- Keep the default values for all other user and contact attributes.
3. Under **Accounts**, select the check box for **Portal Admin User Role**. This gives Lisa Barry administrative Portal User permissions.
 4. Click **Save**. New user Lisa Barry is created and this message appears: User Lisa Barry successfully added. A welcome email is sent to the email address you provided.
 5. Record the credentials you receive in the welcome email, then use them to log in to the FlexNet Operations End-User Portal and verify that the Lisa Barry account is functional.



Note - The first time the customer logs in to the FlexNet Operations End-User Portal, he/she is asked to change the temporary password and select security questions.

6. Log out of the FlexNet Operations End-User Portal.
7. Log out of the FlexNet Operations Producer Portal or continue with [Product Creation](#).

Account and User Creation Next Steps

Product creation, the first stage of the FlexNet Operations license lifecycle, includes packaging features, linking a license model or models, and deploying the product. The exercises in [Product Creation](#) guide you through FlexNet Operations product creation.

Account and User Creation Advanced Topics

For more information about these advanced account topics and others, refer to the sections [Managing Accounts](#), [Managing Users](#), and [Getting Started with Advanced Organization Management](#).

Account Types

FlexNet Operations categorizes accounts into four types: Producer, Customer, Partner, and Self Registered.

Partners and Distribution Tiers

Accounts can represent the relationship between a producer and its distribution chain.

Sub-Accounts

Accounts can have sub-accounts, which can be used to reflect the hierarchical nature of corporate structures. Accounts and sub-accounts are defined in a parent-child relationship.

Product Lines

When the product lines feature is enabled, FlexNet Operations filters what customer users see based on the product lines linked to the users' accounts. Only entitlements that include products in product lines to which the user account is linked are visible.

Working with User Roles and Permissions

You can administer user access roles and permissions.

Product Creation

This topic introduces fundamental FlexNet Operations product concepts, and guides you through product setup tasks in preparation for entitlement creation. Product creation, the first stage of the FlexNet Operations license lifecycle, includes packaging features, linking a license model or models, and deploying a product.

- [Product Creation Key Concepts](#)

- [Product Creation Exercises](#)
- [Product Creation Next Steps](#)
- [Product Creation Advanced Topics](#)

Product Creation Key Concepts

Products, Product Suites, and Product Lines

Products are packages of entities, called features and feature bundles, that can be sold by a producer. A *feature* is a software functionality or set of functionalities. Feature definitions created in the FlexNet Operations Producer Portal correspond to product features defined in the product's code. Features can be grouped into *feature bundles* for modular control over how the features are packaged in different products. Typically, a feature bundle consists of features grouped by similarity, complexity level, or other defined criteria (grouping features into a feature bundle is optional).

A *product suite* is a set of products grouped together for promotional purposes or because the products are functionally complementary (grouping products into a product suite is optional).


Products can be assigned to *product lines*, which define user access rights to product information. Product lines can also be used to group products for searching and reporting purposes.



Important - Product lines are required for FlexNet Embedded licensing and electronic software delivery; otherwise, they are optional. For more information, refer to the sections [Getting Started with FlexNet Embedded Licensing](#) and [Getting Started with Electronic Software Delivery](#).

Entity States

The *state* of an entity, such as a product or its component features or feature bundles, determines how that entity can be referenced in different stages of its configuration. Allowed state transitions are shown in the figure, and the states are described below it.



- **Draft** – The default state when an entity is created. In this state, the entity can be edited, but it is not available for production use.

- **Deployed** – The entity is available for production use. If an entity is deployed accidentally and no other entities refer to it, it can be moved back to draft state.
- **Inactive** – The entity has been withdrawn from use. No new references can be made to it, but existing references remain unchanged.
- **Obsolete** – The entity exists only for reporting purposes. While there is existing data that refers to it, no new references can be made. An obsolete entity can be deleted if there are no references to it.

Changing an entity from one state to another affects the states of related entities. For example, when a product is deployed, its component features and feature bundles are also deployed. However, when a product is made inactive or obsolete, its features and feature bundles are unaffected because a feature or feature bundle can be associated with several different products. A deployed entity may be modifiable, depending on configuration.

Product Creation Exercises

These exercises use examples to guide you through the following product creation tasks:

Exercise	Description
Deploying a License Technology and Model	Deploy the FlexNet Licensing technology and Nodelocked Uncounted license model.
Creating a Product Line	Create product line LargeFormat.
Creating a Product	Create product PhotoPrint.
Linking a License Model to a Product	Link the Nodelocked Uncounted license model to product PhotoPrint.
Mapping a Product to a Product Line	Map product PhotoPrint to product line LargeFormat.
Deploying a Product	Review the attributes of product PhotoPrint and deploy it.

Deploying a License Technology and Model

A license model defines characteristics that determine how, when, where, and by whom a Flex-enabled application can be used. In this exercise, you deploy the FlexNet Licensing technology and its Nodelocked Uncounted license model.



Important - Licensing is not covered in this getting started section. These tasks are included because product PhotoPrint must be linked to a license model to be deployed. For more information, see [Administering License Technologies](#), or these getting started sections:

- [Getting Started with FlexNet Embedded Licensing](#)
- [Getting Started with FlexNet Publisher License File-Based Licensing](#)
- [Getting Started with FlexNet Publisher Trusted Storage-Based Licensing](#)
- [Getting Started with Non-FlexNet Licensing Technologies](#)

**Task** *To deploy the license technology*

1. Log in to the FlexNet Operations Producer Portal if you logged out after completing the [Account and User Creation](#) exercises.
2. Click **Administer** > **License Technologies**. The **License Technologies** page appears, listing **FlexNet Licensing** with a state of draft.
3. Select the **FlexNet Licensing** check box, then click **Change State** ▼ and select **Deploy** from the drop-down menu. Click **OK** in the verification message. In the **License Technologies** table, **FlexNet Licensing** is shown with a **State** of **Deployed**. This message appears: Deployed the following License Technologies successfully: FlexNet Licensing.

**Task** *To deploy the license model*

1. Click **Administer** > **License Models**. The **Package Products - License Models** page appears.
2. Select **Nodelocked Uncounted**.
3. Click **Change State** ▼ and select **Deploy** from the menu.
4. Click **OK** in the verification message. In the **License Models** table, **Nodelocked Uncounted** is shown with a **State** of **Deployed**. This message appears: Deployed the following License Model(s) successfully: Nodelocked Uncounted.

Creating a Product Line

In this exercise, you create product line LargeFormat, which includes the product PhotoPrint that you create in the next exercise.



Important - Product lines are required for FlexNet Embedded licensing and electronic software delivery; otherwise, they are optional. For more information, refer to the sections [Getting Started with FlexNet Embedded Licensing](#) and [Getting Started with Electronic Software Delivery](#).

**Task** *To create product line LargeFormat*

1. Click **Products** > **Product Lines**. The **Package Products | Product Lines** page appears.
2. Click **Add Product Line**. Under **Create Product Line**, enter the product line attributes:
 - **Name:** Type LargeFormat
 - **Description:** Type Includes products PhotoPrint, SignPrint, and CADPrint.
3. Click **Save**. This message appears: Product Line added successfully.
4. Click **Products** > **Product Lines**. The **Package Products | Product Lines** page appears. Note that LargeFormat is listed in the **Product Lines** table with its description.

Creating a Product

In this exercise, you create product PhotoPrint from FlexNet Operations demonstration data features PrintToPDF, Print, and PrintHighQualityColor.



Task To create product PhotoPrint

1. Click **Products > Products**. The **Package Products** page appears.
2. Click **Add New Product**. Under **Create A Product**, enter the product attributes:
 - **Product Name:** Type PhotoPrint
 - **Description:** Type Sends to PDF file, prints normal quality, or prints high quality.
 - **Version:** Type 12.0
 - Keep the default values for all other attributes.
3. Click **Add Features**. The **Add Features To Product** window opens.
4. In the **Add Features To Product** window, search for feature names that contain the string Print. Features Print, PrintHighQualityColor, PrintToFiery, PrintToPDF, and PrintToPlotter are listed under **Available Features**.
5. In the **Add Features To Product** window, under **Available Features**, select Print, PrintHighQualityColor, and PrintToPDF.



Note ▪ Press CTRL+click to select non-contiguous items. Press SHIFT+click to select a range of items.

6. Click **Add ►** to move features Print, PrintHighQualityColor, and PrintToPDF to **Selected Features**, then click **Add**. The window closes and the features are added to product PhotoPrint.
7. The features are listed in the **Feature or Feature Bundle Name** table with their **Name**, **Version**, **State**, and **Quantity**. In the **Quantity** column, keep the default values of **1** to specify that there is one copy each of features Print, PrintHighQualityColor, and PrintToPDF in product PhotoPrint.
8. Click **Save**. Note that product PhotoPrint and its version appear in the list on the right side of the page. This message appears: Product PhotoPrint successfully added.

Linking a License Model to a Product

In this exercise, you link the Nodelocked Uncounted license model to product PhotoPrint.



Task To link the license model to product PhotoPrint

1. Click **Products > Products**. The **Package Products** page appears.
2. Search for product PhotoPrint, then click its link in the product table. The **Package Products | Create A Product** page appears with product PhotoPrint information.
3. Click **Next**. The **Package Products | Link License Models To Product** page for PhotoPrint appears.

4. Click **Link License Models**. The **Select License Models** window opens.
5. Search for and select **Nodelocked Uncounted** from **Available License Models**, then click **Add ►** to move it to **Selected License Models**.
6. Click **Add**. The **Select License Models** window closes.
7. On the **Package Products** page, click **Save**. Product PhotoPrint is linked to the Nodelocked Uncounted license model. This message appears: License models linked successfully. Note that product PhotoPrint appears with its description in the list on the right side of the page.

Mapping a Product to a Product Line

In this exercise, you map product PhotoPrint to product line LargeFormat that you created in the previous exercise.



Task *To map product PhotoPrint to product line LargeFormat*

1. Click **Products > Products**. The **Package Products** page appears.
2. Search for product PhotoPrint, which is listed as an uncategorized product because it is not mapped to a product line. Click the PhotoPrint link in the product table. The **Package Products | Create A Product** page appears with product PhotoPrint information.
3. Click **Next** four times to advance to the **Package Products | Map Product To Product Line** page for PhotoPrint.
4. Under **Map Product To Product Line**, do either of the following to specify the product line LargeFormat:
 - In the **Product Line** field, type LargeFormat.
 - Click the search icon next to the **Product Line** box. The **Select Product Line For Product** window opens. Search for and select product line LargeFormat, then click **OK**. The **Select Product Line For Product** window closes.
5. On the **Package Products** page, click **Save** to map product PhotoPrint to product line LargeFormat. This message appears: PhotoPrint is successfully mapped to product line LargeFormat.

Deploying a Product

In this exercise, you review the attributes of product PhotoPrint, then you deploy it.



Task *To review the attributes of product PhotoPrint*

1. Click **Products > Products**. The **Package Products** page appears.
2. Search for product PhotoPrint and note that it is in the **Draft** state.
3. Click the PhotoPrint link. The **Package Products | Create A Product** page appears. Under **Create A Product**, review these attributes:
 - **Product Name:** PhotoPrint

- **Description:** Sends to PDF file, prints normal quality, or prints high quality.
 - **Version:** 12.0
 - **State:** Draft
4. Scroll down to the **Feature or Feature Bundle Name** table and note that PhotoPrint contains one copy each of features PrintToPDF, Print, and PrintHighQualityColor in the **Draft** state and no feature bundles.
 5. Click **Back** to return to the **Package Products** page.



Task *To deploy product* PhotoPrint

1. On the **Package Products** page, select the product PhotoPrint check box.
2. Click **Change State** ▼ and select **Deploy** from the drop-down menu. Click **OK** in the verification message. The **Package Products** page appears, with the feature and feature bundle deployment information, for product PhotoPrint.
3. Click **Deploy**. The **Package Products** page shows that PhotoPrint and its features are successfully deployed. This message appears: Products deployed successfully.
4. Log out of the FlexNet Operations Producer Portal or continue with [Entitlement Creation](#).

Product Creation Next Steps

Entitlement is the stage of the FlexNet Operations license lifecycle that follows product creation. The entitlement process includes creation, configuration, and deployment of the entitlement. The exercises in [Entitlement Creation](#) use product PhotoPrint to guide you through FlexNet Operations entitlement creation and deployment.

Product Creation Advanced Topics

Free Product Trials

Product trials enable self-service user registration for, and provisioning of a product for customer evaluation.

The producer creates the trial registration page, the custom content of which can include survey questions. When a prospective customer signs up for a free product trial, FlexNet Operations creates an account for that customer, creates an entitlement for a trial product, and sends a welcome email to the customer. The customer logs in to end-user portal using the credentials sent in the email, downloads and activates the product, and runs the trial for the time period specified by the product's license model.

The producer can easily access information about product trial customers, product evaluations, and responses to survey questions.

Maintenance Products

A *maintenance* product represents a customer's right to obtain technical support, upgrades, updates, or new platforms for a particular licensed product or product suite for a specified duration.

Product Part Numbers

After a product is linked to a license model or models, it can be mapped to one or more *part numbers* that link it to an accounting application. Part numbers are referenced by customers in their orders and can be tracked by an enterprise resource planning (ERP) or customer relationship management (CRM) system.

Product Relationships

In addition to being grouped into suites, software products can also be related in these ways:

- **Demo** – A demonstration, or limited functionality version of a product.
- **Upgrade** – A newer version of a product.
- **Upsell** – A product with a wider range, capability, or more advanced features than another product.
- **Maintenance** – An unlicensed product that represents additional rights that a customer can purchase. For example, maintenance may give the customer the right to technical support, upgrades, updates, or new platforms for the duration of the maintenance period.

Product relationships enable follow-up sales operations such as upgrades, upsells, and renewals.

Entitlement Creation

This topic introduces entitlements, the stage of the FlexNet Operations license lifecycle that follows product creation. The entitlement process includes creation, configuration, and deployment of an entitlement.

The exercises in this topic use Lisa Barry of Barry Photography Studio, the customer you created in the [Account and User Creation](#) exercises, and PhotoPrint, the product you deployed in the [Product Creation](#) exercises, to guide you through FlexNet Operations entitlement creation.

- [Entitlement Creation Key Concepts](#)
- [Entitlement Creation Exercises](#)
- [Entitlement Creation Next Steps](#)
- [Entitlement Creation Advanced Topics](#)

Entitlement Creation Key Concepts

Entitlements

An entitlement represents a product, with its associated license model(s), that a customer has purchased. The following figure depicts the relationships that you set up in the exercises of this getting started section.




Figure 15-2: Entitlement Creation Relationships

The entitlement indicates how many copies of the product the customer has the right to use or access, along with any maintenance, and the duration for which the customer can use or access the product. The customer must activate the entitlement to generate licenses in formats like license files, trusted storage, or others.

An entitlement is created for many reasons, including after order shipment. Each entitlement is associated with an entitlement ID. Entitlement IDs are generated when an order is entered in FlexNet Operations; an entitlement ID is associated with every entitlement for that order. Each line item of an entitlement is an activatable unit and is uniquely identified by an activation ID. The details of a line item specify the product and its options, the quantity, and the duration of the license rights. An entitlement can have one or more line items.

Entitlements can be created in a number of ways, but the two most common are manually, by an authorized user using the FlexNet Operations Producer Portal, and by importing them from an external enterprise resource planning (ERP) or customer relationship management (CRM) system that is integrated with FlexNet Operations (importing entitlements, an advanced topic, is not covered in this getting started section).

Entitlement and Line Item Attributes

The **List Entitlements by Order** page of the Producer Portal (click **Entitlements** > **List Entitlements by Order**) lists entitlements and their line items with the following attributes:

- **Entitlement ID** – Unique identifier of the entitlement
- **Account** – End customer and/or channel partner account(s) that the entitlement was sold to
- **State** – Entitlement’s state: Draft, Deployed, Inactive, Test, or Obsolete (refer to [Entitlement States](#))
- **Bulk** – Is this a bulk entitlement? No = Regular and Yes = Bulk (refer to [Entitlement Styles](#))
- **# Line Items** – Number of activatable items in the entitlement

- **Activation ID** – Unique identifier of the activatable item
- **Product** – Product(s) defined for the line item, including version number(s)
- **Maintenance** – Maintenance line item that is related to a product

Clicking an **Entitlement ID** link displays the **Entitle Customers to Licenses | Create An Entitlement** page, which provides more information about the entitlement and its line items. The table on the **Line Items** tab lists the entitlement's line items with the following attributes:

- **Type** – License model type of an activatable line item:
 - FlexNet Embedded **E**
 - FlexNet Publisher license file-based (also called certificate) **C**
 - FlexNet Publisher trusted storage-based **T**
 - Custom, non-FlexNet **NF**
- **Activation ID** – Unique identifier of the activatable item
- **Product** – Product(s) defined for the line item, including version number(s)
- **Part Number** – Unique number assigned by the producer to identify a specific product. Part numbers can be added in FlexNet Operations or imported from a file. Part numbers are optional.
- **Expiration** – Specifies when the line item expires.
- **Total Quantity** – Count of a product in the line item
- **Line Item State** – Line item's state: Draft, Deployed, Inactive, Test, or Obsolete (refer to [Line Item States](#))
- **Maintenance** – Maintenance line item that is related to a product

Entitlement States

Entitlements have states that determine their ability to be edited and to be used in various license lifecycle activities. Changes to these states are tracked by FlexNet Operations. These states are:

- **Draft** – Draft entitlements can be created only from deployed products and suites. An entitlement is created in a draft state so it can be modified or deleted.
- **Deployed** – Deployed entitlements can be activated, upsold, and so on, but not edited or deleted (this can be changed with configuration). However, some fields in a deployed entitlement can be modified.
- **Inactive** – When an entitlement is made inactive, all of its line items are made inactive and cannot be activated, upgraded, upsold, or renewed. Existing activations against an inactive line item cannot be returned, repaired, or rehosted.
- **Test** – Test entitlements can be created from draft products, and enable testing of draft products and license models before they are deployed. All entitlement actions can be performed on test entitlements, but test entitlements cannot be moved to any other state. When a test entitlement is deleted, existing activations against it are also deleted.
- **Obsolete** – An entitlement can be made obsolete if it is no longer required or if it was created and deployed in error. While there is existing data that refers to an obsolete entitlement, no new references to it can be made. An obsolete line item cannot be activated. Existing activations of an obsolete line item cannot be rehosted.



Note - An entitlement that has been activated on a device can have its state changed to *Inactive* or *Obsolete* only if the configuration option **Allow used entitlement/line item state change to Inactive or Obsolete** is selected.

When this configuration option is selected, an entitlement or line item that has been activated on a device can still be used until the license expires, even if the entitlement or line item has been deactivated or made obsolete.

For more information, see [General Options](#) in [Configuring System Settings](#).

Entitlement Styles

The two styles of FlexNet Operations entitlement are *regular* and *bulk*. A regular entitlement is used when the licensee is known, and is created for a direct or drop ship order. It represents a customer's right to use or access a product. A bulk entitlement is used when the licensee is not immediately known and the entitlement must flow through channels. It represents a large number of individual entitlements, for one or more products, that will move through a channel flow or will be claimed by a licensee/end customer (bulk entitlements, an advanced topic, is not covered in this getting started section).

Line Item States

Like entitlements, line items also have states:

- **Draft** - A line item is created and can be edited in the draft state.
- **Deployed** - A line item must be deployed to be activated. Deploying a draft line item allows it to be activated, upgraded, upsold, or renewed.
- **Inactive** - Existing activations against an inactive line item cannot be returned, repaired, or rehosted. Inactive line items can be changed back to a deployed state as necessary.
- **Test** - Test line items can be defined for draft products and license models, and enable testing to ensure that products and license models are defined correctly.
- **Obsolete** - A line item can be made obsolete if it is no longer required or if it was created and deployed in error. An obsolete line item cannot be activated. Activations of an obsolete line item cannot be rehosted. The obsolete state is permanent; when a line item is made obsolete, it cannot be changed back to a deployed state.



Note - An entitlement that has been activated on a device can have its state changed to *Inactive* or *Obsolete* only if the configuration option **Allow used entitlement/line item state change to Inactive or Obsolete** is selected.

When this configuration option is selected, an entitlement or line item that has been activated on a device can still be used until the license expires, even if the entitlement or line item has been deactivated or made obsolete.

For more information, see [General Options](#) in [Configuring System Settings](#).

Entitlement Creation Exercises

These exercises use examples to guide you through the following entitlement tasks:

Exercise	Description
Creating and Configuring an Entitlement	Create and configure an entitlement for product PhotoPrint.
Deploying an Entitlement	Deploy the product PhotoPrint entitlement.
Reviewing an Entitlement on the End-User Portal	Log in to the FlexNet Operations End-User Portal, as customer Lisa Barry, to review the PhotoPrint entitlement.

Creating and Configuring an Entitlement

In this exercise, you create and configure an entitlement for the product PhotoPrint that you deployed in the [Product Creation](#) topic.

Prerequisite

- Complete the [Account and User Creation](#) and [Product Creation](#) exercises



Task

To create an entitlement for PhotoPrint

- Log in to the FlexNet Operations Producer Portal if you logged out after completing the [Product Creation](#) exercises.
- Click **Entitlements > Create**. The **Entitle Customers to Licenses** page appears.
- Under **Create An Entitlement**, enter the entitlement attributes:
 - Entitlement ID:** Select **Specify** from the drop-down list and type **ENT-PhotoPrint** in the box to the right.
 - Keep the default values for all other attributes.

Note that the entitlement is created in the **Draft** state.



Task

To entitle the customer user to product PhotoPrint

- Under **End Customer And Channel Partners** for entitlement ENT-PhotoPrint, click **Add**. The **End Customer And Channel Partners** window opens.
- On the **Customers** tab, search for and select BarryPhoto as the account to receive the entitlement, then click **Next**.
- Under **Contacts**, select Lisa Barry as the end user to receive the entitlement email message.
- Click **Save**. The **End Customer And Channel Partners** window closes, and the **Entitle Customers to Licenses** page shows Barry Photography Studio as the end customer and Lisa Barry as the contact.



Task **To configure the** PhotoPrint **line item**

1. On the **Line Items** tab near the bottom of the page, click **New Line Item**. The **Configure Line Item** wizard opens.
2. In wizard step 1, **Select Product**, search for and select product PhotoPrint, then click **Next**.
3. In wizard step 2, **Select Part Number & License Model**, leave the default values as they are. Click **Next**.
4. In wizard step 3, **Configure Product**, enter these line item attributes:
 - **Qty**: Type **1** for the quantity of PhotoPrint copies in this line item
 - **Start Date**: Select **Use First Activation Date** from the drop-down list
 - **Expiration**: Select **Specify Duration** from the drop-down list, enter **1**, then select **Years** from the drop-down list
 - Keep the default values for all other attributes.Click **Next**.
5. For the remaining wizard steps, keep the default value. Click **Next**.
6. In the last wizard step, click **Save** to save the line item and close the **Configure Line Item** wizard.
7. On the **Line Items** tab, click on the **Activation ID** and change it to **ACT01-PhotoPrint**. Note that the PhotoPrint line item expires after 1 year, has a total quantity of 1 copy, and is in the **Draft** state.

Deploying an Entitlement

In this exercise, you deploy the product PhotoPrint entitlement that you created and configured for customer Barry Photography Studio in the previous exercise.



Task **To deploy the product** PhotoPrint **entitlement**

1. On the **Line Items** tab, select the PhotoPrint line item.
2. At the bottom of the **Entitle Customers to Licenses** page, click **Save & Deploy**. The **Line Item State** of PhotoPrint is changed to Deployed and this message appears: Entitlement deployed successfully.
3. On the **Entitle Customers to Licenses** page, click **Email** to send entitlement notification email to Lisa Barry at Barry Photography Studio. The **Entitle Customers to Licenses** page appears with the customer's address in the **Ship To Email** box.



Note ▪ To include additional recipients, type their email addresses into the **Ship To Email** box separated by commas.



Tip ▪ Add your email address to the recipients list and review the PhotoPrint entitlement certificate you receive.

Click **Send**. This message appears: Email sent to the recipients <address list>.

4. Log out of the FlexNet Operations Producer Portal.

Reviewing an Entitlement on the End-User Portal

In this exercise, you log in to the FlexNet Operations End-User Portal as customer Lisa Barry and review the PhotoPrint entitlement.



Task To review the product PhotoPrint entitlement on the End-User Portal

1. Use the Lisa Barry credentials you recorded in the [Creating a Customer End User](#) procedure to log in to the FlexNet Operations End-User Portal. Note the PhotoPrint entitlement listed under **Recent Entitlements** on the home page.
2. Click the PhotoPrint activation ID. In the **Entitlement Details** window that opens, scroll down and review the **ID Info**, **Product Info**, and **Activation Info**. When you are done, click **Cancel** to close the window.
3. Log out of the FlexNet Operations End-User Portal.

Entitlement Creation Next Steps

Refer to these getting started sections for concepts and exercises that guide you through electronic software delivery, usage management, and cloud licensing service tasks:

- [Getting Started with Electronic Software Delivery](#) (*requires the Software Delivery module*)
- [Getting Started with Usage Management](#)
- [Getting Started with Cloud Licensing Service](#)

Refer to this getting started section for concepts and exercises that guide you through advanced account management tasks:

- [Getting Started with Advanced Organization Management](#)

Refer to these getting started sections for concepts and exercises that guide you through licensing activation and support tasks:

- [Getting Started with FlexNet Embedded Licensing](#)
- [Getting Started with FlexNet Publisher License File-Based Licensing](#)
- [Getting Started with FlexNet Publisher Trusted Storage-Based Licensing](#)
- [Getting Started with Non-FlexNet Licensing Technologies](#)

Entitlement Creation Advanced Topics

Bulk Entitlements

Bulk entitlements are used for channel sales or redistributors who order large quantities of a product, each copy of which is expected to be resold to a different retail end user.

Importing Entitlements

Entities, including entitlements, can be imported to and exported from a FlexNet Operations database into other Operations databases. This enables data migration between different FlexNet Operations installations.

Test Entitlements

Test entitlements allow testing of draft products and license models before they are deployed. All entitlement actions can be performed on test entitlements, but test entitlements cannot be moved to any other state.

Maintenance Entitlements

Maintenance is an unlicensed product that represents additional rights that a customer can purchase with a product. For example, maintenance can give the customer the right to technical support, upgrades, updates, or new platforms for the product for the duration of the maintenance period. A maintenance product cannot exist in an entitlement by itself; it must be associated with a product line item.

Merging Entitlements

Entitlements can be reassigned to another account when two accounts merge into one. When an entitlement is merged, everything in the entitlement remains the same except the *Account* value, which is changed to reflect the new account.

Transferring Entitlements

License rights in a single entitlement can be transferred from one account to another. All of the entitlement's line items are transferred. Line items can also be transferred individually.

Splitting Entitlements

Producer and partner users can split entitlements on the End-User Portal, if this functionality is enabled.

Bulk Operations

All of the following operations can be performed as non-bulk operations also.

Product Upgrades

An upgrade allows a customer to replace an older version of a product with a newer version, such as moving from Calculator version 4.5 to Calculator version 5.0.

Product Upsells

An upsell allows a customer to replace a product with another that has more features, such as moving from Paint Standard Edition to Paint Professional Edition.

Product Renewals

A renewal allows a customer to extend a licensed product's existing entitlement to a date farther in the future.

Getting Started with Electronic Software Delivery

The section *Getting Started with Electronic Software Delivery* presents fundamental electronic software delivery concepts and uses exercises to lead a Producer Portal user through basic download management tasks. The intended audience for this getting started section is the first-time Producer Portal user, or one without FlexNet Operations training or experience.



Version • *Electronic software delivery features are only available for producers who purchase the Software Delivery module.*

Table 16-1 • Electronic Software Delivery Topics

Section	Description
Introduction	Overview of this getting started section and a summary of FlexNet Operations electronic software delivery features.
About Electronic Software Delivery	A discussion of basic FlexNet Operations electronic software delivery concepts. This section introduces download packages, containerized applications, download files, license agreements, and producers.
Electronic Software Delivery Setup for Distributing Files	A series of electronic software delivery setup exercises that demonstrate how to deliver your software electronically via the End-User Portal. The end of this section also provides brief descriptions of more advanced topics and explains where to find more information about them.
Electronic Software Delivery Setup for Containerized Applications	A series of exercises that guide you through the steps of distributing Docker images and Helm charts via download packages, including pushing/pulling images and charts to and from the Revenera registry.

To view a brief, informative video that walks you through the exercises in *Getting Started with Electronic Software Delivery*, click [here](#). We recommend that you read this getting started section in full, to gain an understanding of the concepts it covers, before you view the video.

Introduction

This section includes a summary of prerequisites and FlexNet Operations electronic software delivery features.

- [Prerequisites](#)
- [The License Lifecycle: Electronic Software Delivery](#)
- [The Electronic Software Delivery Module](#)

Prerequisites

Before you begin the exercises in this getting started section:

- The FlexNet Operations demonstration database and seed data must be loaded. (Reverera loads this data as part of the on-boarding process.)
- You must have a FlexNet Operations Producer Portal login.
- The Producer Portal must be configured to Show Product Lines functionality.

Additionally, the exercises in this getting started section make use of the product, features, and entitlements created in the early exercises of the section [Getting Started with Entitlement Management](#). Any product will suffice, as a sample to which download packages can be linked, but the exercises here use the product created in [Getting Started with Entitlement Management](#).

The License Lifecycle: Electronic Software Delivery

The FlexNet Operations license lifecycle is a repeating process of producer and customer activities, as depicted in the figure and described below.



Figure 16-1: FlexNet Operations License Lifecycle

- **Create Products**—Create product definitions that are used to generate licenses.
- **Order/Entitle**—Define an account’s rights to obtain licenses for your products.
- **Deliver/Install**—Deliver the application software to the customer and install that software.
- **Activate**—Deliver licenses to the customer.
- **Return/Rehost**—Manage license transfers from one user or system to another.
- **Maintain/Update**—Deliver software updates to the customer.
- **Upsell/Renew**—Renew customer licenses, or sell the customer additional product functionality.

The Electronic Software Delivery Module

The Electronic Software Delivery module adds electronic software delivery support to FlexNet Operations. Producers who use FlexNet Operations with the Electronic Software Delivery module define their downloads as part of the product packaging process. The downloads they define are available to entitled end users in the End-User Portal.

Downloads are specified as download packages. A download package describes a group of files or containerized applications (Docker images and Helm charts) or both and relates that group with a product, a producer, and, optionally, a license agreement (sometimes called an end-user license agreement or EULA, for short).




Figure 16-2: Download Packages Associations

A product can have many download packages, and download packages can be associated with one or more products. Download packages collect files or containerized applications into groups that might comprise a software release, a component, or any other grouping that fits your account's needs.

For producers who use FlexNet Operations with the Electronic Software Delivery module, the Producer Portal includes features for managing download packages, files, agreements, and producers. The Products menu includes links for creating and managing these items. Also, product lines, which are otherwise optional, are required for producers who use the Electronic Software Delivery module.

Containerized applications are managed and stored in a separate registry (either hosted by Revenera or hosted by you, the software producer).

About Electronic Software Delivery

This section introduces electronic software delivery concepts. Electronic software delivery setup is part of product packaging, the first stage of the FlexNet Operations license lifecycle.

Table 16-2 • Electronic Software Delivery Concepts

Topic	Description
Download Packages	Discusses what download packages are and how they are used in FlexNet Operations.
Download Files	Covers the basics of download files and file images.
Containerized Applications	Introduces containerized applications, the Revenera registry and how to access it, and the concept of projects within the registry.
License Agreements	Describes how license agreements are connected with electronic software delivery.
Producers and Product Lines	Discusses the use of producers as a mechanism for grouping product lines and download packages in the End-User Portal.

See Also

[The Electronic Software Delivery Module](#)

Download Packages

Download packages are groups of files that can be related to one or more products and tied to a producer and a product line. Optionally, a download package can be associated with a license agreement as well.

It is through a download package's relationship to products that FlexNet Operations determines which download packages an end user is entitled to. End-User Portal users see downloads for the products to which they have entitlements.

On the End-User Portal, download packages are grouped by producer and product line so that entitled users can navigate hierarchically through the producer, product line, product, and version to find the downloads they require. And when optional license agreements are associated with a download package, the End-User Portal shows the agreement before allowing end users to download files.

Download Files

On the Producer Portal, you can add and manage the files you want to make available for your customers to download from the End-User Portal. You can add a file by creating a file definition for it and then uploading its file image.

When you create a file definition in the Producer Portal, you specify a file description and file ID. Then, you upload the file image from your local system into FlexNet Operations. Without the file image upload, the file definition in FlexNet Operations has no payload when a customer tries to download it from the End-User Portal.

The creation of a download file follows the sequence below:

1. Create the file definition—Create a placeholder for the file image in FlexNet Operations and give the file, at minimum, a file ID. Other file details are optional at this point.
2. Upload the file image—Copy the actual file into FlexNet Operations. This file is what gets delivered to End-User Portal users when they download the file.
3. Associate the file with one or more download packages—Download packages collect one or more files and tie them to a product. Without any association to a download package, the file will never appear for download on the End-User Portal.

Once a file has been added and associated with a download package, it is available for End-User Portal users to download from any product to which the download package is associated and to which the End-User Portal user is entitled.

Containerized Applications

In this documentation, the term “containerized applications” refers to Docker images and Helm charts.

Like download files, you distribute containerized applications by associating them with a download package. However, containerized applications are not stored in the FlexNet Operations database, but in a separate registry that is hosted by Reverera or hosted by you, the software producer. You manage your containerized applications by associating them with a download package in FlexNet Operations, and by tagging and pushing them to their corresponding [project](#) in the Reverera registry using a Docker or Helm command-line interface (CLI).

Entitled customers can view the download packages and any associated Docker images or Helm charts in the End-User Portal. The End-User Portal also shows the path and pull command for downloading an image or chart directly from the registry. Customers must have a Docker or Helm client (CLI) installed to be able to pull images or charts from the registry.

About the Reverera Registry

The Reverera registry is a central place to manage and distribute your Docker images and Helm charts. Software producers and end-users use a Docker or Helm CLI to connect to the registry.

The following deployment options of a Reverera registry are available:

- **Shared Registry**—A registry that supports multiple tenants in the Reverera datacenter. To distinguish between tenants, each download package (as well as the resulting projects in the registry, see [About Projects in the Reverera Registry](#)) is automatically prefixed with the 4-character tenant ID. For tag, push, and pull operations, the path of Docker charts or Helm images must be edited to include this tenant ID.
- **Dedicated Registry**—Tenants have exclusive access to one registry instance in the Reverera datacenter. Download packages and projects do not require a prefix.
- **Open Registry (Bring Your Own)**—Software producers provision their own registry, which must be a Harbor instance. Software producers who choose this option need to communicate the connection details for their Harbor registry to Reverera to enable FlexNet Operations to interact with this registry.


Refer to the standard Docker and Helm documentation for information about viewing images and charts in a registry.

Accessing the Reverera Registry

You need the URL and registry secret to access the Reverera registry.

Registry URL

The URL for accessing the Reverera registry depends on the deployment type and has the following format:

Deployment Type	URL
Shared registry	<ul style="list-style-type: none"> ● UAT: https://container-registry.uat-uswest1.reverera.com ● Production: https://container-registry.uswest1.reverera.com
Dedicated registry	<ul style="list-style-type: none"> ● UAT: <a href="https://container-registry.uat<tenant-ID>-uswest1.reverera.com">https://container-registry.uat<tenant-ID>-uswest1.reverera.com ● Production: <a href="https://container-registry.<tenant-ID>-uswest1.reverera.com">https://container-registry.<tenant-ID>-uswest1.reverera.com <p> Note ▪ Replace <tenant-ID> with your 4-character tenant ID.</p>
Open Registry (Bring Your Own)	<p>URLs are as specified by the software producer.</p> <p>Producers who use the Open Registry model need to communicate the URL to their respective producer users.</p>



Tip ▪ The registry URL can be displayed on the **View Download Package** page in the Producer Portal (see [Identifying Syntax for “pull” Command](#)) or in the pull command tooltip on the Download List page in the End-User Portal (see [“Viewing Details of Containerized Applications” in the FlexNet Operations End-User Portal Help Library](#)).

Registry Secret

Producer users use their FlexNet Operations user name and the container registry secret found in their profile page to log on to the Reverera registry. Customer users use their End-User Portal login and their container registry secret to log on to the Reverera registry.

A registry secret is available for all users (producer user and end users) who have been copied by FlexNet Operations to the Reverera registry and have been associated by FlexNet Operations as members to a [project](#).



Task **To determine your container registry secret**

- **Producer users**—in the Producer Portal, point to the **User** menu (next to the System menu at the top right corner of the Producer Portal page) and click **My Profile**.
- **Customer users**—in the End-User Portal, point to the **User** menu (next to the System menu at the top right corner of the End-User Portal page) and click **Profile**.

The option **Container registry secret** shows your secret. You can use **Copy** to copy the secret to the clipboard.

About Projects in the Reverera Registry

When you create a download package in FlexNet Operations that supports the distribution of containerized applications, a “project” is created in the Reverera registry. A project reflects the information that FlexNet Operations holds about the corresponding download package, such as, for example, the producer users that are associated with the download package. A project is empty until it is mapped to the images and charts that you push to the registry.



Note - The project name is prefixed with your tenant ID unless you are using a dedicated or open registry.

Important Information for Open Registry Users

All configuration tasks (such as adding and removing projects or users) are handled by FlexNet Operations. Software producers who use the Open Registry (Bring Your Own) model must not do any of the following:

- Alter the project structure in the registry, either by adding projects or removing them
- Alter the user lists directly in the registry, either by adding users or removing them, or by editing membership information

License Agreements

In FlexNet Operations, producers can add agreements that can be tied to one or more download packages.

A click-through or end-user license agreement (EULA) commonly contains content supplied by your legal department. The license agreement is an optional attribute of a download package.

In the Producer Portal, producers add agreements by providing an agreement name and the content for the agreement text. (The agreement content can be plain text or HTML.) Then, the agreement can be linked to a download package on the Edit Download Package page.

When an agreement is connected to a download package, the End-User Portal prompts users to agree to the terms of that agreement before proceeding with the download.

Considerations

The EULA is presented to the user the first time a user downloads a file from the package. Subsequent downloads from the same download package do not require the user to accept the EULA unless the EULA has been changed or updated. The EULA acceptance date is always a date prior to the file download start date. This is because the EULA has to be accepted before the file is downloaded.

Producers and Product Lines

When an end user is entitled to downloads from more than one producer, the End-User Portal groups download packages by producer and then product line. For this reason, both Producer and Product Line are required attributes for download packages. Each download package can have only one producer and only one product line.

Producers

Although FlexNet Operations documentation frequently refers to Producer Portal users—typically software publishers or intelligent device manufacturers—as “producers,” this term also refers to the logical entities that Producer Portal users must define as part of their electronic software delivery setup.

Many software publishers and intelligent device manufacturers only use a single producer. In this case, the Producer attribute typically reflects the name of the user’s account. Others define multiple producers and use the Producer attribute to distinguish between different product groups or families or simply as an additional layer of navigation before end users choose a product line. When you click List Producers in the Products menu, the Producer Portal displays a list of all the producers your account has created.

Product Lines

Product lines allow you to group, classify, and describe products and to control how download packages are presented in the End-User Portal. Product lines can also be used to define end-user access rights to product information. In the End-User Portal, users can only see the product lines to which their user accounts are linked.

Display of Downloads in the End-User Portal

In the End-User Portal, the producer is the highest level of grouping for products lines, download packages, and files. Users who are entitled to products of more than one producer see a list of producers when they look for downloads. For example, users who click List Downloads from the Downloads menu in the End-User Portal must first choose from a list of producers and then from a list of product lines to show a list of download packages for that product line. If an end user is entitled to downloads from only one producer, the End-User Portal skips the producer list and shows product lines directly.



Tip ▪ For more information about other tasks and topics related to the Electronic Software Delivery module, see [Electronic Software Delivery: Advanced Topics](#) at the end of this document.

Electronic Software Delivery Setup for Distributing Files

This section walks through the process of creating download packages and files for the product created in the early exercises of the section [Getting Started with Entitlement Management](#).

Topic	Description
Before You Begin	This section prepares a customer user to acquire downloads in the End-User Portal and reviews the customer account, customer user, product, product line, and entitlements created in the exercises in the section Getting Started with Entitlement Management .
Creating a Producer	Adds a producer to use when creating a download package.
Creating Download Packages	Adds download packages for the products in the LargeFormat product line.

Topic	Description
Associating Download Packages with a Product	Links the new download packages to their respective products.
Creating Download Files	Creates files and uploads file images for the files that will be the deliverables in the download packages.
Associating Download Files with Download Packages	Links the new files with the download packages to tie products to their deliverables.
Viewing and Downloading Files from the End-User Portal	Uses an end user account entitled to the PhotoPrint product to view and download the files for PhotoPrint Installer Package and PhotoPrint Documentation Package.
Electronic Software Delivery: Advanced Topics	Briefly introduces advanced electronic software delivery topics and explains where to get additional information on them.

Before You Begin

The exercises in this section make use of the entities created as part of the exercises in [Getting Started with Entitlement Management](#). This section lists the customer account, customer user, product, product line, and entitlements created in [Getting Started with Entitlement Management](#). For Producer Portal users who have not yet created their own products and customer users, these items are necessary for the rest of the exercises in this section.

Entity Type	Entities
Customer Account	Barry Photography Studio
Customer User	Lisa Barry
Product	PhotoPrint This product includes the following features: <ul style="list-style-type: none"> ● Print ● PrintHighQualityColor ● PrintToPDF As indicated in the section Getting Started with Entitlement Management , the features, above, are among those pre-defined in your environment's demo data.
Product Line	LargeFormat
Entitlement	ENT-PhotoPrint

If these entities, such as the entitlement, ENT-PhotoPrint, do not yet exist in your FlexNet Operations instance, follow the exercises in the section [Getting Started with Entitlement Management](#) to create the necessary entities.



Important - If the customer user, Lisa Barry, already exists but is not associated with an email address you control, you must create another customer user in the Barry Photography Studio account with the Portal User role. Choose an email address you control for this new customer user so that you can use it to log in to the End-User Portal and see the downloads.

Later in this section, we create download packages and files to be the deliverables for the PhotoPrint product.

Creating a Producer

In this exercise, you add the producer, ABC Networks, Inc. Producer is a required attribute for the download packages that are created later in this section.

Prerequisites

- Review of the key concepts in the previous section, [About Electronic Software Delivery](#)
- FlexNet Operations login



Note - If the producer, ABC Networks, Inc. already exists in your FlexNet Operations instance, you can skip this exercise.



Task **To add the ABC Networks, Inc. producer**

1. Log in to the Producer Portal.
2. Click **Products** > **Create Producer**. The Producer Portal opens the Create Producer page.
3. In the **Producer ID** box, type **ABCNetworks**.
4. In the **Producer Name** box, type **ABC Networks, Inc.** This value is what the End-User Portal shows to your end users when they choose among multiple producers.

Create Producer

Fill out the information for the new Producer and click **Save** to add it. Once you have created a Producer, it will appear in the drop down lists on screens where you maintain the Products and Download Packages, and you can associate them.

Producer ID* ? ABCNetworks
Producer Name* ? ABC Networks, Inc.

Save

Figure 16-3: The Create Producer page for ABC Networks, Inc.

5. Click **Save**.

The Producer Portal saves the new producer and shows the List Producers page.

Creating Download Packages

In this exercise, you add two download packages for the PhotoPrint product:

- PhotoPrintInstaller
- PhotoPrintDocumentation



Task *To create the PhotoPrintInstaller download package*

1. In the Producer Portal, click **Products > Create Download Package**. The Producer Portal opens the Create Download Package page.
2. On the Create Download Package page, set values for the following attributes in Download Package Details.

Attribute	Value
Download Package ID	PhotoPrintInstaller
Download Package Name	PhotoPrint Installer Package
Extended Description	Includes the installer and release notes for PhotoPrint.
Effective Date	Keep the current date default value.
Expiration Date	Set for one year from current date.
Download Package Producer	ABC Networks, Inc.
Product Line	LargeFormat
Restrict to US/CANADA (NLR)	Yes

Keep the default values for all other attributes.

3. For End-User Download Instructions, type the following:
Review system requirements in the release notes (included) prior to running the installer.

Create Download Package

To add a new Download Package fill out the form below. Clicking the **Save Download Package** button will add the new Download Package then display it in view mode. Clicking the **Save & add another** button will add the Download Package and then return to the **Add Download Package** page. To add files to this new Download Package click the **Save & add file** button. To associated already existing files to this new Download Package click the **Save & associate file** button.

Download Package Details

Download Package ID*

Download Package Name*
Show languages

Extended Description
Show languages

Container Delivery Yes No

Version

Release Group

Effective Date* 📅

Expiration Date* 📅

Archive Date 📅

Download Package Producer* ▼

Product Line* ▼

OR Enter Product Line ID

End User License Agreement ▼

Physical Distribution Available* Yes No

* Required information

Restrict to US/CANADA (NLR)* Yes No

If "Restrict to US/CANADA (NLR)" is set to "No", ECCN, ENC, and CCATS codes must be entered in **valid combinations**. You will not be able to select an ENC or CCATS code if it's not a valid option in relation to the selected ECCN code.

ECCN*

ENC*

CCATS*

+ **add another ccats**

Adds another CCATS text entry box (all existing text entry boxes must be populated prior to adding another).

End-user Download Instructions

Download Instructions
Show languages

Figure 16-4: The Create Download Package page for PhotoPrint Installer Package.

4. Click **Save**.

The Producer Portal adds the PhotoPrintInstaller download package and shows its **View Download Package** page. Repeat these steps to create the PhotoPrintDocumentation download package using the values in shown below.

- Download Package Details:

Attribute	Value
Download Package ID	PhotoPrintDocumentation
Download Package Name	PhotoPrint Documentation Package
Extended Description	Includes release notes and user guide for PhotoPrint.
Effective Date	Keep the current date default value.
Expiration Date	Set for one year from current date.

Attribute	Value
Download Package Producer	ABC Networks, Inc.
Product Line	LargeFormat
Restrict to US/CANADA (NLR)	Yes

- End-User Download Instructions:

PhotoPrint documentation includes PDF files for release notes and the PhotoPrint User Guide.

The Producer Portal adds the PhotoPrintDocumentation download package and shows its **View Download Package** page.

Associating Download Packages with a Product

In this exercise, you associate the PhotoPrintInstaller and PhotoPrintDocumentation download packages with the PhotoPrint product.



Task

To associate the PhotoPrintInstaller download package to the PhotoPrint product

1. In the Producer Portal, click **Products > Search Download Packages**. The Producer Portal opens the **Search Download Packages** page.
2. On the **Search Download Packages** page, type a value for **Download Package ID: PhotoPrintInstaller**.
3. Click **Search**. The Producer Portal opens the **Search Results: Download Packages** page and shows the PhotoPrintInstaller download package in the search results.
4. Click **PhotoPrintInstaller**. The Producer Portal opens the **View Download Package** page for PhotoPrintInstaller.
5. On the **View Download Package** page, click **Associate > Associate to Product**. The Producer Portal opens the Associate this Download Package to Products page.
6. In Search Products, for **Product ID** type **Photo*** and click **Search**. The Producer Portal shows a list of products with matching product IDs.

Associate this Download Package to Products

Listed below are the results of your search. To associate this Download Package to Products check the box next to the Product(s) you want to associate this Download Package to and click the Associate this Download Package to the Selected Products button.

Download Package ID PhotoPrintInstaller
System Download Package ID 4020563

Download Package Name PhotoPrint Installer Package
Version

1 to 1 of 1 Show 25 per page Search again

	System Product ID	Product ID	Product Name	Product Producer	Product Product Line	Product Status	Download Packages	License Group
<input checked="" type="checkbox"/>	4020553	PhotoPrint::12.0	Sends to PDF file, prints normal quality, or prints high quality.	DEFAULT	LargeFormat	ACTIVE	0	

[Associate download package to the selected products](#)

Figure 16-5: In Search Products, use Photo* to find the PhotoPrint product.

7. Select the check box for **PhotoPrint::12.0** and then click **Associate Download Package to Selected Products**.



Important - Notice that the product ID for PhotoPrint is a combination of the product name and product version: **PhotoPrint::12.0**. This is how FlexNet Operations identifies the product, internally. One ramification of the product ID syntax is that a search for the product by its product name, **PhotoPrint**, does not match the product ID. For best results, use an asterisk as a wildcard character to be sure your product search captures the product you are looking for. For example, **Photo*** or **PhotoPrint*** successfully finds PhotoPrint.

The Producer Portal saves the product-download package association and shows the Where Download Package Used page for PhotoPrintInstaller.

Repeat the steps above to associate the PhotoPrintDocumentation download package with the PhotoPrint product as well.

Creating Download Files

In this exercise, you create five download files as the deliverables for the PhotoPrint product.

- PhotoPrintInstaller
- PhotoPrintUserGuide
- PhotoPrintReleaseNotes

For each file, the exercises add a file definition and upload its file image. For these exercises it does not matter what files images you upload for the files. The file images used in these exercises are simple text files with different file names.



Task **To create the PhotoPrintInstaller file**

1. In the Producer Portal, click **Products** > **Create File**. The Producer Portal opens the Create File page.
2. On the Create File page, type values for the following attributes.

Attribute	Value
File ID	PhotoPrintInstaller
File Description	PhotoPrint Installer
Extended Description	Installs PhotoPrint.
Content Detail	Review the release notes prior to running the installer. See the PhotoPrint User Guide for more information.

Keep the default values for all other attributes.

Create File

To add a new File fill out the form below. Clicking **Save** will add the new file and display the new file in view mode. Clicking **Save & add another** will add the file and then return you to the Add a File page. To upload a file image click the **Save & upload file** button.

The screenshot shows a form with the following fields and values:

- File ID: PhotoPrintInstaller
- File Description*: PhotoPrint Installer
- Extended Description: Installs [PhotoPrint](#).
- File Name: (empty)
- Content Detail: Review the release notes prior to running the installer. See the [PhotoPrint User Guide](#) for more information.




Figure 16-6: The Create File page for PhotoPrintInstaller.

3. Click **Save & Upload File**. The Producer Portal opens the Upload File page.

Upload File

After the file definition has been added the next step is to upload the file image/binary. Choose one of the methods below. During the upload process these data fields: File Name, File Size, File Contents (for .zip and jar files), and MD5 CheckSum will become populated and their status updated to "LOADED".

View Edit Associate

File Details

File ID [?] PhotoPrintInstaller
System File ID [?] 5302783
Alias No

File Description [?] PhotoPrint Inst:
File Name [?]
File Status [?] NOT_LOADED

Figure 16-7: The Upload File page for PhotoPrintInstaller.

4. Click **Choose File** and select a file to upload. (Button names may vary for different web browsers and operating systems.)
5. Click **Upload**.

The Producer Portal uploads the file image, saves the file, and shows its View File page.

Repeat these steps, above, to create file definitions and upload file images for PhotoPrintUserGuide and PhotoPrintReleaseNotes. Use the values below for the file definitions. Use any small file as the file image. (For these exercises we used text files renamed to reflect their prospective file contents.)

- PhotoPrintUserGuide:

Attribute	Value
File ID	PhotoPrintUserGuide
File Description	PhotoPrint User Guide
Extended Description	Includes a PDF of the PhotoPrint user Guide

- PhotoPrintReleaseNotes:

Attribute	Value
File ID	PhotoPrintReleaseNotes
File Description	PhotoPrint Release Notes
Extended Description	Includes a PDF of the PhotoPrint Release Notes

Next, you will associate these files to their download packages and review the customer experience in the End-User Portal.

Associating Download Files with Download Packages

In this exercise, you associate the download files with their download packages, as shown in the table below.

Download Package	Download Files
PhotoPrintInstaller	PhotoPrintInstaller
	PhotoPrintReleaseNotes
PhotoPrintDocumentation	PhotoPrintUserGuide
	PhotoPrintReleaseNotes

These associations complete the connection between the download files and the product to which the customer user, Lisa Barry, is entitled.



Task *To associate the PhotoPrintInstaller download package with its download files*

1. In the Producer Portal, click **Products > Search Download Packages**. The Producer Portal opens the Search Download Packages page.
2. On the Search Download Packages page, type a value for **Download Package ID: PhotoPrintInstaller**.
3. Click **Search**. The Producer Portal opens the Search Results: Download Packages page and shows the PhotoPrintInstaller download package in the search results.
4. Click **PhotoPrintInstaller**. The Producer Portal opens the **View Download Package** page for PhotoPrintInstaller.
5. On the **View Download Package** page, click **Associate > Associate Files**. The Producer Portal opens the Associate Files to this Download Package page.
6. Enter the following in **File IDs: PhotoPrintInstaller, PhotoPrintReleaseNotes**.

Associate Files to this Download Package

To associate files to this Download Package either enter in the file IDs and click the **Associate files** button or if you don't know the IDs perform a search and a list of files that meet your criteria will be displayed.

Download Package Details

Download Package ID ⓘ PhotoPrintInstaller
System Download Package ID ⓘ 4020563
Download Package Name ⓘ PhotoPrint Installer Package
Version ⓘ

Enter the File IDs of Files to Associate to this Download Package

File IDs PhotoPrintInstaller,
PhotoPrintReleaseNotes //

Use System IDs

Multiple File IDs can be entered one per line or separated by commas. To enter System File IDs, check the box "Use System IDs" below the input box. Wildcards can not be used.

Associate files

Figure 16-8: The Associate Files to this Download Package page with file IDs for the PhotoPrint Installer Package.

7. Click **Associate Files**.

The Producer Portal makes the file associations with the PhotoPrintInstaller download package and shows its **View Download Package** page. Notice that the **View Download Package** page now shows the two associated files: PhotoPrintInstaller and PhotoPrintReleaseNotes.

Repeat the steps, above, to make similar associations between the PhotoPrintDocumentation download package and the PhotoPrintUserGuide and PhotoPrintReleaseNotes files.

When both download packages are associated with their download files, you are ready to review the End-User Portal experience.

Viewing and Downloading Files from the End-User Portal

In this exercise, you log in to the End-User Portal and navigate through to view your downloads. Use the customer account, Barry Photography Studio (created as part of the exercise sets in the section [Getting Started with Entitlement Management](#)). That account is now entitled to the PhotoPrint product and its downloads.



Task Logging in to the End-User Portal

1. In a web browser, navigate to the End-User Portal.

`https://<siteID>.flexnetoperations.com/flexnet/operationsportal/`

Replace <siteID> with your organization's DNS name or the specific site ID supplied by Revenera. For more information about the site ID, see [FlexNet Operations Environments](#).

2. On the End-User Portal Login page, type values for the Username and Password fields.
 - **Username**—The email address you used when you created the user Lisa Barry.

- **Password**—The password you setup for the Lisa Barry user account. If you have not logged in to the End-User Portal, previously, you must use the temporary password included in the welcome message to Lisa Barry and first create a new password and security question/response before you can log in.

3. Click **Log In**.

The End-User Portal opens to the Home page. Notice that Barry Photography Studio has an entitlement to PhotoPrint and downloads available for LargeFormat—the product line to which PhotoPrint belongs.



Note ▪ These instructions assume you control the Lisa Barry user account as described in *Before You Begin* and that PhotoPrint is the only product to which that account is entitled. When an end user is entitled to product lines from multiple producers, the Downloads panel first lists producers, like ABC Networks, Inc., instead of product lines.



Task **Navigating the End-User Portal and downloading files**

1. In the End-User Portal, use the Downloads menu to list the downloads available to you. Click **Downloads > List Downloads**. The End-User Portal opens the Downloads page. This page shows a link for the product line, LargeFormat.



Note ▪ If the demonstration account, Lisa Barry, has been entitled to products from other producers, the End-User Portal first shows a list of producers on the Product List page. Click a producer name to show entitled product lines. In this case, click **ABC Networks, Inc.**

2. Click **LargeFormat**. The End-User Portal shows the Download Packages page for the LargeFormat product line: PhotoPrint Installer Package and PhotoPrint Documentation Package.
3. Click **PhotoPrint Installer Package**. The End-User Portal shows the Downloads page for the PhotoPrint Installer Package download package. To view file details, click **+** by the file name.

Notice that the Download Instructions value you specified on the Producer Portal appears right under the download package name: “Review system requirements in the release notes (included) prior to running the installer.” Also, notice that the Extended Description value appears in the expanded file details: “Includes a PDF of the PhotoPrint Release Notes.”

Downloads

PhotoPrint Installer Package

Review system requirements in the release notes (included) prior to running the installer.

	File Description	File Size	File Added	File Name
<input type="checkbox"/>	PhotoPrint Release Notes Includes a PDF of the PhotoPrint Release Notes	9B	May 28, 2015	PhotoPrintReleaseNotes.pdf MD5 Signature 1e2db57dd6527ad4f8f281ab028d2c70
<input type="checkbox"/>	PhotoPrint Installer	11B	May 28, 2015	PhotoPrintInstaller.exe

Figure 16-9: The Downloads page for PhotoPrint Installer Package showing file details for PhotoPrint Release Notes.

4. Click your browser's Back button to return to the Download Packages page for LargeFormat.
5. Click **PhotoPrint Documentation Package**. The End-User Portal shows the download files for PhotoPrint Documentation Package.

Downloads

PhotoPrint Documentation Package

PhotoPrint documentation includes PDF files for release notes and the PhotoPrint User Guide.

	File Description	File Size	File Added	File Name
<input checked="" type="checkbox"/>	PhotoPrint User Guide	11B	May 28, 2015	PhotoPrintUserGuide.pdf
<input checked="" type="checkbox"/>	PhotoPrint Release Notes	9B	May 28, 2015	PhotoPrintReleaseNotes.pdf

Figure 16-10: The Downloads page for PhotoPrint Documentation Package.

6. To download files, select the files you want to download and click **Download Selected Files**. The End-User Portal opens the Download Manager in a pop-up window.



Important • To complete your download, the Download Manager must be installed on your system. If it is not installed, follow the instructions in the Download Manager window to download and run the installer, then accept the license agreement.



Tip • You can also download individual files by clicking on the file name link for the file you want to download.

The End-User Portal downloads the selected files to your operating system's default downloads folder.

This concludes the getting-started exercises for FlexNet Operations users with the Electronic Software Delivery module. For information about more advanced download management options and activities—such as those listed in Advanced Topics (below)—see the appropriate sections in this user guide.

Electronic Software Delivery: Advanced Topics

Restricting Access to Files and Download Packages

Access to individual download packages or files can be controlled by customer account. Using the Producer Portal, producers can create allowed lists or non-allowed lists of the accounts permitted to see a download package or a file in the End-User Portal. For more information, see [Restricting a Download Package](#) and [Restricting a File](#) in the [Packaging Products](#) section.

Visibility of Download Packages for Maintenance Customers

Visibility of download packages is dependent on the Maintenance Line Item expiration date. If there is no maintenance plan, the visibility is based on the expiration date of the line item. If there is a maintenance plan, the visibility is based on the expiration of the maintenance line item. The following table illustrates what is visible based on the maintenance plan in effect. The assumed current date is 1 July 2016.

Customer Name	Line Item Expiration	Maintenance Line Item Expiration	Visibility of Base Download Package	Visibility of Maintenance Download Package
Acme	Perpetual	NA	Yes	Yes
Blandit	January 2018	January 2018	Yes until January 2018	Yes until January 2018
Convallis	Perpetual	Expired	Yes, if the effective date of the base download package was before the maintenance expiration date	Yes, if the effective date of the maintenance download package was before the maintenance expiration date
Dapibus	November 2017	April 2016 February 2017 January 2018	Yes until January 2018	Yes until January 2018
Eusmod	May 2019	January 2018	Yes until May 2019	Yes until May 2019



Important - If an electronic software delivery entitlement has an associated maintenance line item, that maintenance line item's expiration should not be set to Permanent.

Sending Email Notifications for Files and Download Packages

In the Producer Portal, producers can send email messages to end-users entitled to a file or a download package. Instructions for sending email notifications are in the sections [Managing Download Packages](#) and [Managing Download Files](#).

Order Media Requests and Physical Distribution

For producers who want their end users to be able to request download files on physical media, the End-User Portal includes an Order Media control. Configuring the End-User Portal to handle these request requires some configuration in the Producer Portal. For more information, see [About Physical Distribution and Order Media Requests](#) in the section [Packaging Products](#).

Making File Aliases

Aliasing a file creates a duplicate of an existing file that points to the same file image but can be managed separately. File aliases allow you to avoid uploading multiple copies of the same file image. See [About Aliases](#) in the section [Packaging Products](#) for more information about file aliases.

Export Compliance

Producers must specify export compliance settings that define how download delivery is controlled internationally. Export compliance settings are part of a download package. To learn more about export compliance settings, see [About Export Compliance](#) in the section [Packaging Products](#).

Enabling Channel Partners to Download Files

A producer can enable a channel partner to download files, on behalf of end users, for product demonstration and support purposes.

After the product is deployed and associated with a download package, the producer creates the channel partner user, creates an entitlement line item for the product for the channel partner user's account, and assigns an end customer user account to the entitlement.



Important - This option is limited to entitlements with end customer and channel partner user accounts. It does not work for entitlements with only channel partner users.

The channel partner user logs in to the FlexNet Operations End-User Portal with the line item's activation ID, navigates to the **List Entitlements** page, and locates the entitlement in the table. From there, the file can be downloaded using the standard download procedure.

Electronic Software Delivery Setup for Containerized Applications

This section walks through the process of creating a download package that supports the distribution of Docker images and Helm charts. It builds on the exercises in the previous section [Electronic Software Delivery Setup for Distributing Files](#).

Topic	Description
Prerequisites	Discusses the requirements that must be met before attempting the exercises in this section.
Creating a Download Package with Containerized Applications Support	Walks you through the steps for creating the photoprint download package that supports the distribution of Docker images and Helm charts for the LargeFormat product line.
Associating the Download Package with a Product	Demonstrates how to link the new photoprint download package to the PhotoPrint product.
Pushing Containerized Applications to the Registry	Describes the procedure to upload a Docker image and a Helm chart to the Revenera registry, which ties them to their photoprint download package.
Viewing Containerized Applications in the End-User Portal	Discusses the steps to log in to the End-User Portal and to view the photoprint download package and its associated Docker image and Helm chart.
Pulling Docker Images and Helm Charts from the Registry	Downloads the Docker image and Helm chart associated with the photoprint download package from the Revenera registry.

Prerequisites

The following items are prerequisites that need to be fulfilled before you complete the exercises in this section.

Entities

The exercises in this section [Electronic Software Delivery Setup for Containerized Applications](#) make use of the same entities used in [Electronic Software Delivery Setup for Distributing Files](#). Ensure that the following entities exist before you attempt to perform the steps in the following sections.

Entity Type	Entities
Customer Account	Barry Photography Studio
Customer User	Lisa Barry

Entity Type	Entities
Product	PhotoPrint This product includes the following features: <ul style="list-style-type: none">• Print• PrintHighQualityColor• PrintToPDF As indicated in the section Getting Started with Entitlement Management , the features, above, are among those pre-defined in your environment's demo data.
Product Line	LargeFormat
Entitlement	ENT-PhotoPrint
Producer	ABC Networks, Inc.

Docker Images and Helm Charts

These exercises require a Docker image and Helm chart called `photoprint-image` and `photoprint-chart`, respectively. The actual content of the image and chart are not relevant; you can use any image and chart that you have at hand.

You also must have a Docker client and a Helm client (CLI) installed to perform the steps in this section.

Reverera Registry

It is assumed that you have access to the Reverera registry. For more information, see [About the Reverera Registry](#). The Reverera registry can only be accessed using the Docker or Helm command-line interface (CLI).


Creating a Download Package with Containerized Applications Support

In this exercise, you add a download package called `photoprint` that supports the distribution of containerized applications for the `LargeFormat` product line.



Task **To create the photoprint download package**

1. In the Producer Portal, click **Products > Create Download Package**. The Producer Portal opens the Create Download Package page.
2. On the Create Download Package page, set values for the following attributes in Download Package Details.

Attribute	Value
Download Package ID	photoprint  Important - For download packages that support containerized applications, the download package ID can only contain lowercase letters and must start with a letter or number.
Download Package Name	PhotoPrint Package
Extended Description	Download package providing the container artefacts for the PhotoPrint application.
Container Delivery	Select Yes .
Effective Date	Keep the current date default value.
Expiration Date	Set for one year from current date.
Download Package Producer	ABC Networks, Inc.
Product Line	LargeFormat
Restrict to US/CANADA (NLR)	Yes

Keep the default values for all other attributes.

Download Package Details

The screenshot shows a form for creating a download package. The form is titled "Download Package Details" and includes the following fields and options:

- Download Package ID***: photoprint
- Download Package Name***: PhotoPrint Package (with a "Show languages" button)
- Extended Description***: Download package providing the container artefacts for the PhotoPrint application (with a "Show languages" button)
- Container Delivery**: Yes No
- Version**: (empty text field)
- Release Group**: (empty text field)
- Effective Date***: 09/20/2022 (with a calendar icon)
- Expiration Date***: 09/20/2023 (with a calendar icon)
- Archive Date**: mm/dd/yyyy (with a calendar icon)
- Download Package Producer***: ABC Networks, Inc. (ABCNetworks) (dropdown menu)
- Product Line***: (dropdown menu)
- OR Enter Product Line ID**: (empty text field)
- End User License Agreement**: ** None ** (dropdown menu)
- Physical Distribution Available***: Yes No

On the right side of the form, there are additional options and a note:

- Restrict to US/CANADA (NLR)***: Yes No
- ECCN***: (dropdown menu)
- ENC***: (dropdown menu)
- CCATS***: (text entry box)
- + add another ccats**: (button)

A note states: "If 'Restrict to US/CANADA (NLR)' is set to 'No', ECCN, ENC, and CCATS codes must be entered in **valid combinations**. You will not be able to select an ENC or CCATS code if it's not a valid option in relation to the selected ECCN code."

Figure 16-11: The Create Download Package page for the photoprint package.

3. Leave the End-User Download Instructions field blank.
4. Click **Save**.

The Producer Portal adds the photoprint download package and shows its **View Download Package** page. In addition, an (empty) project photoprint has been created in the Revenera registry.

Associating the Download Package with a Product

In this exercise, you associate the photoprint download package with the PhotoPrint product.

After you complete this exercise, the customer user Lisa Barry is added as a member to the photoprint project, because she is entitled to the PhotoPrint product (the entitlement, ENT-PhotoPrint, was created in an earlier exercise, [Getting Started with Entitlement Management](#)).



Task To associate the “photoprint” download package with the PhotoPrint product

1. In the Producer Portal, click **Products > Search Download Packages**. The Producer Portal opens the Search Download Packages page.
2. On the Search Download Packages page, type a value for **Download Package ID**: photoprint.
3. Click **Search**. The Producer Portal opens the Search Results: Download Packages page and shows the photoprint download package in the search results.
4. Click **photoprint**. The Producer Portal opens the **View Download Package** page for photoprint.
5. On the **View Download Package** page, click **Associate > Associate to Product**. The Producer Portal opens the Associate this Download Package to Products page.

6. In Search Products, for **Product ID** type **Photo*** and click **Search**. The Producer Portal shows a list of products with matching product IDs.
7. Select the check box for **PhotoPrint::12.0** and then click **Associate Download Package to Selected Products**.



Important - Notice that the product ID for PhotoPrint is a combination of the product name and product version: **PhotoPrint::12.0**. This is how FlexNet Operations identifies the product, internally. One ramification of the product ID syntax is that a search for the product by its product name, **PhotoPrint**, does not match the product ID. For best results, use an asterisk as a wildcard character to be sure your product search captures the product you are looking for. For example, **Photo*** or **PhotoPrint*** successfully finds PhotoPrint.

The Producer Portal saves the product-download package association and shows the Where Download Package Used page for photoprint.

Pushing Containerized Applications to the Registry

As a result of creating the photoprint download package—which supports containerized applications—in FlexNet Operations, the project photoprint is simultaneously created in the registry. This project is empty until you push a Docker image and Helm chart to the registry. The procedure described in this section ties the photoprint-image Docker image and photoprint-chart Helm chart to the photoprint project in the Reverera registry, which makes them available to the customer user, Lisa Barry.

The section is split into the following subsections:

- [Logging in to the Registry](#)
- [Pushing Docker Images](#)
- [Pushing Helm Charts](#)



Important - For the steps in this section it is assumed that you are accessing a dedicated registry. If you are using a shared registry, you need to use a registry URL without the tenant ID. Also, for the shared registry, the project name is prefixed with your tenant ID. See [About the Reverera Registry](#).

Logging in to the Registry



Task To log in to the Reverera registry

1. In a terminal window on the client machine running Docker, enter a command similar to the following to log in:

```
docker login https://container-registry.uat<tenant-ID>-uswest1.reverera.com
```

where <tenant-ID> is your 4-character tenant ID.
2. You are then prompted to enter your username and password. Your user name is your FlexNet Operations user name. Your password is the container [registry secret](#), which you can find in your user profile.

Pushing Docker Images

After you log in to the registry you can tag and push the Docker image photoprint-image to the registry, where it will be associated with the photoprint project.



Task To tag and push “photoprint-image” to the Reverera registry

1. Enter the following to tag the target image photoprint-image:2.0 that refers to the source image photoprint-image:latest (you can skip this step if the Docker image was tagged when it was built):

```
docker tag photoprint-image:latest container-registry.uat<tenant-ID>-uswest1.reverera.com/  
photoprint/photoprint-image:2.0
```

2. Use the following command to share photoprint-image to the Reverera registry:

```
docker push container-registry.uat<tenant-ID>-uswest1.reverera.com/photoprint/photoprint-  
image:2.0
```

Pushing Helm Charts

In the steps below, replace <user-name> with your FlexNet Operations user name, and <password> with your container registry secret (which you can find in your user profile).



Tip ▪ If you are unsure about the syntax for the `helm repo add` command, navigate to the Downloads page and click the **Add Repo Command** button in the Helm Charts section, which will show the syntax. For more information, see [Identifying Syntax for “helm repo add” Command](#).



Task To push “photoprint-chart” to the Reverera registry

1. Use the following command to add the photoprint-repo repository:

```
helm repo add --username=<user-name> --password=<password> photoprint-repo https://container-  
registry.uat<tenant-ID>-uswest1.reverera.com/chartrepo/photoprint
```

2. Then use the following command to share photoprint-chart to the Reverera registry:

```
helm push --username=<user-name> --password=<password> photoprint-chart photoprint-repo
```

Viewing Containerized Applications in the End-User Portal

In this exercise, you log in to the End-User Portal as the customer user to view the photoprint download package and its associated photoprint-image Docker image and photoprint-chart Helm chart that you created in the previous section. Use the customer account, Barry Photography Studio (created as part of the exercise sets in the section [Getting Started with Entitlement Management](#)). That account is now entitled to the PhotoPrint product and its downloads.

Logging in to the End-User Portal



Task To log in to the End-User Portal

1. In a web browser, navigate to the End-User Portal.

`https://<siteID>.flexnetoperations.com/flexnet/operationsportal/`

Replace <siteID> with your organization's DNS name or the specific site ID supplied by Revenera. For more information about the site ID, see [FlexNet Operations Environments](#).
2. On the End-User Portal Login page, type values for the Username and Password fields.
 - **Username**—The email address you used when you created the user Lisa Barry.
 - **Password**—The password you setup for the Lisa Barry user account. If you have not logged in to the End-User Portal, previously, you must use the temporary password included in the welcome message to Lisa Barry and first create a new password and security question/response before you can log in.
3. Click **Log In**.

The End-User Portal opens to the Home page. Notice that Barry Photography Studio has an entitlement to the PhotoPrint product and downloads available for LargeFormat—the product line to which PhotoPrint belongs.



Note - These instructions assume you control the Lisa Barry user account as described in the [Prerequisites](#) section and that PhotoPrint is the only product to which that account is entitled. When an end user is entitled to product lines from multiple producers, the Downloads panel first lists producers, like ABC Networks, Inc., instead of product lines.

Viewing the “photoprint” Download Package



Task To view the “photoprint” download package and details about its associated images and charts in the End-User Portal

1. In the End-User Portal, click **Downloads > List Downloads**, to list the downloads available to you. The End-User Portal opens the Downloads page. This page shows a link for the product line, LargeFormat.



Note - If the demonstration account, Lisa Barry, has been entitled to products from other producers, the End-User Portal first shows a list of producers on the Product List page. Click a producer name to show entitled product lines. In this case, click **ABC Networks, Inc.**

2. Click **LargeFormat**. The End-User Portal shows the Download Packages page for the LargeFormat product line with the photoprint download package.




Note - If you previously completed the exercises in section [Electronic Software Delivery Setup for Distributing Files](#), the Download Packages page also lists the PhotoPrint Installer Package and PhotoPrint Documentation Package.

3. Click **photoprint**. The End-User Portal shows the Downloads page for the photoprint download package.

The Container Images and Helm Charts sections show the image and chart, respectively, that you pushed to the registry in section [Pushing Containerized Applications to the Registry](#).

4. To view details, in the Container Images and Helm Charts sections:

- a. Click **+** for the image or chart for which you want to display details.

- b. Point to the  icon in the Pull Command column to display the pull command used for downloading the image or chart from the Revenera registry.



Tip • Make a note of the pull commands for the image and chart, because you will use these in the next exercise.

Pulling Docker Images and Helm Charts from the Registry

In this exercise, you use the customer user, Lisa Barry, that you are already familiar with, to pull the image and chart that you uploaded in section [Pushing Containerized Applications to the Registry](#).

Because Lisa Barry is entitled to the PhotoPrint product, which is associated with the photoprint download package, she has permissions to pull images and charts from the Revenera registry. This also means that her profile includes a [registry secret](#), which is required to access the Revenera registry.



Tip • You can use the pull command that you noted down at the end of the previous section, [Viewing Containerized Applications in the End-User Portal](#).

Logging in to the Revenera Registry

You log in to the Revenera registry as customer user, Lisa Barry.



Task **To log in to the Revenera registry**

1. In a terminal window on the client machine running Docker, enter the following to log in:

```
docker login https://container-registry.uat<tenant-ID>-uswest1.revenera.com
```

where <tenant-ID> is your 4-character tenant ID.

2. You are then prompted to enter a username and password.

- **User name**—The email address you used when you created the user Lisa Barry.
- **Password**—The container registry secret, which you can find in Lisa Barry's user profile (see [Accessing the Revenera Registry](#)).

Downloading Docker Images



Task **To pull “photoprint-image” from the Reverera registry**

1. Log in to the Reverera registry, as described in [Logging in to the Reverera Registry](#).
2. Use the following command to pull photoprint-image from the Reverera registry:

```
docker pull https://container-registry.uat<tenant-ID>-uswest1.reverera.com/photoprint/  
photoprint-image:2.0
```

Downloading Helm Charts



Task **To pull “photoprint-chart” from the Reverera registry**

1. Log in to the Reverera registry, as described in [Logging in to the Reverera Registry](#).
2. Use the following command to pull photoprint-chart from the Reverera registry:

```
helm pull photoprint-repo photoprint-chart
```

Getting Started with Usage Management

The purpose of this getting started section is to provide an overview on the use of the FlexNet Operations and FlexNet Usage Management (a feature of FlexNet Operations). These components, when used with FlexNet licensing products, help application producers maximize software revenues and eliminate revenue leakage through new support of increasingly popular usage-based trust but verify, pay-for-use, and pay-for-overage models. Revenera's market-leading compliance management solution provides application producers the flexibility to implement any software licensing model across the entire spectrum—from strict enforcement to usage-based, trust but verify.

This getting started section primarily describes concepts and tasks related to FlexNet Operations with FlexNet Usage Management. For information about implementing an application that performs usage capture, see the appropriate FlexNet licensing documentation. For example, if you are implementing a connected software client that will run in a customer environment, see your FlexNet client documentation: The *FlexNet Embedded Client C SDK User Guide* or the *FlexNet Embedded Client C XT SDK User Guide*.

It is expected that you will use this section *Getting Started with Usage Management* in conjunction with the usage-capture instructions in your FlexNet licensing user guide.

This getting started section is organized into the following subsections.

Table 17-1 ■ Getting Started With Usage Management

Topic	Content
FlexNet Usage Management Concepts	Provides general information about usage-capture and usage-management terminology and tasks.
FlexNet Usage Management Exercises	Provides an introductory walkthrough of preparing FlexNet Operations to work with the FlexNet licensing usage-capture in order to perform usage management.
Advanced FlexNet Usage Management Activities	Provides additional information about usage-capture and usage-management terminology and tasks.

To view a brief, informative video that walks you through the exercises in the section *Getting Started with Usage Management*, click [here](#). We recommend that you read this getting started section in full, to gain an understanding of the concepts it covers, before you view the video.

FlexNet Usage Management Concepts

This section describes general concepts involved in working with FlexNet Usage Management. The following are some of the concepts and terminology used throughout this documentation.

- [Usage Management](#)
- [Metered Licensing](#)
- [Products](#)
- [Features](#)
- [Capability Requests and Responses](#)
- [License Servers](#)
- [Usage Dashboard](#)

Usage Management

FlexNet Usage Management allows producers to flexibly track, view, and report on feature usage in the usage-capture clients. FlexNet Operations' usage management features support compliance management licensing models.

In the FlexNet Operations Producer Portal, you define the metered license model, features, products, and entitlements to model the usage events your clients are capturing. The exercises in this getting started section walk through the setup in the Producer Portal necessary to connect with the “survey” feature included in the FlexNet Embedded licensing code samples.

As usage capture data is collected in your license servers and uploaded to FlexNet Operations, you can also use the Producer Portal to view graphs and gauges of your customers' usage.

Connecting to the back office, producers can also pull usage data in CSV format via reconciliation summary requests.

Metered Licensing

Metered licensing refers to usage-based licensing. In FlexNet Operations, metered licensing starts with the creation of a metered license model and related choices about the reusability, undo interval, and overdraft settings for products that use it. For more information about these settings, see the exercise, [Usage Management: Creating License Models](#).

With a metered license model created, you can define features to match the usage data your usage capture clients are sending and create a product that delivers those features under the rules defined by your metered license model.

Products

Products are packages of features that can be sold by a producer. Products that will support usage management must use a metered license model. Also, producers specify a *usage model* for the product. The usage model defines the length of the reporting period and frequency at which usage data is reset. See [Usage Management: Creating Products](#).



Important • Products using the same feature must be configured with the same usage model per account. For an account, the usage model that is specified for a product containing a specific feature will be the usage model that is used for subsequent entitlements or products containing that specific feature. For example:

- Product A (feature f1) and product B (features f1 and f2)
- Account C is first entitled to product A (feature f1) with usage model Monthly Statements (No Reset)
- Account C is then entitled to product B (features f1 and f2) with usage model Monthly Statements (Reset Monthly)
- Account C will use usage model Monthly Statements (No Reset) for both products A and B because they both contain feature f1 which was included in the first entitlement.

If Account C was first entitled to product B (features f1 and f2) with usage model Monthly Statements (Reset Monthly), this usage model would be used for both products/entitlements for the account.

Features

The smallest unit for which usage can be captured is a *feature*. You define the feature or features that make up your products in FlexNet Operations, and your usage-capture code sends information about these features. In addition, feature-clipping code checks for the availability of certain features to determine a product's functionality.

During execution, your capped-usage or feature-clipping code uses FlexNet licensing functions that attempt to *acquire* a license. The FlexNet licensing libraries validate such conditions as the feature not having expired. If the license acquisition succeeds, your code would then enable the corresponding capability.

For features intended to support usage management, you will also specify units and scale settings. Together, these settings allow you capture usage data in fine detail but report on usage counts with more manageable or meaningful numbers. *Units* define the label to be shown when usage data is reported. *Scale* is the factor by which the raw usage counts are divided. For example, if your usage-capture client tracks the time for which a feature is used in seconds but you want usage reports to show usage in minutes, you might set Units to "Minutes" and Scale to "60." For more about features, see the exercise, [Usage Management: Creating Features](#).

Capability Requests and Responses

When your usage-capture code communicates with FlexNet Operations, the communications involve *capability requests* and *capability responses*. A capability request is generated by the client (either a client reporting usage or requesting features that it will acquire). The request data contains some combination of a host identifier, one or more desired features, and other optional data to pass to FlexNet Operations.

The license server instance then processes the request, reading the various identifiers, desired features, and custom data. If FlexNet Operations determines that the client requires a response, it generates a capability response. The response data contains current license rights available for the client. The capability response is then conveyed back to the client, which processes the response, after which the features in the response can be queried for the sake of detecting if a quota has been exceeded or for feature clipping (programmatically restricting access to features based on the capability response).

Your usage-capture code specifies one or more *desired features*, which represent features whose usage is being reported or features desired for the sake of feature clipping, in the capability request.

Your code also specifies an *operation* in the capability request, which indicates whether it is simply reporting feature usage, or whether a response is expected. The “report” operation is used in uncapped-usage scenarios, when no response is needed; and the “request” operation is used in capped-usage and feature-clipping scenarios, where a response is needed. The request operation can also be used in untrusted environments to report uncapped usage to force a confirmation response from the server, ensuring that the usage has been reported. (There is also an “undo” operation, which enables recent information to be undone, in case of error or canceled usage.)

License Servers

Your usage-capture clients send usage data to a *license server*. The license server can be a local license server or, as in the case in this getting started section, a license server instance in the FlexNet Cloud Licensing Service. In both cases, the license server captures the metered usage data that your usage-capture clients send.

- [Local License Servers](#)
- [Cloud Licensing Service Instances](#)
- [Auto-Provisioning](#)

Local License Servers

Usage-capture clients can send usage data to license servers that you deploy into your customers' enterprises. (The deployment of local license servers is not covered in this getting started section.) Consult your FlexNet licensing documentation for more information about deploying local license servers.

Cloud Licensing Service Instances

For producers who use FlexNet Cloud Licensing Service in addition to FlexNet Operations, license servers can be created in the FlexNet Cloud Licensing Service. These license server instances can be manually created or dynamically generated (using the Auto Provision feature of FlexNet Operations). The chief benefits of using cloud licensing service instances rather than deploying local license servers is the speed with which license servers can be deployed and the ease with which licenses can be mapped to the license server instance.

Auto-Provisioning

When the license model permits auto-provisioning, cloud licensing service instances can be automatically generated by FlexNet Operations.

When auto-provisioning is permitted, FlexNet Operations generates a new license server when an entitlement using such a license model and owned by an end customer account, is deployed. Also, line items included in the entitlement are automatically mapped to the license server instance.

When auto-provisioning is not permitted, producers can create the license server instance manually. In this scenario, the producer uses the **Create License Server** page to create a license server for the end customer and then manually maps the entitlement line items to that server.

The exercises in this getting started section make use of auto-provisioning in the license model to streamline license server creation and entitlement mapping.

Limitations

The following limitations exist for auto-provisioned license servers that have entitlements mapped for metered features:

- License servers cannot be moved to another account.
- Only unused licenses for metered features can be removed using **Licenses > Remove Licenses**.
- License servers can be made obsolete, which will remove all licenses mapped to the server. However, this is not recommended, because future line items will not be mapped automatically to the auto-provisioned license server.

Usage Dashboard

FlexNet Operations enables you to view enterprise customers' current usage data in the Producer Portal. Similarly, your enterprise customers can view their current usage data in Usage Management in the enterprise portal you set up.

The following types of graphs are supported with respect to usage capture. Usage data can also be downloaded as a text file in CSV format. After selecting what usage data to display—as described in [Usage Management: Viewing Usage Information](#)—and selecting the desired usage period, you can select the type of graph in which to display the usage data.



Figure 17-1: Buttons for selecting the graph type

These buttons in FlexNet Operations correspond to usage gauges, tables, timelines, and comparisons, as described in the following sections.

- [Usage Gauges](#)
- [Usage Tables](#)
- [Usage Timelines](#)

Usage Gauges

This type of graph shows usage data as a graphical gauge representing the percentage of usage compared to the overall entitled amount. The green region of the gauge indicates usage of none to 75 percent of the available count; the yellow region indicates 75 percent to 100 percent of the available count; and the red region indicates over 100 percent (overage) of the entitled amount.




Figure 17-2: Usage gauge

Details of the usage information are displayed beneath the gauge.

Usage Tables

Usage information can also be displayed in a textual table.

[Download summary](#)

Meter	Unit	Actual Use	Entitled	Overage (since statement)	Overage (since reset)	%	Interval/Reset	Period
End2EndUHRP_MC-ReCH Download	copies	111	150	0	0	74	3 Month/12 Month	Feb 11, 2015 - May 11, 2015
End2EndUHRP_MUC-NonRe Download	gb	101	100	0	1	101	3 Month/Never	Feb 11, 2015 - May 11, 2015

Figure 17-3: Usage table

Usage Timelines

Usage information can also be displayed in an interactive Flash-based timeline. Commands in the upper left corner enable zooming in to different time periods, and you can click and drag the graph left and right to control the dates for which data are being displayed.



Figure 17-4: Interactive usage timeline

A similar interactive option is the **Compare Meters** graph, which simultaneously displays multiple features' usage information over the same period of time.

The following section describes setting up FlexNet Operations with FlexNet Usage Management to handle usage capture.

FlexNet Usage Management Exercises

This section describes how to get started with FlexNet Usage Management. You will learn about setting up FlexNet Operations to support usage-based licensing and connecting your usage clients to a license server instance hosted in the FlexNet Cloud Licensing Service.

The section is divided into the following subsections.

Section	Description
Prerequisites	Prerequisites for included exercises.
Preparing FlexNet Operations	Exercises to set up FlexNet Operations with FlexNet Usage Management for usage capture. This section includes creating license models, features, products, and entitlements.
Usage Management: Obtaining the License Server URL	Instructions for determining the license server URL to which your usage-capture clients send their usage data.

Section	Description
Usage Management: Running a Usage-Capture Client Example	Brief discussion of running a usage-capture client.
Usage Management: Viewing Usage Information	Instructions for viewing usage graphs and gauges on the Producer Portal.
Usage Management: Next Steps	Identifies other, more advanced usage capture activities covered, briefly, in the following section.

Prerequisites

The following items are prerequisites for developing and deploying usage-capture code with FlexNet Usage Management.

FlexNet Licensing Usage-Capture Client Implementation

It is assumed that you have downloaded your FlexNet licensing platform for implementing an application to perform usage capture. Refer to the corresponding licensing client documentation for information about building the example code and implementing a usage-capture client.

To complete the exercises in this getting started section, users also must have received publisher keys from Revenera.



Note - The creation of a publisher and an identity are covered in the section [Getting Started with FlexNet Embedded Licensing](#).

FlexNet Operations Instance

It is also assumed that you have access to FlexNet Operations via the Producer Portal and the End-User Portal. Producers must have already have their producer account activated and a user account on the Producer Portal in which FlexNet Embedded, FlexNet Usage Management, and FlexNet Cloud Licensing Service features are enabled.

Preparing FlexNet Operations

To prepare FlexNet Operations to receive usage data, you must create and associate several entities using the Producer Portal. Some of these steps are common to any use of FlexNet Operations with FlexNet Licensing, and some steps are specific to FlexNet Usage Management.

This preparation includes the following exercises.

Exercise	Description
Usage Management: Creating License Models	Shows how to create two license models: one for metered products and one for unmetered products.

Exercise	Description
Usage Management: Creating Features	Explains how to create the metered feature, survey, for which metered usage is tracked and an unmetered feature, baseline-client-reg, that is necessary to register usage-capture clients running outside of trusted environments.
Usage Management: Creating a Product Line	Covers the creation of a product line necessary for usage reporting.
Usage Management: Creating Products	Explains how to create two separate products: one for the metered feature and one for the unmetered feature.
Usage Management: Creating an Account and User	Shows how to create a customer account and user to which the new products will be entitled.
Usage Management: Entitling the Account	Describes how to create an entitlement, configure its line items with the new products, and entitle the customer account to those line items.
Usage Management: Viewing the Auto-Provisioned License Server	Explains how to find the Cloud Licensing Service license server that was created when the entitlement was deployed.

After you verify that the new license server was created, the FlexNet Operations preparations are complete. Continue with [Usage Management: Obtaining the License Server URL](#), [Usage Management: Running a Usage-Capture Client Example](#), and [Usage Management: Viewing Usage Information](#).

If you have not previously used FlexNet Operations, see [Getting Started with FlexNet Embedded Licensing](#) for more information.

Usage Management: Creating License Models

In this exercise, you create two license models: one is a usage-based (metered) license model to be used with metered products and the other is an unmetered license model to use with the unmetered product and facilitate client registration.



Note • The unmetered product is used to register usage-capture clients operating in untrusted environments.

Creating a Metered License Model to Track Usage

Usage-based license models are FlexNet Embedded license models that use metered licensing—typically following a metered-capped (limits to usage counts) and metered-uncapped (tracking and reporting but no limits) approach.

To indicate that usage data should be tracked for a feature (capability), you must create a metered license model with appropriate settings. For the example basic uncapped usage client, you will define a metered-uncapped license model.

When working with usage capture, the important settings are **Metered**, **Reusable**, **Undo Interval**, and **Overdraft**, and **Auto Provision**.

- Defining a license model as **Metered** indicates that it is intended for use with usage capture and usage management.
- **Reusable** and **Undo Interval** attributes work together to determine whether usage counts can only increase or are permitted to decrease as well. **Reusable** allows the decrease of feature checkouts, generally. **Undo Interval** optionally expresses a window in which checkouts can be canceled even if **Reusable** is set to **No**.
- The **Overdraft** setting defines the policy for usage over the entitled license count: overdraft can be **Not Used** (no overdraft allowed), **Unlimited** (uncapped usage, as with this example), or defined as a fixed value or percentage of the total entitlement.
- Set **Auto Provision** to **Yes** to support license server auto-provisioning. Auto-provisioning allows FlexNet Operations to automatically create new license servers when new entitlements require it and, when a default license server is present, automatically maps new rights to the default license server.

For the first part of this exercise, you specify the following settings for the metered license model attributes:

Attribute	Value
Name	Example Metered License Model
Expiration	None
Is this an Embedded License Model?	Yes
Is this a Counted Model?	Yes
Is this a Metered Model?	Yes
Reusable	Yes
Undo Interval	Not Used
Overdraft	Unlimited
Auto Provision	Yes
Issuer	Not Used
Serial Number	Not Used
Vendor String	Not Used
Notice	Not Used



Task *To create a usage-based license model*

1. In the Producer Portal, click **Administer > License Models**. The Producer Portal opens the **License Models** page.
2. On the **License Models** page, click **Create New License Model**. This button opens the **Select a License Technology** page.
3. Select **FlexNet Licensing** and click **Next**. The Producer Portal opens the **Create a License Model** page.
4. Specify license model name and expiration setting. For this exercise, use the values specified in the table above: **Example Metered License Model** and **None**.
5. Click **Next**. The Producer Portal begins rendering interactive settings for license model policies.
6. Set the license model policy values described in the table above, and click **Save**.

The Producer Portal creates the license model with the settings you specified.

Creating an Unmetered License Model for Client Registration

If you are implementing a connected software client, the client registration process requires an additional unmetered license model. For this purpose, create a second license model, called **Example Baseline LM**, with **Metered** set to **No** and **Counted** set to **No**.

For the second part of this exercise, repeat the license model creation process but specify the following settings for the unmetered license model attributes:

Attribute	Value
Name	Example Baseline LM
Expiration	None
Is this an Embedded License Model?	Yes
Is this a Counted Model?	No
Is this a Metered Model?	No
Issuer	Not Used
Serial Number	Not Used
Vendor String	Not Used
Notice	Not Used

Retain the defaults for all other attributes.

Deploying the License Models

Before these new license models can be used in an entitlement, you must deploy them. (Deploying a license model changes its state from draft to deployed.)



Task To deploy Example Metered License Model and Example Baseline LM

1. In the Producer Portal, click **Administer > License Models**. The Producer Portal opens the **License Models** page.
2. On the **License Models** page, locate the **Example Metered License Model** and **Example Baseline LM** license models. If they do not immediately appear in the **License Models** list, try searching **License Models** for **Example**.
3. Select the check boxes for **Example Metered License Model** and **Example Baseline LM**, and then click **Change State > Deploy**.
4. Click **OK** to confirm the state-change operation.

The Producer Portal deploys the license models and refreshes the **License Models** page to show the new Deployed state.

Usage Management: Creating Features

In FlexNet Operations, usage data is tracked by *feature*. In this exercise you will create two features.

The FlexNet Embedded C SDK and FlexNet Embedded XT usage-capture examples track usage for a feature called **survey**. You will create that feature as our metered feature in this exercise. In addition, you will create another feature, called **baseline-client-reg**, to facilitate client registration.

- For instruction on creating the survey feature, see [Creating a Metered Feature](#).
- For instruction on creating the baseline-client-reg feature, see [Creating an Uncounted, Unmetered Feature for Client Registration](#).

For each feature, we will create a separate product and then combine those products in an entitlement to deliver to a user in a customer account.

Creating a Metered Feature

In the Producer Portal, use the commands under the **Products** menu to add a feature called **survey**, version **1.0**. When defining the feature, use the following settings:

Attribute	Value
Feature Name	survey
Feature Version	1.0
Description	Example feature for usage capture.
Units	Measurements
Scale	1

Attribute	Value
Counted	Do Not Override
Reusable	Do Not Override

Leave all other attribute settings on their default values.



Task

To create the survey feature

1. In the Producer Portal, click **Products > Features**. The Producer Portal opens the **Feature** page.
2. On the **Feature** page, click **Add New Feature**. This button opens the **Create a Feature** page.
3. On the **Create a Feature** page, set the feature attributes using the values in the table above.
4. Click **Save**.

The Producer Portal creates the survey feature and remains on the **Create a Feature** page.

In practice, a feature count of 1 should represent the smallest possible difference in values you intend to capture. If this choice would cause large numbers in usage reports, you can use the **Scale** setting to define a factor by which the values in the reports will be divided before they are displayed. For example, a realistic choice for file sizes is to have feature usage counted in bytes, set the scale to one billion, and set **Units** to **GB**.

Creating an Uncounted, Unmetered Feature for Client Registration

The client registration process requires an additional unmetered, uncounted feature. For this purpose, create a second feature called **baseline-client-reg**.

Repeat the feature creation process for the baseline feature. Use the settings shown in the table below.

Attribute	Value
Feature Name	baseline-client-reg
Feature Version	1.0
Description	Example unmetered feature to do client-registration for entitlements that deliver metered products.

Leave all other attribute settings on their default values.

Usage Management: Creating a Product Line

In the Producer Portal, use the commands under the **Products** menu to create a product line. No particular settings are required for usage capture. The following instructions create a product line called Example Product Line.



Task **To create the Example Product Line**

1. In the Producer Portal, click **Products > Product Lines**. The Producer Portal opens the **Product Lines** page.
2. On the **Product Lines** page, click **Add Product Line**. This button opens the **Create Product Line** page.
3. On the **Create Product Line** page, type the name of the product line: **Example Product Line**.
4. Click **Save**.

The Producer Portal saves Example Product Line. The product line is used as an attribute in the search criteria on the Usage Search page, when you want to view usage graphs or gauges for a particular product line.

Usage Management: Creating Products

Use commands under the **Products** menu to create two products:

- Example Survey for the metered feature for which you intend to capture usage (survey)
- Example Baseline for the client registration feature (baseline-client-reg)

Creating the Example Survey Product

Follow the steps, below, to create the Example Survey product.

Attribute	Value
Product Name	Example Survey
Version	1.0
Licensing Technology	FlexNet Licensing
Can Be Used on a Device	Yes
Usage Models	Monthly Statements (Reset Monthly)
Feature	Survey,1.0
Feature Quantity	1
License Model	Example Metered License Model
Product Line	Example Product Line



Task **To create Example Survey**

1. In the Producer Portal, click **Products > Products**. The Producer Portal opens the **Products** page.
2. On the **Products** page, click **Add New Product**. This button opens the **Create a Product** page.

3. On the **Create a Product** page, set the **Product Name**, **Version**, **License Technology**, **Can Be Used on a Device**, and **Usage Model** as shown in the table above.



Note ▪ A usage model must be set for reconciliation to take place and to be able to view usage gauges and graphs. Also, be aware that usage models labeled as monthly statements refer to a rolling 30-day window and not a calendar month.



Important ▪ Products using the same feature must be configured with the same usage model per account. For an account, the usage model that is specified for a product containing a specific feature will be the usage model that is used for subsequent entitlements or products containing that specific feature.

Example:

- Product A (feature f1) and product B (features f1 and f2)
- Account C is first entitled to product A (feature f1) with usage model Monthly Statements (No Reset)
- Account C is then entitled to product B (features f1 and f2) with usage model Monthly Statements (Reset Monthly)
- Account C will use usage model Monthly Statements (No Reset) for both products A and B because they both contain feature f1 which was included in the first entitlement.

If Account C was first entitled to product B (features f1 and f2) with usage model Monthly Statements (Reset Monthly), this usage model would be used for both products/entitlements for the account.

4. Click **Add Features**. The Producer Portal opens the **Add Features to Product** page in a pop-up window.
 - a. Locate the feature, **survey, 1.0.**, and click **Add**. This selects the feature and moves it to the **Selected Features** list.
 - b. Click **Add**. The Producer Portal closes the **Add Features to Product** window.
5. On the **Create a Product** page, set the **Quantity** for the survey feature to **1**, and click **Next**. (For a counted feature, this is the feature count per copy of the product ordered.) The Producer Portal opens the **Link License Models to Product** page.
6. Click **Link License Models** to open the **Select License Models** page in a pop-up window.
 - a. Locate the license model, **Example Metered License Model**, and click **Add**. This selects the license model and moves it to the **Selected License Models** list.
 - b. Click **Add**. The Producer Portal closes the **Select License Models** window.
7. Click **Next** until you see the **Map Product to Product Line** page. (Depending on your Producer Portal configuration, you will pass a few pages—such as **Map Part Numbers to Products** and **Relate to Different Products**—without making any changes.)
8. On the **Map Product to Product Line** page, do either of the following to specify the product line **Example Product Line**:
 - In the **Product Line** field, type **Example Product Line**.
 - Click the search icon next to the **Product Line** box. The Producer Portal opens the **Select Product Line for Product** page in a pop-up window. Search for and select product line **Example Product Line**, then click **OK**. The Producer Portal closes the **Select Product Line for Product** window.

9. Click **Save**.

The Producer Portal saves Example Survey and remains on the **Map Product to Product Line** page.

Creating the Example Baseline Product

Next, repeat the steps, creating a product for the uncounted baseline-client-reg feature and unmetered license model used in client registration. Use the following settings for the Example Baseline product.

Attribute	Value
Product Name	Example Baseline
Version	1.0
Licensing Technology	FlexNet Licensing
Can Be Used on a Device	Yes
Usage Models	None
Feature	baseline-client-reg,1.0
Feature Quantity	1
License Model	Example Baseline LM
Product Line	Example Product Line



Important - Before these new products can be used in an entitlement, you must deploy them. (Deploying a product changes its state, and the state of its features, from draft to deployed.) Select the check boxes for the Example Survey and Example Baseline products, click **Change State > Deploy**, and follow the on screen instructions to confirm the change.

Usage Management: Creating an Account and User

In the FlexNet Operations Producer Portal, use the commands under the **Accounts & Users** menu to create an account that represents a customer enterprise. For this example, create an account called **Demo Customer Org**.



Note - The customer account and end user created in these exercises are the same as those created in the exercises in the section *Getting Started with Electronic Software Delivery*. If the account and user already exist, you can skip the steps that create them, below.


If you already have a test end user in a customer account you can entitle to these products, you can opt use that user instead of creating the user described here.

Follow the instructions, below, to create the customer account (Demo Customer Org), the end user account (Demo Customer) and entitle it to the survey product.



Task *To create the customer account and end user*

1. In the Producer Portal, click **Accounts & Users > Create Account**. The Producer Portal opens the **Create an Account** page.
2. On the **Create an Account** page, type the following values for the **Account ID** and **Account Name** attributes.

Attribute	Value
Account ID	DemoCustOrg
Account Name	Demo Customer Org
	
	Important - Do not enter a colon (:) character in the Account Name field.

Keep the default values for all other attributes.

3. Click **Create a User**. The Producer Portal saves the Demo Customer Org account and opens the **Create a User** page to add a new user to it.
4. On the **Create a User** page, type the following values for the new user's Contact Details:

Attribute	Value
First Name	Demo
Last Name	Customer
Email Address	An email address you control. This email account is where FlexNet Operations will send the initial login credentials and entitlements.

Keep the default values for all other User Details and Contact Details attributes.

5. In **Accounts**, select the check box for **Portal User Role**. This gives Demo Customer the standard permissions for portal users.
6. Click **Save**.

The Producer Portal creates Demo Customer as a new user and sends a welcome message to the email address you provided. Use the credentials in that email to log in to the End User Portal and verify the Demo Customer account is functional.

Usage Management: Entitling the Account

Use the commands in the **Entitlements** menu to create an entitlement to the survey and baseline products for Demo Customer Org.

In this exercise, you will create a new entitlement, add Demo Customer Org as the end customer, configure a line item for the uncounted, unmetered product for client registration, Example Baseline, and configure another line item for the metered product, Example Survey.



Task *To create the entitlement ENTL-SURVEY001*

1. In the Producer Portal, click **Entitlements > Create**. The Producer Portal opens the **Create an Entitlement** page.
2. For **Entitlement ID**, select **Specify** and type ENTL-SURVEY001.
3. For End Customer and Channel Partners, click **Add**. The Producer Portal opens the **End Customer and Channel Partners** page in a pop-up window.
 - a. Click the radio button for **DemoCustOrg** to select the Demo Customer Org as the customer account to receive the entitlement.
 - b. Click **Next**. The Producer Portal shows the **End Customer and Channel Partners: Contacts** page in the pop-up window.
 - c. Click the radio button for **Demo Customer** to select Demo Customer as the end user who will receive the entitlement message.
 - d. Click **Save**.

The Producer Portal closes the pop-up window and shows Demo Customer Org and Demo Customer as the end customer.

4. Click **New Line Item** to begin configuring a line item for the Example Baseline product. The Producer Portal opens the **Configure Line Item** page in a pop-up window.




Figure 17-5: Starting the line item configuration process for the Example Baseline product.

- a. Locate and select the **Example Baseline** product, and then click **Next**.
- b. Select the license model, **Example Baseline LM**, and click **Next**.

- c. Specify the following settings for product configuration:
 - **Qty:** 1
 - **Start Date:** 01/01/2016
 - **Expiration:** 01/01/2020
 - d. Click **Next**.
 - e. Click **Save**.
5. Click **New Line Item** to begin configuring a line item for the Example Survey product. The Producer Portal opens the **Configure Line Item** page in a pop-up window.
- a. Locate and select the **Example Survey** product, and then click **Next**.
 - b. Select the license model, **Example Metered License Model**, and click **Next**.
 - c. Specify the following settings for product configuration:
 - **Qty:** 2000
 - **Start Date:** 01/01/2016
 - **Expiration:** 01/01/2020
 - d. Click **Next**.
 - e. Click **Save**.
6. Click **Save & Deploy**.

The Producer Portal saves ENTL-SURVEY001 with line items for Example Baseline and Example Survey.



Important - Notice, in the instructions above, that the entitlement line item for the Example Survey product stipulates dates for **Start Date** and **Expiration** settings. To track usage for a product, you must specify a date for the Start Date value when you create the entitlement. Start Date cannot be Specify at First Activation, Specify at Each Activation, Use First Activation Date, or Use Each Activation Date. Similarly, Expiration cannot be set to Specify Duration. Its value must be either Permanent or a specified date.

At this point, if you log in to the End-User Portal, as Demo Customer, you can see the survey entitlement listed on the End-User Portal's home page.

FlexNet Operations also generates the license server instance in the FlexNet Cloud Licensing Service and maps the Example Survey line item to the new server.



Tip - Make a note of the activation ID for Example Baseline. When you run a usage capture client, you will use the activation ID as the rights ID during the client registration process.

Usage Management: Viewing the Auto-Provisioned License Server

Once you deploy the entitlement, ENTL-SURVEY001, FlexNet Operations automatically generates the license server instance from which served clients in the end customer account acquire their license rights. In this exercise, you will locate the auto-provisioned license server in the Producer Portal.



Task **To view the auto-provisioned license server**

1. In the Producer Portal, click **Devices > Search License Servers**. The Producer Portal opens the **Search License Servers** page.
2. On the **Search License Servers** page, locate the new license server by its account name. For Account Name, type **DemoCustOrg** and then click **Search**. The Producer Portal opens the **Search Server Results** page.
3. On the **Search Server Results** page, click the license server ID for DemoCustOrg's license server. The Producer Portal opens the **View Server** page.

Notice that the **View Server** page shows a number of important attributes of the license server. In particular, make a note of the license server ID. The license server ID, in this case 3VH8MNZESMSP, is used in the endpoint URL for that license server, where the served clients connect to make capability requests. (See [Usage Management: Obtaining the License Server URL](#).)

Notice also, that the license server's **View Server** page also shows the product licenses that are served by it. In this case, the license server includes the Example Survey line item from the ENTL-SURVEY001 entitlement. (The Example Baseline line item is not served by the license server. Instead, it is present in the entitlement to support the registration of the license server's served clients.)



Tip ▪ When auto-provisioning is used, you can also find a customer account's default license server instance on customer account's **Create an Account** page. There, click the license server ID link, labeled **Cloud Licensing Service instance (Auto Provisioned)**, to open the **View Server** page.

Usage Management: Obtaining the License Server URL

The URL for the license server instance hosted in the FlexNet Cloud Licensing Service is the location where your FlexNet licensing client sends its usage capture data.



Tip ▪ This getting started section uses the FlexNet Operations User Acceptance Testing (UAT) site for demonstration purposes. Any URLs mentioned will need to be adjusted when used in Production.

For a connected software client using FlexNet licensing, such as the FlexNet Embedded C SDK or FlexNet Embedded XT, the URL is:

```
https://<siteID>-uat.compliance.flexnetoperations.com/instances/<CLS instance ID>/request
```

In the URL, above, <siteID> is the site ID for your account and <CLS instance ID> is the license server ID of the license server to which usage capture data is sent. For example, the <CLS instance ID> value based on the auto-provisioned license server instance created in the exercises in this section would be 3VH8MNZESMSP. For more information about the site ID, see [FlexNet Operations Environments](#).

The URL of the license server instance for 3VH8MNZESMSP, for a producer account with the site ID *example* might appear as:

```
https://example-uat.compliance.flexnetoperations.com/instances/3VH8MNZESMSP/request
```

Usage Management: Running a Usage-Capture Client Example

At this point, you can put the pieces together and run the usage-capture client example from the appropriate client toolkit.

If you are using FlexNet Embedded C SDK or FlexNet Embedded XT to implement a connected software application or device, the example is called *usage capture client*. In these implementations, you will use the example to first send a capability request that specifies the activation ID as a rights ID, to register the client, and then send capability requests containing desired features that describe the usage being captured.

See your licensing user guide for implementation and usage details for the examples.

Usage Management: Viewing Usage Information

You can view usage information in the Producer Portal. Recall that your product must have a usage model set for usage information to be shown in the usage graphs and gauges, as described in [Usage Management: Creating Products](#).

Under the **Usage** menu, select **Usage Search**. In the **Usage Search** screen, enter the name of your metered feature—**survey**—in the **Meter Name** field and then click **Search**. Click the desired account from the list of results to see usage reports for that account. For these exercises, choose the customer account you created earlier: **DemoCustOrg**.

The captured usage information is then rendered on the **Usage Search** page. By default, the usage information is displayed as a gauge showing the percentage of the usage count compared to the entitled count. The label for the gauge shows the text you entered for the feature description, if any. The value you entered for Units on the **Create a Feature** page—in this case, **Measurements**—appears as the label for the usage count. In practice, this might be Downloads or Gigabytes or whatever usage you are tracking.

Usage Search

View Usage For Account: DemoCustOrg

The gauges below show the percentage of entitled amount used for the statement period which includes the selected date. Selecting a new date will show percentages for meters within the statement period surrounding the new date. Click the download link on a meter to see that meter's usage events for the selected statement period.




Figure 17-6: Example usage gauge for the survey feature

In the **View Usage** page, you can view the captured usage information as different types of graphs, or download the usage information for analysis. With the graph buttons, you can display usage information as a gauge, a textual table of usage information, a graphical timeline, or a graphical timeline comparing multiple metrics.



Note - Unless you have a client that is already reporting usage data, expect the usage reports to show 0 usage.

Similarly, a user in the enterprise customer account can view current usage information by logging in to the End-User Portal and viewing usage reports.

Usage Management: Next Steps

This section demonstrates a simple scenario for verifying that your toolkit is working properly. See the following section for further information about more advanced FlexNet Usage Management tasks, like manually created license servers, uploading usage history data, and downloading reconciliation summaries.

Advanced FlexNet Usage Management Activities

The following are some more advanced activities for producers who use FlexNet Operations with FlexNet Usage Management.

Topic	Description
Manually Creating a License Server	Shows how to manually create a new license server instance in the FlexNet Cloud Licensing Service and then map the entitlement line item for the metered product to it.
Uploading Historical Usage	Very briefly discusses the option to directly upload usage data for testing or demonstrations.
Reconciliation Summaries	Explains how to programmatically pull usage and overage data from the FlexNet Operations back office.
Obtaining Raw Usage Data	Provides an overview on how to use the Usage Data Extract job on the Producer Portal and the data extract RESTful services to retrieve raw usage data from FlexNet Operations.
Usage Data via SOAP	Introduces the getUsage web service as a method of retrieving real-time, reconciled usage data for an account.

Manually Creating a License Server

An enterprise customer's usage data is sent to a license server. In some cases, such as for a large enterprise customer, it may be desirable to provide multiple license servers hosted in the Cloud Licensing Service. This exercise shows how to use the Producer Portal to manually create a single license server deployed via FlexNet Cloud Licensing Service, to receive usage data for the Example Survey product.



Note - The exercises in the previous section, [FlexNet Usage Management Exercises](#), show the license server created automatically with auto-provisioning. With auto-provisioning off, a producer must manually create the license server instance and then map any entitlements to it.

From the **Devices** menu, click **Create License Server**. Use the following settings to create a server.

Attribute	Value
Deployment	Cloud Licensing Service
Identity	fne-demo
Site Name	Demo Customer Org's Hosted Server 1

Attribute	Value
Owner ID	Demo Customer Org

Retain the default settings for all other attributes.

Figure 17-7: Creating a license server instance to be hosted in the FlexNet Cloud Licensing Service

The **View Server** page displays the server’s license server ID. The license server ID, in this case RD1KPTL6NJ21, is also the instance ID value for the server. This instance ID value is used in the URL where usage information is sent for this enterprise customer.

While still in the **View Server** page, click **Action** and then click **Map Entitlements**. Use the Map Entitlements page to associate a quantity of line items to the server. From the list of entitlements, type quantities in the Qty to Add column. Type **1000** for Example Survey and click **Save**.



Note ▪ The metered Example Survey product is the one that is used on this license server. The unmetered Example Baseline is for registering devices that report usage data.

Map Entitlements

View Edit Action

Server Details

Server ID RD1KPTL6NJ21
Alias

Entitlements Available

Product	Activation Code	License Model	Expiration	Available Units in Line Item	Total Units in Line Item	Qty to Add
Example Survey Ver 1.0, Qty/Copy 1 An example metered-uncounted product created as part of the exercises in the Getting Started Guide for FlexNet Usage Management.	e691-c06f-0b6c-4d14-8b2e-0446-f810-f9b3	Example Metered License Model	Jan 1, 2020	2000	2000	1000

Figure 17-8: Mapping a product to a license server

After the product is mapped, usage-capture code can send capability requests to this license server instance.

Uploading Historical Usage

When testing or demonstrating FlexNet Operations usage reporting functionality, it may be useful to quickly upload some test usage data rather than waiting for your usage-capture clients to report actual usage data. This operation is supported via the Upload Historical Usage command in the FlexNet Operations Producer Portal. For more information, consult the section [Managing Usage](#).

Reconciliation Summaries

In addition to viewing gauges in the Producer Portal, FlexNet Usage Management provides a way to download simple usage reports that can be uploaded to a billing system. A *reconciliation summary* is a file containing records of usage and overage data for a given account ID, product name, and feature name, for the desired billing period.

While logged in to the Producer Portal, you can download a reconciliation summary file by opening this URL, where <siteID> is your account's site ID and *yyyy-mm-dd* is the billing period end date (for information about the site ID, see [FlexNet Operations Environments](#)):

```
https://<siteID>-fno.flexnetoperations.com/flexnet/service/ReconSummary?StmtCloseDate=yyyy-mm-dd
```

For a UAT environment, include `-uat` in the URL:

```
https://<siteID>-fno-uat.flexnetoperations.com/flexnet/service/ReconSummary?StmtCloseDate=yyyy-mm-dd
```

If you are not logged in, the URL must include username and password values in the query string.

Instead of using a browser, you can automate download of the reconciliation summary data with a utility such as `cURL`, using a command similar to the following:

```
curl --url 'https://<siteID>-fno.flexnetoperations.com/flexnet/service/ReconSummary?username=user@domain.com&password=pwd&StmtCloseDate=yyyy-mm-dd'
```

The reconciliation summary file is a comma-separated text file (CSV file) containing the summary usage data for the specified billing period. The file contains a header row followed by records of usage data.

```
enterpriseName, accountID, productName, productID, featureName, friendlyName, startDate,
  endDate, usageUnitName, usageFromStatement, entitled, overageFromReset, overageFromStatement
"DEMO1", "DEMO1", "Storage", "55555", "Connections", "Number of Connections", 2014-07-01,
  2014-08-01, , 0, 5000, 0, 0
"DEMO1", "DEMO1", "Storage", "55555", "Storage", "Storage (GB)", 2014-07-01, 2014-08-01, , 0, 2000, 0, 0
```

You can then transform the data into the required format before uploading it to your billing system for processing.

Obtaining Raw Usage Data

Producers who schedule the Usage Data Extract job can download raw usage data from the results of that job via a RESTful service. The Usage Data Extract job generates an extract of all usage events from the end time of the last successful run to the current time.

See the [Administering Alerts](#) section for instructions on how to schedule the Usage Data Extract job.

See the Data Extract RESTful Services section of the *FlexNet Operations Web Services Integration Guide* for instructions on how to query the results of the Usage Data Extract job.

Usage Data via SOAP

FlexNet Operations includes a `getUsage` web service. `getUsage` is a SOAP-based web service that retrieves real-time, reconciled usage data for an account. It allows producers to programmatically gather the same data used in the Producer Portal to render usage in the usage gauges, tables, and timelines.

`getUsage` returns the end-user's product line, meter, unit of measure, actual usage, entitled quantity, overage since statement, overage since reset, percentage, interval/reset, and time period.

For more information, see the *FlexNet Operations SOAP Web Services Guide*.

Getting Started with Updates and Insights

This *Getting Started with Updates and Insights* section presents fundamental updates and insights concepts and uses exercises to lead a Producer Portal user through automated update management tasks. The intended audience for this getting started section is the first-time Producer Portal user, or one without FlexNet Operations training or experience.



Version ▪ *Updates and Insights features are only available for producers who purchase the Software Delivery module.*

Table 18-1 ▪ Getting Started with Updates and Insights

Section	Description
The License Lifecycle: Updates and Insights	Overview of the FlexNet Operations license lifecycle.
About Updates and Insights	A discussion of basic FlexNet Operations updates and insights concepts. This section introduces FlexNet Operations Updates and Insights module features and provides a process overview for creating and delivering an update.
Requesting Update Information	Describes how devices can obtain information about updates.
Logging Device Events	Explains how to log device events with the Notification Server to gain insights about the process or outcome of an upgrade.
Authorizing Update Requests	Only authorized devices are allowed to access the REST APIs. This section explains how to authorize devices to make update requests.
Securing Update Responses	Explains how to use the Notification Server to provide update responses.

Table 18-1 • Getting Started with Updates and Insights

Section	Description
Updates and Insights Exercises	A series of exercises that demonstrate how to create an update package. The end of this section also provides brief descriptions of more advanced topics and explains where to find more information about them.

The License Lifecycle: Updates and Insights

The FlexNet Operations license lifecycle is a repeating process of producer and customer activities, as depicted in the figure and described below.



Figure 18-1: FlexNet Operations License Lifecycle

- **Create Products**—Create product definitions that are used to generate licenses.
- **Order/Entitle**—Define an account's rights to obtain licenses for your products.
- **Deliver/Install**—Deliver the application software to the customer and install that software.
- **Activate**—Deliver licenses to the customer.
- **Return/Rehost**—Manage license transfers from one user or system to another.
- **Maintain/Update**—Deliver software updates to the customer.

- **Upsell/Renew**—Renew customer licenses, or sell the customer additional product functionality.

About Updates and Insights

This section introduces updates and insights concepts.

Topic	Description
The Updates and Insights Module	Overview of the Updates and Insights module
Prerequisites for Automated Updates	Describes the process for creating an update
Update Key Concepts	Describes the basic components of an update
Notification Server	Describes the Notification Server which receives update requests from devices and communicates with FlexNet Operations.
Anonymous Devices	Explains what anonymous devices are, and how using Updates and Insights features for anonymous devices differ from devices assigned to an account.

The Updates and Insights Module

The Updates and Insights module provides a single delivery and update experience for software and devices within FlexNet Operations. It provides an integrated solution for entitlement, account, and update management to give producers visibility and control to manage product releases for their customer accounts.

With this module, producers can provide:

- security patches to keep devices up to date and reduce security risk,
- in-product updates to applications (2018 R2 and later versions),
- entitlement-driven updates to help prevent revenue loss by ensuring only those with valid entitlements get updates. (Entitlement checks can be disabled to deliver vital security patches.)

This module uses the FlexNet Operations mechanism for hosting and delivering updates, or can leverage a producer's existing hosting infrastructure investment.

Updates can be delivered to all types of devices—standalone devices (including anonymous devices), served devices, and servers. However, the way updates are delivered differ for anonymous devices. For more information, see [Anonymous Devices](#).

End users can keep up to date with automated security patches without having to download them manually from a portal, reducing security exposure. They will have access to updates on a per-platform basis, including custom platforms defined by the producer.

In addition to providing updates, the Updates and Insights module also enables devices to log events in the Notification Server. Events provide insights into the process or outcome of an upgrade, or how the software is being used. They can be of particular interest to product managers in understanding how software is being used and whether new features are being adopted. For more information, see [Logging Device Events](#).

The Updates and Insights module does not support the distribution of containerized applications.

Prerequisites for Automated Updates

The following steps must be performed before updates can be delivered:

- [Prepare Download Packages](#)
- [Register Devices](#)

Prepare Download Packages

For a device to poll for, and receive, automated updates it must use the provided REST APIs.

Before creating an update, the producer must do at least one of the following:

- Configure an existing download package and files (files can be stored in FlexNet Operations or can be loaded from an external delivery source),
- Associate a download package to a product (for entitlement-driven updates),
- Configure a new download package to be used as the delivered content.

The next step is for the producer to define an update in FlexNet Operations.

Download packages and updates can be created through the FlexNet Operations Producer Portal, through a data import file, or using REST APIs. (Download packages can also be created using SOAP Web Services.)

Register Devices

Standalone devices (including anonymous devices) and servers should be registered before they attempt to obtain update information. This enables the producer to track the device and any updates that are associated with it. A device can:

- Be registered through the FlexNet Operations Producer Portal.
- Standalone devices (including anonymous devices) only: Use the activation ID of a line item to register itself and request an update through a notification command. (For more details see either the *FlexNet Embedded Client C XT SDK User Guide* or the *FlexNet Embedded Client .NET XT SDK User Guide*.)
- Standalone devices (including anonymous devices) only: Register itself using the `/registrations` REST API in the Notification Server. Devices which are not associated with an account—called "anonymous devices"—should use this method of registration. This avoids a manual step of registering using the Producer Portal and ensures the device is known about in FlexNet Operations when verifying successful software updates.

Served devices can not be registered with FlexNet Operations.

Update Key Concepts

An update consists of four components:

Table 18-2 • Update Components

Component	Description
Overview	Status, name, ID, availability, and description. If the Entitlement check is selected, the update components will be used to verify whether a device requesting an update is authorized to receive it.
Release From	Defines the existing download package, installed on the device, that the update is intended for. More than one download package can be defined for a single update. When the Entitlement check is selected, the download package ID in the device's request for updates must match the download package specified in the update, otherwise no updates will be delivered.
Release To	Defines the download package that will be sent in the update. Only one package per platform is allowed. To define an update for multiple platforms, a separate entry must be made for each platform. When the Entitlement check is selected, the platform in the device's request for updates must match the platform specified in the update, otherwise no updates will be delivered.
Languages	The language or languages of the update. When the Entitlement check is selected, the language in the notification request must match the language in the device's request for updates, otherwise no updates will be delivered.

Anonymous devices will only receive updates when the Entitlement check is set to **None**. Served devices will only receive updates when the Entitlement check is set to **Account** or **None**.

Notification Server

The Notification Server is the service within FlexNet Operations that handles update requests from authorized devices. The Notification Server communicates with the other FlexNet Operations back offices services to retrieve and deliver update information to the requesting device.

Notification Server Base URL

The REST API paths for the Notification Server that are described in this section must be prefixed with the following base URL:

```
https://<siteID>-ns-uat.flexnetoperations.com/
```

where <siteID> is your organization's specific site ID supplied by Revenera. For more information about the site ID, see [FlexNet Operations Environments](#).

Note that the URL above points to a User Acceptance Test (UAT) environment indicated by the -uat part following the <siteID>. For production environments, the -uat is omitted.

Anonymous Devices

Devices must be registered in FlexNet Operations in order to view information about update activity. When registering the device, assigning it to an account is an optional step. For some devices, particularly those sold to a single end user, or those running software that is not licensed, assigning to an account is not necessary or possible. Devices not assigned to an account are known as "anonymous devices".

It is possible to use Updates and Insights features for anonymous devices. However, the way such devices use the registration and update APIs, and are subject to entitlement checks, differs from devices assigned to an account.

- When registering the device using the /registrations REST API, an activationID will not be available, and so should be left blank.
- When requesting updates, the fields id and idType (which identify the device) and the field publisherName should be left blank.
- Only updates with entitlement check set to **None** are returned to such devices.

The rest of this documentation includes further information about how to carry out registration and updates for anonymous devices.

Requesting Update Information

It is recommended that devices are registered in FlexNet Operations before making update requests. For more information, see [Register Devices](#).

Communication to the Notification Server is only supported via REST.

This section describes the following:

- [Flow of Requests](#)
- [REST APIs for Requesting Update Information](#)

Flow of Requests

This section describes the workflow where devices are communicating directly with the Notification Server.



Important - REST API access must be restricted to authorized devices. For more information, see [Authorizing Update Requests](#).

Once an update has been added to FlexNet Operations it is available for download to a device. The workflow for handling an update is as follows:




Figure 18-2: Flow of Update Requests in FlexNet Operations, Steps 1 - 6

The steps for obtaining update information are:

1. A device sends an initial request for updates to the Notification Server (see [/uai/2.0/updates](#) or [/uai/2.0/signed-updates](#)).
2. The device receives back a polling ID.
3. The device uses the polling ID periodically to request the updates until they are available (using [/uai/2.0/updates/{pollingId}](#) or [/uai/2.0/signed-updates/{pollingId}](#)).
4. The Notification Server, when it receives the first request for updates, logs the request with the FlexNet Operations back-office.
5. The Notification Server retrieves the information about updates that are possible from the package currently installed on the device.
6. The Notification Server then returns the update information in response to the latest poll from the device. This may include several updates possible from the package currently installed on the device. (Anonymous devices will only receive updates when the Entitlement check is set to **None**. Served devices will only receive updates when the Entitlement check is set to **Account** or **None**.)

At this point, the device must decide which update, if any, to proceed with. If one is chosen, the following happens:




Figure 18-3: Flow of Update Requests in FlexNet Operations, Steps 7 - 12

7. The device requests the manifest using the ID in the update (using [/uai/2.0/updates/manifests](#) or [/uai/2.0/signed-updates/manifests](#)). (A manifest is a list of files needed to perform the update.)

8. The device receives back a polling ID.
9. The device uses the polling ID periodically to request the manifest until it is available (using [/uai/2.0/updates/manifests/{pollingId}](#) or [/uai/2.0/signed-updates/manifests/{pollingId}](#)).
10. The Notification Server requests the manifest from the FlexNet Operations back-office.
11. The Notification Server retrieves the manifest from the FlexNet Operations back-office database.
12. The Notification Server then returns the manifest in response to the latest poll from the device.

Finally, the device requests each file listed in the manifest using the supplied URLs, also contained in the manifest. The device should use a checksum provided by the original update response to verify the authenticity of each file retrieved. The files can then be used to perform the update.

REST APIs for Requesting Update Information

The APIs described in this section are used by devices to obtain information about updates, so that they can complete the steps described in section [Flow of Requests](#). In addition to the APIs used to obtain the list of available updates and their related manifests, devices can:

1. Register with FlexNet Operations so that devices assigned to an account can establish their entitlement to updates, and all device update statuses can be displayed in FlexNet Operations on the Devices page.

This API is asynchronous, so that the registration must start with a POST to [/uai/2.0/devices/registrations](#), and then be followed by a series of GET calls to [/uai/2.0/devices/registrations/{pollingId}](#) until a 200 response indicates that the registration has completed successfully.



Note - Only standalone devices (including anonymous devices) can use the `/registrations` API. Servers should be registered through the FlexNet Operations Producer Portal. Served devices can not be registered.

2. Make status log updates, which record their progress through the update process. These status log updates can be viewed through the FlexNet Operations device pages.

Again, this API is asynchronous, requiring an initial POST followed by a series of GET calls, indicating that the status has been applied successfully.

The REST APIs mentioned in the following sections must be prefixed with a base URL, as described in [Notification Server Base URL](#).

Device Registration

It is recommended that standalone devices (including anonymous devices) register themselves using the `/registrations` API, to avoid a manual step of registering using the FlexNet Operations Producer Portal. Servers can only be registered through the FlexNet Operations Producer Portal. Served devices can not be registered.


Instructions for registering a device are described in the following sections:

- [Register a Device](#)
- [Poll for Device Registration Status](#)

Register a Device

Register the standalone device with FlexNet Operations to enable it to receive information about updates which have entitlement checking enabled.

Table 18-3 - Register a Device

Item	Description
URI	/uai/2.0/devices/registrations
Method	POST
Query parameters	registerRequest
Request body	<pre>{ "activationId": "string", "id": "string", "idType": "string", "identityName": "string", "publisherName": "string" }</pre>  <p>Note - For devices that are assigned to an account, it is recommended to provide the activation ID. For anonymous devices, the field <code>activationId</code> should be left blank.</p>
Response codes	<p>200: Not used</p> <p>202: Asynchronous request. Use the URL returned to poll for a response. The response will indicate whether the request succeeded.</p>

Sample Response

If the request has been accepted (status 202), a URL including a polling ID to poll for completion of the registration is returned:

```
{
  "url": "string"
}
```

Poll for Device Registration Status

Poll for a response to the registration status request, using the polling ID returned by a POST to the [/uai/2.0/devices/registrations](#) API. It can be used repeatedly until a 200 response is received.

Table 18-4 - Poll for Device Registration Status

Item	Description
URI	/uai/2.0/devices/registrations/{pollingId}

Table 18-4 • Poll for Device Registration Status

Item	Description
Method	GET
Query parameters	pollingId
Request body	N/A
Response codes	200: Processing complete. 202: Submitted request is still being processed. Use the URL returned to continue to poll for the response. 401: The request is unauthorized. This could be because a JWT was not found in the header, the token has expired, the signature is invalid, or a public key could not be identified (most commonly because the public key has not been uploaded to FlexNet Operations).

Sample Response

This is the data structure for a response when processing the device registration is complete (status 200):

```
{  
  "arguments": "string",  
  "key": "string",  
  "message": "string"  
}
```

If the request is still being processed (status 202), a URL to poll for completion of the status request is returned:

```
{  
  "url": "string"  
}
```

Status Log

Instructions for logging status updates are described in the following sections:

- [Log the Status of the Update Process](#)
- [Poll for Completion of Status Change](#)

The /statusLog API can be used for any device type.

Log the Status of the Update Process

Use the deviceClass parameter to indicate the type of device for which status log updates are requested. The following values are available:

- **client**—indicates a standalone device (this can also be an anonymous device)
- **server**—indicates either a Cloud License Server or a Local License Server

- **served**—indicates a served device.

If deviceClass is not specified, client is the default value.

Table 18-5 ▪ Log the Status of the Update Process

Item	Description
URI	/uai/2.0/updates/statusLog
Method	POST
Query parameters	statusLogRequest
Request body	<pre>{ "deviceClass": "string", "id": "string", "idType": "string", "language": 0, "packageId": "string", "platform": "string", "publisherName": "string", "statusCode": 0, "statusReason": "string", "timeStamp": "string", "updateId": "string", "updateName": "string" }</pre>
Response codes	<p>200: Not used</p> <p>202: Asynchronous request. Use the URL returned to poll for a response. The response will indicate whether the request succeeded.</p>

Sample Response

If the request has been accepted (status 202), a URL including a polling ID to poll for completion of the update process is returned:

```
{
  "url": "string"
}
```

Poll for Completion of Status Change

Indicate the success or failure to log the status of an update's progress.

Table 18-6 ▪ Poll for Completion of Status Change

Item	Description
URI	/uai/2.0/updates/statusLog/{pollingId}

Table 18-6 • Poll for Completion of Status Change

Item	Description
Method	GET
Query parameters	pollingId
Request body	N/A
Response codes	200: Processing complete. 202: Submitted request is still being processed. Use the URL returned to continue to poll for the response. 401: The request is unauthorized. This could be because a JWT was not found in the header, the token has expired, the signature is invalid, or a public key could not be identified (most commonly because the public key has not been uploaded to FlexNet Operations).

Sample Response

This is the data structure indicating the success or failure to log the status of an update's progress (status 200):

```
{  
  "arguments": "string",  
  "key": "string",  
  "message": "string"  
}
```

If the request is still being processed (status 202), a URL to poll for completion of the status change is returned:

```
{  
  "url": "string"  
}
```

Updates

The sequence of calls for an update is described in the following sections:

- [Find Available Updates](#)
- [Poll for Response to the Request for Updates](#)
- [Request Manifest File](#)
- [Poll for Response to the Request for Manifest File](#)

Find Available Updates


Find all updates available to a device given its identification and the version currently being run.

Use the `deviceClass` parameter to indicate the type of device for which updates are requested. The following values are available:

- **client**—indicates a standalone device (this can also be an anonymous device)
- **server**—indicates either a Cloud License Server or a Local License Server
- **served**—indicates a served device.

If deviceClass is not specified, client is the default value.

Table 18-7 • Find Available Updates

Item	Description
URI	/uai/2.0/updates
Method	POST
Query parameters	updatesRequest
Request body	<pre>{ "deviceClass": "string", "id": "string", "idType": "string", "language": 0, "platform": "string", "publisherName": "string", "updateFromPkgId": "string" }</pre>  <p>Note • For devices that are assigned to an account, it is recommended to populate the fields id, idType, and publisherName. For anonymous devices, these fields should be left blank.</p>
Response codes	<p>200: Not used</p> <p>202: Asynchronous request. Use the URL returned to poll for a response. The response will indicate whether the request succeeded.</p>

Sample Response

If the request has been accepted (status 202), a URL including a polling ID to poll for completion of the search is returned:

```
{
  "url": "string"
}
```

Poll for Response to the Request for Updates

Poll for a response to the request for updates, using the polling ID returned by a POST to the [/uai/2.0/updates](#) API. It can be used repeatedly until a 200 response is received.

Table 18-8 - Poll for Response to the Request for Updates

Item	Description
URI	/uai/2.0/updates/{pollingId}
Method	GET
Query parameters	pollingId: ID returned in Find Available Updates service
Request body	N/A
Response codes	200: Processing complete. 202: Submitted request is still being processed. Use the URL returned to continue to poll for the response. 401: The request is unauthorized. This could be because a JWT was not found in the header, the token has expired, the signature is invalid, or a public key could not be identified (most commonly because the public key has not been uploaded to FlexNet Operations).

Sample Response

This is the data structure for a response (status 200) to the request for available updates. In case of an error, the structure will be populated with relevant error details:

```
{
  "error": {
    "arguments": "string",
    "key": "string",
    "message": "string"
  },
  "updateItems": [
    {
      "commandLine": "string",
      "description": "string",
      "expireDate": "string",
      "fromPackageId": "string",
      "languageCode": 0,
      "manifestURL": "string",
      "productName": "string",
      "startDate": "string",
      "title": "string",
      "toPackageId": "string",
      "updateId": "string",
      "updateName": "string"
    }
  ]
}
```

If the request is still being processed (status 202), a URL to poll for completion of the request is returned:

```
{
  "url": "string"
}
```

Request Manifest File

Request the manifest file which contains details of all files required to achieve the update.

Table 18-9 • Request Manifest File

Item	Description
URI	/uai/2.0/updates/manifests
Method	POST
Query parameters	manifestRequest
Request body	{ "uuid": "string" }
Response codes	200: Not used 202: Submitted request is still being processed. Use the URL returned to continue to poll for the response.

Sample Response

If the request has been accepted (status 202), a URL including a polling ID to poll for completion of the request is returned:

```
{
  "url": "string"
}
```

Poll for Response to the Request for Manifest File

Poll for a response to the request for the manifest file, using the polling ID returned by a POST to the [/uai/2.0/updates/manifests](#) API. It can be used repeatedly until a 200 response is received.

Table 18-10 • Poll for Response to the Request for Manifest File

Item	Description
URI	/uai/2.0/updates/manifests/{pollingId}
Method	GET
Query parameters	pollingId: The ID returned in Find Available Updates service.

Table 18-10 • Poll for Response to the Request for Manifest File

Item	Description
Request body	N/A
Response codes	<p>200: Success</p> <p>202: Submitted request is still being processed. Use the URL returned to continue to poll for the response.</p> <p>401: The request is unauthorized. This could be because a JWT was not found in the header, the token has expired, the signature is invalid, or a public key could not be identified (most commonly because the public key has not been uploaded to FlexNet Operations).</p> <p>410: A response for the polling ID could not be found. This could be a result of using an incorrect polling ID, or of too much time having elapsed, so that the polling ID is no longer valid.</p>

Sample Response

This is the data structure for a successful response (status 200) to the request for the manifest file:

```
{
  "manifestFiles": [
    {
      "execute": "string",
      "fileSize": "string",
      "fileUrl": "string",
      "md5Hash": "string",
      "sha256Hash": "string"
    }
  ],
  "manifestVersion": "string"
}
```

If the request is still being processed (status 202), a URL to poll for completion of the request is returned:

```
{
  "url": "string"
}
```

If a response for the polling ID could not be found (status 410), the response body will describe the error, as shown in the following example:

```
{
  "arguments": "string",
  "key": "string",
  "message": "string"
}
```

Logging Device Events

The Updates and Insights module provides the ability for devices to log events in the Notification Server. Events are ways for devices to provide early and frequent feedback from the software installed on the device. They can be of particular interest to Product Managers in understanding, for example:

- How software is being used
- Whether new features are being adopted
- Whether certain activities (for example, a post-install test) have been completed
- Precise difficulties an update might have experienced
- Detailed information about the device's overall status

Devices log events with the Notification Server after the software has been installed or upgraded on the device.

Only registered devices should log events. For more information about registering a device see [Prerequisites for Automated Updates](#).

What Is an Event?

An event consists of an **event name** and optionally the following elements:

- an **event group**, to be able to categorize and search for events across a range of devices
- an **event value**, to add extra contextual information to the event.

One example of an event might be:

```
event name: "postUpgradeTest"  
event group: "upgrades"  
event value: "passed"
```

The steps for logging an event are described in the following section.

Logging a Device Event

Before performing the following steps, ensure that the device is registered with FlexNet Operations. For detailed information about the /events API, see [Events REST API](#).



Task **To log a device event**

1. Send a POST request to the /events Notification Server end point with the appropriate payload.
2. Use the polling ID returned by the POST request to GET the response to the /events call, until a 200 response is received.



Note - This step is optional. The polling should not take place too frequently; once per 10 seconds is adequate. The polling ID will become invalid after 5 minutes.

Events REST API

The /events API logs information about events that happen during an update and while the device is running the product at any time after the update.

This section describes the following:

- [Log the Event of the Update Process](#)
- [Poll for Response to the Request for Event Logging](#)

Log the Event of the Update Process

Event logging makes particular use of the following main fields:

- **eventName**—This can be any string you choose to use. This field enables you to define a number of events that you might want to monitor while the device is running your software. This field is required.
- **eventGroup**—This field enables you to group a number of eventNames into categories, for easier analysis at a later time. This field is optional.
- **eventValue**—This field provides additional information, for example to explain why a particular event has been logged. This field is optional.

Use the deviceClass parameter to indicate the type of device for which events should be logged. The following values are available:


- **client**—indicates a standalone device (this can also be an anonymous device)
- **server**—indicates either a Cloud License Server or a Local License Server
- **served**—indicates a served device.

If deviceClass is not specified, client is the default value.

Table 18-11 • Logging device events

Item	Description
URI	/uai/2.0/events
Method	POST
Query parameters	eventRequest

Table 18-11 • Logging device events

Item	Description
Request body	<pre>{ "deviceClass": "string", "downloadPackageId": "string", "eventGroup": "string", "eventName": "string", "eventValue": "string", "id": "string", "idType": "string", "language": 0, "platform": "string", "publisherName": "string", "timestamp": "string", "updateId": "string", "updateName": "string" }</pre> <p></p> <p>Note • The fields <code>downloadPackageId</code>, <code>eventGroup</code>, <code>eventValue</code>, <code>language</code>, <code>platform</code>, <code>updateId</code>, and <code>updateName</code> are optional.</p>
Response codes	<p>200: Not used</p> <p>202: Asynchronous request. Use the URL returned to poll for a response.</p>

Sample Response

If the request has been accepted (status 202), a URL including a polling ID to poll for completion of the registration is returned:

```
{
  "url": "string"
}
```

Poll for Response to the Request for Event Logging

Indicate the success or failure to log the event.

Table 18-12 • Poll for response to the request for event logging

Item	Description
URI	<code>/uai/2.0/events/{pollingId}</code>
Method	GET
Query parameters	<code>pollingId</code> : ID returned by <code>/uai/2.0/events</code> API (see Log the Event of the Update Process)

Table 18-12 • Poll for response to the request for event logging

Item	Description
Request body	N/A
Response codes	200: Success. 402: Asynchronous request. Use the URL returned to poll for a response. 401: The request is unauthorized. This could be because a JWT was not found in the header, the token has expired, the signature is invalid, or a public key could not be identified (most commonly because the public key has not been uploaded to FlexNet Operations).

Sample Response

This is the data structure indicating the success (status 200) or failure (status 401) to log the event for an update.

```
{  
  "arguments": "string"  
  "key": "string"  
  "message": "string"  
}
```

If the request is still being processed (status 202), a URL to poll for completion of the request is returned:

```
{  
  "url": "string"  
}
```

Viewing Logged Events

The manage-device-service-rest-controller API includes the REST API /devices/events. The /devices/events API returns all events logged by devices using the Updates and Insights feature in a list ordered by the date of the event. The list includes standalone, server, and served devices. It is paged, with 100 events per page. A specific page of results can be requested by setting the query parameter "page-number" in the URL.

Table 18-13 • Retrieving logged events

Item	Description
URI	/operations/manageDevice/2.0/devices/events
Method	GET
Query parameters	page-number: Request a specific page of results.
Request body	N/A

Table 18-13 • Retrieving logged events

Item	Description
Response codes	<p>200: Success.</p> <p>401: Returned if the Updates and Insights module is not licensed, or the user calling the API does not have permission to manage updates.</p> <p>405: Returned if the /devices/events/ API is not supported.</p> <p>500: The request failed due to an internal error. More details can be found in the error message.</p>

Sample Response

In case of a successful response (status 200), an ordered list of device events is returned:

```
{
  "creationDate": "string",
  "deviceClass": "string",
  "downloadPackageId": "string",
  "eventGroup": "string",
  "eventName": "string",
  "eventValue": "string",
  "id": "string",
  "idType": "string",
  "language": 0,
  "platform": "string",
  "publisherName": "string",
  "timestamp": "string",
  "updateId": "string",
  "updateName": "string"
}
```



Note - The fields `downloadPackageId`, `eventGroup`, `eventValue`, `language`, `platform`, `updateId`, and `updateName` are optional and can be empty.

Authorizing Update Requests

A producer must restrict REST API access to authorized devices. Updates and Insights makes this authorization possible by means of a JSON Web Token (JWT) in the headers of requests, which authenticates (and hence authorizes) the device. The producer must create the JWT and sign it using the private key of a public/private key pair, created using the RS256 algorithm. The JWT must also include an expiration date, in seconds since 1970-01-01 (the purpose of the expiration date is to provide a way for the token to expire, so that it will not be possible for a device to be perpetually authorized).

This JWT must be made available to the device software, so that it can be added to the REST API request using the `Authorization: Bearer` header. The token must be added to every POST request to the Notification Server (but is not required in any GET request used to poll for completion of these requests.)

The Notification Server will check the token in the following ways:

- Validate the signature in the JWT
- Check the expiration date to ensure it has not passed

To validate the signature, the Notification Server requires the public key from a key pair previously generated by the producers operating within a single tenant of FlexNet Operations. The producers must therefore upload the public key to FlexNet Operations, which will then make it available to the Notification Server. The producers can upload the public key using the `updates-service-rest-controller` REST API `/operations/api/updates/update-authorization-key`. For more information, see [Providing FlexNet Operations with the Public Key](#).

The REST APIs mentioned in the following sections must be prefixed with a base URL, as described in [Notification Server Base URL](#).

Documentation about JSON Web Tokens

For further information about JSON Web Tokens, refer to <https://tools.ietf.org/html/rfc7515>. The documentation for your JWS/JWT library will describe how to create JWTs programmatically.

You can also find guidance about generating a JSON web token in the technical article *Demonstration Code to Generate JSON Web Tokens for Updates and Insights* (PDF format), which is accessible from the [Reverera Learning Center](#). To download the PDF, sign into the Learning Center using your Reverera Community credentials. If you do not have a community login, please sign up and be sure to provide your account ID upon registration. On the Learning Center homepage, click **FlexNet Operations** and select the course *Updates and Insights using FlexNet Operations*. Click **Register** to access the PDF in the Resources section.

Update Authorization Key REST API

Upload the public key to FlexNet Operations. FlexNet Operations makes the public key available to the Notification Server, which uses it to verify the JWT sent by a device in an update request.

Table 18-14 • Upload Public Key to FlexNet Operations

Item	Description
URI	<code>/operations/api/updates/update-authorization-key</code>
Method	PUT
Query parameters	<code>authKeyData</code>
Request body	<pre>{ "publicKey": "string" }</pre>
Response codes	200: OK 400: Returned if authorization key format is unsupported. 401: Returned if the Updates and Insights module is not licensed, or the user calling the API does not have permission to manage updates. 500: The request failed due to an internal error. More details can be found in the error message.

Sample Response

For a successful PUT method, no response will be sent.

For a failed PUT method, the response contains an error message and the public key, using the following data structure:

```
{  
  "errorMessage": "string",  
  "publicKey": "string"  
}
```

Securing Update Responses

It is important for devices to be able to verify that information about updates, and the manifests, have not been tampered with. In this way devices can ensure that they only use legitimate download files provided by their software supplier.

The Notification Server therefore provides a `/signed-updates/` API (see [Signed Updates REST API](#)). This API operates in the same way as the `/updates/` API (see [Updates](#)), requiring an initial request followed by a periodic poll. The responses, however, are in the form of a JSON Web Token (JWT) and contain a JSON Web Signature (JWS) which can be used to validate the contents of the response.

The response is validated by checking the signature, and if the signature is found to be invalid then the response should not be used because it has been tampered with. To validate the signature, a public key is needed. This public key can be obtained from FlexNet Operations using the `updates-service-rest-controller REST API /operations/api/updates/update-signing-key/`. You can find instructions on how to use this API in section [Update Signing Key REST API](#). For more details about this API, consult the FlexNet Operations Swagger documentation.

The format of these signed responses, and their detailed use, is described in sections [/uai/2.0/signed-updates](#) and [/uai/2.0/signed-updates/manifests](#).

For further information about JSON Web Signatures, refer to <https://tools.ietf.org/html/rfc7515>. The documentation for your JWS/JWT library will describe how to check the signatures, and decode the responses, programmatically.

Update Signing Key REST API

To ensure the integrity of requests for Updates and Insights update information from devices or other software, the Notification Server creates a JSON Web Signature (JWS) for each update response. A private/public key pair is required to be able to generate and verify the JWS. The client device or software must have access to the public key to verify the JWS.

This API requests the unique public key to be used for the each site. The public key corresponds to a unique private key used to generate the JWS for update requests.

Table 18-15 ▪ Request Public Key from FlexNet Operations

Item	Description
URI	<code>/operations/api/updates/update-signing-key</code>

Table 18-15 • Request Public Key from FlexNet Operations

Item	Description
Method	GET
Query parameters	N/A
Request body	N/A
Response codes	200: OK

Sample Response

This is the data structure for a successful GET method:

```
{  
  "publicKey": "string"  
}
```

Signed Updates REST API

Information on signed updates is divided into the following sections:

- [Find Available Signed Updates](#)
- [Poll for Response to the Request for Signed Updates](#)
- [Request Manifest File](#)
- [Poll for Response to the Request for Manifest File](#)

The REST APIs mentioned in these sections must be prefixed with a base URL, as described in [Notification Server Base URL](#).

Find Available Signed Updates


Request all signed updates available to a device given its identification and the version currently being run, in a JWS signed format.

Use the `deviceClass` parameter to indicate the type of device for which signed updates are requested. The following values are available:

- `client`—indicates a standalone device (this can also be an anonymous device)
- `server`—indicates either a Cloud License Server or a Local License Server
- `served`—indicates a served device.

If deviceClass is not specified, client is the default value.

Table 18-16 • Find Available Signed Updates

Item	Description
URI	/uai/2.0/signed-updates
Method	POST
Query parameters	updatesRequest
Request body	<pre>{ "deviceClass": "string", "id": "string", "idType": "string", "language": 0, "platform": "string", "publisherName": "string", "updateFromPkgId": "string" }</pre>  <p>Note • For devices that are assigned to an account, it is recommended to populate the fields <code>id</code>, <code>idType</code>, and <code>publisherName</code>. For anonymous devices, these fields should be left blank.</p>
Response codes	<p>200: Not used</p> <p>202: Asynchronous request. Use the URL returned to poll for a response.</p>

Sample Response

If the request has been accepted (status 202), a URL including a polling ID to poll for completion of the search is returned:

```
{
  "url": "string"
}
```

Poll for Response to the Request for Signed Updates

Poll for a list of possible signed updates, using the polling ID returned by a POST to the </uai/2.0/signed-updates> API. It can be used repeatedly until a 200 response is received.

Table 18-17 • Poll for Response to the Request for Signed Updates

Item	Description
URI	/uai/2.0/signed-updates/{pollingId}
Method	GET

Table 18-17 • Poll for Response to the Request for Signed Updates

Item	Description
Query parameters	pollingId: ID returned in Find Available Signed Updates service
Request body	N/A
Response codes	200: Success. 202: Submitted request is still being processed. Use the URL returned to continue to poll for the response. 401: The request is unauthorized. This could be because a JWT was not found in the header, the token has expired, the signature is invalid, or a public key could not be identified (most commonly because the public key has not been uploaded to FlexNet Operations). 404: The request failed due to bad input data provided in the request. The response could not be signed because either it was not possible to identify the private key from the request body, or a public key had not yet been requested. More detail can be found in the error response body. 500: The request failed due to an internal error and it was not possible to sign the response. More detail can be found in the error response body.

Sample Response

This is the data structure for a successful response (status 200). The body of the response is a JWS token. Refer to JWS documentation for further details. Once the response has been received, the first step is to verify the signature using the public key and the three fields in the JWS token. If the signature verification fails, then the response content has been tampered with and should not be used. The second step is to Base64 decode the payload field, which will result in a JSON structure containing the list of possible updates for the response. (See the description of the response for [/uai/2.0/updates](#) for more information.)

```
{  
  "payload": "string",  
  "protected": "string",  
  "signature": "string"  
}
```

If the request is still being processed (status 202), a URL to poll for completion of the request is returned:

```
{  
  "url": "string"  
}
```

This is the data structure for a status 404 and 500 response:

```
{  
  "arguments": "string",  
  "key": "string",  
  "message": "string"  
}
```

Request Manifest File

Request a manifest for a specific update, selected from the response to a request for signed updates. (The manifest file contains details of all files required to achieve the update.)

Table 18-18 • Request Manifest File

Item	Description
URI	/uai/2.0/signed-updates/manifests
Method	POST
Query parameters	manifestRequest
Request body	<pre>{ "uuid": "string" }</pre>
Response codes	200: Not used 202: Asynchronous request. Use the URL returned to poll for a response.

Sample Response

If the request has been accepted (status 202), a URL including a polling ID to poll for completion of the request is returned:

```
{
  "url": "string"
}
```

Poll for Response to the Request for Manifest File

Poll for the requested manifest, using the polling ID returned by a POST to the [/uai/2.0/signed-updates/manifests](#) API. It can be used repeatedly until a 200 response is received.

Table 18-19 • Poll for Response to the Request for Manifest File

Item	Description
URI	/uai/2.0/signed-updates/manifests/{pollingId}
Method	GET
Query parameters	pollingId: ID returned in Find Available Signed Updates service
Request body	N/A

Table 18-19 • Poll for Response to the Request for Manifest File

Item	Description
Response codes	<p>200: Success.</p> <p>202: Submitted request is still being processed. Use the URL returned to continue to poll for the response.</p> <p>401: The request is unauthorized. This could be because a JWT was not found in the header, the token has expired, the signature is invalid, or a public key could not be identified (most commonly because the public key has not been uploaded to FlexNet Operations).</p> <p>404: The request failed due to bad input data provided in the request. The response could not be signed because either it was not possible to identify the private key from the request body, or a public key had not yet been requested. More detail can be found in the error response body.</p> <p>410: A response for the polling ID could not be found. This could be a result of using an incorrect polling ID, or of too much time having elapsed, so that the polling ID is no longer valid.</p> <p>500: The request failed due to an internal error and it was not possible to sign the response. More detail can be found in the error response body.</p>

Sample Response

This is the data structure for a successful response (status 200). The body of the response is a JWS token. Refer to JWS documentation for further details. Once the response has been received, the first step is to verify the signature using the public key and the three fields in the JWS token. If the signature verification fails, then the response content has been tampered with and should not be used. The second step is to Base64 decode the payload field, which will result in a JSON structure containing the manifest contents for the response. (See the description of the response for [/uai/2.0/signed-updates/manifests](#) for more information.)

```
{  
  "payload": "string",  
  "protected": "string",  
  "signature": "string"  
}
```

If the request is still being processed (status 202), a URL to poll for completion of the request is returned:

```
{  
  "url": "string"  
}
```

This is the data structure for a status 404, 410, and 500 response:

```
{  
  "arguments": "string",  
  "key": "string",  
  "message": "string"  
}
```


Updates and Insights Exercises

This section walks through the process of creating an additional download package and files for the PhotoPrint product created in the early exercises of the sections [Getting Started with Entitlement Management](#) and [Getting Started with Electronic Software Delivery](#).

Table 18-20 • Updates and Insights Exercises

Topic	Description
Prerequisites	Prerequisites for included exercises.
Preparing FlexNet Operations	Exercises to create a second installation download in FlexNet Operations.
Creating an Update	Instructions for creating an update.
Updates and Insights Next Steps	Instructions for requesting an update from a device and viewing the results.

Prerequisites

The exercises in this getting started section make use of the entities created as part of the exercises in the section [Getting Started with Entitlement Management](#). This section lists the customer account, customer user, product, product line, and entitlements created in [Getting Started with Entitlement Management](#).

Before you begin the exercises in this getting started section:

- The FlexNet Operations demonstration database and seed data must be loaded. (Reverera loads this data as part of the on-boarding process.)
- You must have a FlexNet Operations Producer Portal login.
- You must have a FlexNet Operations Notification Server URL (supplied by Reverera)
- You should have access to the Notification Server REST APIs.

Additionally, the exercises in this getting started section make use of the product, features, and entitlements created in the exercises of the sections [Getting Started with Entitlement Management](#) and [Getting Started with Electronic Software Delivery](#). Any product will suffice, as a sample to which download packages can be linked, but the exercises here use the products created in those getting started sections.

For Producer Portal users who have not yet created their own products and customer users, these items are necessary for the rest of the exercises in this section.

Table 18-21 • Prerequisites

Entity Type	Entities
Customer Account	Barry Photography Studio
Customer User	Lisa Barry

Table 18-21 • Prerequisites

Entity Type	Entities
Product	PhotoPrint This product includes the following features: <ul style="list-style-type: none"> • Print • PrintHighQualityColor • PrintToPDF As indicated in the section Getting Started with Entitlement Management , the features, above, are among those pre-defined in your environment’s demo data.
Product Line	LargeFormat
Entitlement	ENT-PhotoPrint
Activation ID	ACT01-PhotoPrint
Producer	ABCNetworks
File	PhotoPrintInstaller and PhotoPrintReleaseNotes
Download Package	PhotoPrintInstaller

If these entities, such as the entitlement, ENT-PhotoPrint or the download package PhotoPrintInstaller, do not yet exist in your FlexNet Operations instance, follow the exercises in the sections [Getting Started with Entitlement Management](#) and [Getting Started with Electronic Software Delivery](#) to create the necessary entities. For the purposes of these exercises you can skip the section on [Viewing and Downloading Files from the End-User Portal](#) in [Getting Started with Electronic Software Delivery](#).



Important - If the customer user, Lisa Barry, already exists but is not associated with an email address you control, you must create another customer user in the Barry Photography Studio account with the Portal User role. Choose an email address you control for this new customer user so that you can use it to log in to the End-User Portal and see the downloads.

Later in this section, you will create an additional download package and file to be the deliverables for the PhotoPrint update.

Preparing FlexNet Operations

Before creating an update, you must create an additional download package using the Producer Portal. An update requires two packages, **Release From** (the download package the update is for), and **Release To** (the download package that will be delivered for the update). An update can have several Release From packages but only one Release To per software platform. The exercises in section [Getting Started with Electronic Software Delivery](#) created two packages, an installer and a product documentation package. These exercises will create a second installer package.

This preparation includes the following exercises:

Table 18-22 • Preparing FlexNet Operations

Topic	Description
Creating a Download Package	Adds a download package for the products in the LargeFormat product line.
Associating a Download Package with a Product	Links the new download package to a product.
Creating Download Files	Creates files and uploads file images for the files that will be the deliverables in the download package.
Associating Download Files with a Download Package	Links the new files with the download packages to tie products to their deliverables.

Creating a Download Package

In this exercise, you add one download package for the PhotoPrint product:

- PhotoPrintInstaller-V12.1



Task *To create the PhotoPrintInstaller download package*

1. In the Producer Portal, click **Products > Create Download Package**. The Producer Portal opens the Create Download Package page.
2. On the Create Download Package page, set values for the following attributes in Download Package Details.

Attribute	Value
Download Package ID	PhotoPrintInstaller-V12.1
Download Package Name	PhotoPrint Installer Package Ver-12.1
Extended Description	Includes the installer and release notes for PhotoPrint Version 12.1.
Effective Date	Keep the current date default value.
Expiration Date	Set for one year from current date.
Download Package Producer	ABC Networks, Inc.
Product Line	LargeFormat

Attribute	Value
Restrict to US/CANADA (NLR)	No
ECCN	EAR99

Keep the default values for all other attributes.

- For End-User Download Instructions, type the following:

Review system requirements in the release notes (included) prior to running the installer.

Create Download Package

To add a new Download Package fill out the form below. Clicking the **Save Download Package** button will add the new Download Package then display it in view mode. Clicking the **Save & add another** button will add the Download Package and then return to the **Add Download Package** page. To add files to this new Download Package click the **Save & add file** button. To associated already existing files to this new Download Package click the **Save & associate file** button.

Download Package Details

Download Package ID*

Download Package Name*

Extended Description*

Version

Release Group

Effective Date*

Expiration Date*

Archive Date

Download Package Producer*

Product Line*

OR Enter Product Line ID

End User License Agreement

Physical Distribution Available* Yes No

* Required information

Restrict to US/CANADA (NLR) Yes No

If "Restrict to US/CANADA (NLR)" is set to "No", ECCN, ENC, and CCATS codes must be entered in **valid combinations**. You will not be able to select an ENC or CCATS code if it's not a valid option in relation to the selected ECCN code.

ECCN*

ENC*

CCATS*

+ add another ccats

Adds another CCATS text entry box (all existing text entry boxes must be populated prior to adding another).

Figure 18-4: The Create Download Package page for PhotoPrint Installer Package Ver-12.1.

- Click **Save**.

The Producer Portal adds the PhotoPrintInstaller-V12.1 download package and shows its **View Download Package** page.

Associating a Download Package with a Product

In this exercise, you associate the PhotoPrintInstaller -V12.1 download package with the PhotoPrint product.



Task *To associate the PhotoPrintInstaller download package to the PhotoPrint product*

1. In the Producer Portal, click **Products > Search Download Packages**. The Producer Portal opens the Search Download Packages page.
2. On the Search Download Packages page, type this value for **Download Package ID: PhotoPrintInstaller-V12.1**.
3. Click **Search**. The Producer Portal opens the Search Results: Download Packages page and shows the PhotoPrintInstaller-V12.1 download package in the search results.
4. Click the download package ID link for **PhotoPrintInstaller-V12.1**. The Producer Portal opens the **View Download Package** page for PhotoPrintInstaller-V12.1.
5. On the **View Download Package** page, click **Associate > Associate to Product**. The Producer Portal opens the Associate this Download Package to Products page.
6. In Search Products, for **Product ID** type **Photo*** and click **Search**. The Producer Portal shows a list of products with matching product IDs.

Associate this Download Package to Products

Listed below are the results of your search. To associate this Download Package to Products check the box next to the Product(s) you want to associate this Download Package to and click the Associate this Download Package to the Selected Products button.

Download Package ID PhotoPrintInstaller-V12.1

System Download Package ID 6688322

Download Package Name PhotoPrint Installer Package Ver-12.1

Version

1 to 1 of 1

Show 25 per page

Search again

System Product ID	Product ID	Product Name	Product Line	Product Status	Download Packages
<input type="checkbox"/> 6686542	PhotoPrint:12.0	Sends to PDF file, prints normal quality, or prints high quality.	LargeFormat	ACTIVE	2

[Associate download package to the selected products](#)

Figure 18-5: In Search Products, use Photo* to find the PhotoPrint product.

7. Select the check box for **PhotoPrint::12.0** and then click **Associate Download Package to Selected Products**.



Important - Notice that the product ID for PhotoPrint is a combination of the product name and product version: **PhotoPrint::12.0**. This is how FlexNet Operations identifies the product, internally. One ramification of the product ID syntax is that a search for the product by its product name, **PhotoPrint**, does not match the product ID. For best results, use an asterisk as a wildcard character to be sure your product search captures the product you are looking for. For example, **Photo*** or **PhotoPrint*** successfully finds PhotoPrint.

The Producer Portal saves the product-download package association and shows the Where Download Package Used page for PhotoPrintInstaller.

Creating Download Files

In this exercise, you create 2 download files as the deliverables for the PhotoPrint product.

- PhotoPrintInstaller-V12.1
- PhotoPrintReleaseNotes-V12.1

For each file, the exercises add a file definition and upload its file image. For these exercises it does not matter what files you upload. You can use text files renamed to reflect their respective contents.



Task To create the PhotoPrintInstaller-V12.1 file

1. In the Producer Portal, click **Products > Create File**. The Producer Portal opens the Create File page.
2. On the Create File page, type values for the following attributes.

Attribute	Value
File ID	PhotoPrintInstaller-V12.1
File Description	PhotoPrint Installer Ver-12.1
Extended Description	Installs PhotoPrint version 12.1.
Content Detail	Review the release notes prior to running the installer.

Select the **Execute Upon Download** box and keep the default values for all other attributes.

Create File

To add a new File fill out the form below. Clicking **Save** will add the new file and display the new file in view mode. Clicking **Save & add another** will add the file and then return you to the Add a File page. To upload a file image click the **Save & upload file** button.

File ID* PhotoPrintInstaller-V12.1

File Description* PhotoPrint Installer Ver-12.1

Extended Description Installs PhotoPrint version 12.1.

Delivery Source FlexNet Operations External

Execute Upon Download?

File Name

Content Detail Review the release notes prior to running the installer.

Save Save & add another... Save & upload file...

Figure 18-6: The Create File page for PhotoPrintInstaller-V12.1.

3. Click **Save & Upload File**. The Producer Portal opens the Upload File page.

Upload File

After the file definition has been added the next step is to upload the file image/binary. Choose one of the methods below. During the upload process these data fields: File Name, File Size, File Contents (for .zip and .jar files), and MD5 CheckSum will become populated and their status updated to "LOADED".

View Edit Associate

File Details

File ID ? PhotoPrintInstaller-V12.1
 System File ID ? 6681742
 Alias No

File Description ? PhotoPrint Installer Ver-12.1
 File Name ?
 File Status ? NOT_LOADED

HTTP Upload
FTP Upload
Remote FTP Server
High Speed Upload

Click the **Browse** button to select the file from your PC then click **Upload file** to start the upload.

File to Upload from Local File System ? No file selected.

Expected MD5 CheckSum ?

Figure 18-7: The Upload File page for PhotoPrintInstaller-V12.1.

4. Click **Browse...** and select a file to upload. (Button names may vary for different web browsers and operating systems.)
5. Click **Upload**.

The Producer Portal uploads the file image, saves the file, and shows its View File page.

6. Repeat steps 1-5, above, to create the file definitions and upload file image for PhotoPrintReleaseNotes-Version 12.1. Use the values below for the file definition. Use any small file as the file image.

Attribute	Value
File ID	PhotoPrintReleaseNotes-V12.1
File Description	PhotoPrint Release Notes Version 12.1
Extended Description	Includes a PDF of the PhotoPrint Release Notes

Next, you will associate these files to their download packages and review the customer experience in the End-User Portal.

Associating Download Files with a Download Package

In this exercise, you associate the download files with their download package, as shown in the table below.

Table 18-23 - Associating Download Files with a Download Package

Download Package	Download Files
PhotoPrintInstaller-V12.1	PhotoPrintInstaller-v12.1
	PhotoPrintReleaseNotes-V12.1

These associations complete the connection between the download files and the product to which the customer user, Lisa Barry, is entitled.







Task *To associate the PhotoPrintInstaller-V12.1 download package with its download files*

1. In the Producer Portal, click **Products > Search Download Packages**. The Producer Portal opens the Search Download Packages page.
2. On the Search Download Packages page, type this value for **Download Package ID: PhotoPrintInstaller***.
3. Click **Search**. The Producer Portal opens the Search Results: Download Packages page and shows the PhotoPrintInstaller and PhotoPrintInstaller-V12.1 download packages in the search results.
4. Click the Download Package ID link for **PhotoPrintInstaller-v12.1**. The Producer Portal opens the **View Download Package** page for PhotoPrintInstaller-V12.1.
5. On the **View Download Package** page, click **Associate > Associate Files**. The Producer Portal opens the Associate Files to this Download Package page.
6. Under **Enter the File IDs of Files to Associate to this Download Package**, type the following in **File IDs**: **PhotoPrintInstaller-V12.1, PhotoPrintReleaseNotes-V12.1**.

Associate Files to this Download Package

To associate files to this Download Package either enter in the file IDs and click the **Associate files** button or if you don't know the IDs perform a search and a list of files that meet your criteria will be displayed.

Download Package Details

Download Package ID  PhotoPrintInstaller-V12.1
System Download Package ID  6688322
Download Package Name  PhotoPrint Installer Package Ver-12.1
Version 

Enter the File IDs of Files to Associate to this Download Package

File IDs

Use System IDs

Multiple File IDs can be entered one per line or separated by commas. To enter System File IDs, check the box "Use System IDs" below the input box. Wildcards can not be used.

Associate files

Figure 18-8: The Associate Files to this Download Package page with file IDs for the PhotoPrint Installer Package.

7. Click **Associate Files**.

The Producer Portal makes the file associations with the PhotoPrintInstaller download package and shows its **View Download Package** page. Notice that the **View Download Package** page now shows the two associated files: PhotoPrintInstaller-v12.1 and PhotoPrintReleaseNotes-V12.1.

When the download package is associated with its download files, you are ready to create an Update.

Creating an Update



Task *To create an update*

1. In the Producer Portal, click **Products > Updates**. The Producer Portal opens the Updates page.
2. Click the **Create** button. The Producer Portal opens the Update page to the Overview tab.
3. On the Overview tab, set values for the following attributes:

Attribute	Value
Name	PhotoPrint-Update
ID	PhotoPrint-Update-V12.1
Start Date	Keep the current date default value.

Attribute	Value
End Date	Set for one year from current date.
Description	Update PhotoPrint from version 12 to version 12.1

4. Leave the other default settings.



Figure 18-9: Update overview tab



Note ▪ The entitlement check setting is used when you want to ensure that the account or device requesting an update is authorized to do so. If the update must be usable by an anonymous device (a device which is not assigned to an account) then the Entitlement check must be set to **None**. Served devices will only receive updates whose entitlement check is set to **Account** or **None**. For all devices, the default setting is **Account**. For information on the available settings, see [Update Overview](#).



Task *To add the download package to be updated to the Release From tab*

1. Click on the **Release From** tab. The Producer Portal opens the **Release From** tab.
2. Click the **Add** button. The **Release From** pop-up window is displayed.
3. In the Search field, type **PhotoPrint*** and click **Search**. The Producer Portal shows a list of download packages with matching download package IDs, including: **PhotoPrintInstaller** and **PhotoPrintInstaller-V12.1**.
4. Select the **PhotoPrintInstaller** package check box, the version 12.0 installer that the update is for.




Figure 18-10: Release From download package selection

5. Click **OK**. **PhotoPrintInstaller version 12.0** is listed on the **Release From** tab.



Task *To add the download package update to the Release To tab*

1. Click on the **Release To** tab. The Producer Portal opens the **Release To** tab.
2. Click the **Add** button. The **Release To** pop-up window is displayed.
3. From the Platform drop-down list, select **Windows-64**.
4. In the Search box, type **PhotoPrint*** and click **Search**. The Producer Portal shows a list of download packages with matching download package IDs: **PhotoPrintInstaller** and **PhotoPrintInstaller-V12.1**.
5. Select the **PhotoPrintInstaller-V12.1**





Figure 18-11: Release To selection

6. Click **Select**.
7. Repeat steps 1-6 to create a second **Release To** package using the Windows-32 platform.



Task *To add a language to the update*

1. Click on the **Languages** tab. The Producer Portal opens the **Languages** tab.
2. Click the **Add** button. The **Language** pop-up window is displayed.
3. From the Language drop-down list, select, **English**. The Producer Portal opens the **Languages** tab.
4. In the Title field type: **English**
5. In the Description field type: **English language**.



6. Click **OK**. **English** is listed on the Languages tab.
7. Click **Save**. The Producer Portal displays a message that says update creation was successful.

Updates and Insights Next Steps

Before carrying out the following steps, it is recommended that the device is registered with FlexNet Operations. This enables you to verify that an update has been successful.

Registration can be achieved:

- Using the FlexNet Operations Producer Portal
- Carrying out a capability request with a valid activation ID
- Using the `/registrations` REST API in the Notification Server. This last method is particularly recommended for anonymous devices, because they will not have an activation ID to be able to execute a capability request. The `/registrations` API allows a device to register itself with FlexNet Operations, and avoids the manual step of using the Producer Portal.

The next steps walk you through exercises showing how to request updates using the REST APIs.

The REST API calls, with examples of their payloads and responses, are shown below. The steps differ depending on whether the updates and manifests that you request are signed or not.

Steps for [Requesting Updates and Manifests](#) include the following:

- [Requesting Updates](#)
- [Polling for Updates](#)
- [Requesting the Manifest](#)
- [Polling for Manifest](#)

Steps for [Requesting Signed Updates and Manifests](#) include the following:

- [Obtaining the Public Key](#)
- [Requesting Signed Updates](#)
- [Polling for Signed Updates](#)
- [Requesting the Signed Manifest](#)
- [Polling for Signed Manifest](#)

Finally, verify the update in the FlexNet Operations Producer Portal as described in [Verifying the Update](#).

Requesting Updates and Manifests

Instructions for requesting updates and manifests are described in the following sections:

- [Requesting Updates](#)
- [Polling for Updates](#)

- Requesting the Manifest
- Polling for Manifest

Requesting Updates



Task To request the updates

Make a POST call to `https://<siteID>-ns-uat.flexnetoperations.com/uai/2.0/updates`.

Body Type	Code
Request Body	<pre>{ "updateFromPkgId": "PhotoPrintInstaller", "language": "1033", "platform": "WIN64", "id": "PhotoPrintInstaller-V12", "idType": "STRING", "publisherName": "ABCNetworks" }</pre>
	<p>Note - For devices that are assigned to an account, it is recommended to populate the fields <code>id</code>, <code>idType</code>, and <code>publisherName</code>. For anonymous devices, these fields should be left blank.</p>
Response Body	<pre>{ "url": "/uai/2.0/updates/67089b0f-4b8a-4e53-a970-2cb92217459e" }</pre>

Polling for Updates

Poll for the updates using the provided polling URL. If a 202 response code is received, repeat the polling until a 200 response is received.



Task To poll for the updates

Make a GET call to `https://<siteID>-ns-uat.flexnetoperations.com/uai/2.0/updates/67089b0f-4b8a-4e53-a970-2cb92217459e`.

Body Type	Code
Request Body	N/A

Body Type	Code
Response Body	<pre>{ "updateItems": [{ "commandLine": "", "description": "Update PhotoPrint from version 12 to version 12.1", "expireDate": "05/01/2025", "fromPackageId": "PhotoPrintInstaller-V12", "updateId": "PhotoPrint-Update-V12.1", "languageCode": 1033, "updateName": "PhotoPrint-Update", "productName": "", "startDate": "05/01/2018", "title": "Update for PhotoPrint", "toPackageId": "PhotoPrint-Update-V12.1", "manifestURL": "/uai/2.0/updates/manifests/c4c8c5d6-3574-42ae-9cd9- d6aa737a1dbe" }], "error": { "key": "", "message": "", "arguments": "" } }</pre>

Requesting the Manifest

Request the manifest using the manifest UUID in the response received in [Polling for Updates](#).



Task *To request the manifest*

Make a POST call to `https://<siteID>-ns-uat.flexnetoperations.com/uai/2.0/updates/manifests`.

Body Type	Code
Request Body	<pre>{ "uuid": "c4c8c5d6-3574-42ae-9cd9-d6aa737a1dbe" }</pre>
Response Body	<pre>{ "url": "/uai/2.0/updates/manifests/16489f0c-3b34-abfa-b342-3fe2459023e1" }</pre>

Polling for Manifest

Poll for the manifest using the provided polling URL. If a 202 response code is received, repeat the polling until a 200 response is received.



Task **To poll for the manifest**

Make a GET call to `https://<siteID>-ns-uat.flexnetoperations.com/uai/2.0/updates/manifests/16489f0c-3b34-abfa-b342-3fe2459023e1`.

Body Type	Code
Request Body	N/A
Response Body	<pre>{ "manifestVersion": "1.0", "manifestFiles": [{ "fileUrl": "https://example.com/filename.txt", "fileSize": "2781", "md5Hash": "624fd6479cbc870e2ed53db729827954", "sha256Hash": "cffffe67239921fbde19f4d1994bafb49016e7bd257f8ef81fe63501b81872346", "execute": "no" }] }</pre>

This step completes the registration.

Requesting Signed Updates and Manifests

Instructions for requesting signed updates and manifests are described in the following sections:

- [Obtaining the Public Key](#)
- [Requesting Signed Updates](#)
- [Polling for Signed Updates](#)
- [Requesting the Signed Manifest](#)
- [Polling for Signed Manifest](#)

Obtaining the Public Key

The public key can be obtained directly from FlexNet Operations using the `updates-service-rest-controller` REST API.



Task *To obtain the public key*

Make a GET call to `https://<siteID>-uat.flexnetoperations.com/flexnet/operations/api/updates/update-signing-key`.

Body Type	Code
Request Body	<code>BarryPhotoStudio</code>
Response Body	<pre>{ "publicKey": "MIGfMA0GCSqGSIb3DQEBAQUAA4GNADCBiQKBgQCvVqg5xomVn3ZCnp+Ln5Ia1z 0DUPmyETIAw8I+N9zsf+c3PSWrFBQr8RwuJDFndT7bjGB/UhATyk3yaGT7Lsp/ v8XUY1iUegQ0ZxK83h6DzRDcOemApchEffAwJp0Egw1t3qpZbEhxaT2wJaiodLyYEX0ebk1+dAW00ME o3A0L+wIDAQAB", "errorMessage": "" }</pre>


This public key is required to verify the signature in the response obtained in [Requesting Signed Updates](#).

Requesting Signed Updates



Task *To request signed updates*

Make a POST call to `https://<siteID>-ns-uat.flexnetoperations.com/uai/2.0/signed-updates`.

Body Type	Code
Request Body	<pre>{ "updateFromPkgId": "PhotoPrintInstaller", "language": 1033, "platform": "WIN64", "id": "PhotoPrintInstaller-V12", "idType": "STRING", "publisherName": "ABCNetworks" }</pre>  <p>Note - For devices that are assigned to an account, it is recommended to populate the fields <code>id</code>, <code>idType</code>, and <code>publisherName</code>. For anonymous devices, these fields should be left blank.</p>
Response Body	<pre>{ "url": "/uai/2.0/signed-updates/67089b0f-4b8a-4e53-a970-2cb92217459e" }</pre>

Requesting the Signed Manifest



Task To request the manifest

Make a POST call to `https://<siteID>-ns-uat.flexnetoperations.com/uai/2.0/signed-updates/manifests`.

Body Type	Code
Request Body	<pre>{ "uuid": "c4c8c5d6-3574-42ae-9cd9-d6aa737a1dbe" }</pre>
Response Body	<pre>{ "url": "/uai/2.0/signed-updates/manifests/16489f0c-3b34-abfa-b342-3fe2459023e1" }</pre>

Polling for Signed Manifest

Poll for the signed manifest using the provided polling URL. If a 202 response code is received, repeat the polling until a 200 response is received.



Task To poll for the signed manifest

Make a GET call to `https://<siteID>-ns-uat.flexnetoperations.com/uai/2.0/signed-updates/manifests/16489f0c-3b34-abfa-b342-3fe2459023e1`.

Body Type	Code
Request Body	N/A
Response Body	<pre>{ "protected": "eyJhbGciOiJSUzI1NiJ9", "payload": "eyJtYW5pZmVzdFZlcnNpb24iOiIxLjAiLCJtYW5pZmVzdEZpbGVzIjpbeyJmaWxlVXJsIjoiaHR0cHM6Ly9leGFtcGxlLmNvbS9maWxlbmFtZS50eHQiLCJmaWxlU216ZSI6IjY2Njg5MSIsIm1kNUhhc2giOiJlMzgzOTB1NDcwM2ViNjVkbmZkMmVjMTA5ZjJjOTg4NiIsInNoYTI1Nkhhc2giOiIiLCJleGVjdXRlIjoibm8ifV19", "signature": "S0xEZx0rPPRr_tWQ2ufQJ9pkC90ZGkrjxuAqLunm7GDjw2hreXAsEFsxlahiklwaLcJUfArN03C4o0XEAQRs0prJhfRxywHzLzyf1ImO3Ku-A9XRxr3rYpmCfLWJWxVH8cVXHBHVmo5mV50sXPOBeohrcLKUSzo1u3IMTEoi5cQ" }</pre>

Use the response to do the following:

- Check signature.** Any tool or library that verifies a signature will use all three fields from the response and the public key (obtained using the REST API `/update-signing-key/`).

- **Decode response.** Any Base64URL decoder will be able to decode the response into JSON format, providing the same information as seen in the previous section, **Requesting Updates and Manifests**. (The tool used to check the signature will probably return a decoded response.)

This step completes the registration.

Authorizing Requests for Updates and Manifests

This section describes how to include a JSON Web Token (JWT) in the header of a request coming from a device. This JWT can then be used to check that the device is authorized to make the request.

Authorizing a request for an update or manifest usually involves the following steps:

1. **Generating a Public/Private Key Pair**
2. **Providing FlexNet Operations with the Public Key**
3. **Creating a JWT**
4. **Adding the JWT to the Request**

Generating a Public/Private Key Pair

Using a third-party application or library of your choice, generate a public and private key pair, using the RS256 algorithm. This key pair will be used to generate and validate the JWT sent in authorization requests.

Various third-party tools are available for generating this key pair. Refer to the documentation supplied with the tool for instructions.

Providing FlexNet Operations with the Public Key

You need to provide FlexNet Operations with the public key created in the previous step. FlexNet Operations then makes this public key available to the Notification Server, which uses the key to validate the signature of the JWT.



Task *To upload the public key to FlexNet Operations*

Make a PUT call to `https://<siteID>-uat.flexnetoperations.com/flexnet/operations/api/updates/update-authorization-key`.

Body Type	Code
Request Body	<pre>{ "publicKey": "MIGfMA0GCSqGSIb3DQEBAQUwJp0Egwlt3qpZbEhxaT2wJaiodLyYEXn3ZCnp+Ln5Ia1 z0DUPm yETIAw8I+N9zsf+c3PSWr-fBQr8RwuJDFndT7bjGB/UhATyk3yaGT7Lsp/ v8XUY1iUegQ0ZxK83h6DzRDc0emApchEffa0ebk1+dAw0OMeo3A0LAA4GNADCBiQKBgQCVvQg5xomV +wIDAQAB" }</pre>
Response Body	N/A

No response will be sent.

Creating a JWT

Using a suitable third-party tool, generate a JWT signed by the private key that you generated in step [Generating a Public/Private Key Pair](#). Refer to the documentation supplied with the tool for instructions. Ensure that the JWT includes an appropriate expiration date, in seconds since 1970-01-01 (the purpose of the expiration date is to provide a way for the token to expire, so that it will not be possible for a device to be perpetually authorized).

See also [Documentation about JSON Web Tokens](#).

Adding the JWT to the Request

The signed JWT must be added to the Authorization: Bearer header of every POST request to the Notification Server.



Task To submit the authorized POST request

When making a request for either /updates/ or /signed-updates/, add the JWT to the Authorization: Bearer header so that it resembles this example:

```
Authorization: Bearer
eyJhbGciOiJSUzI1NiJ9.eyJleHAiOjE1NTcwOTEwOT19.PMMvCR10kTctS1pDIKzEHIVeJictvc5RrN2keQCU5AUp-tg1e-kIX00tuaHKZJEfVfDmZqvDu1I47t5_vcB_VeFb12QQirvzkrG1YHbyZMLmc_jMSSsgAqvS1az83jOU71JvF_bZ1_xv503jb5MJDoD6v4Miuc-J46hJGe4UvEc
```

Verifying the Update

For registered devices, the update can be verified in the FlexNet Operations Producer Portal. (It is recommended that devices are registered before updates begin. Anonymous devices—devices that are not assigned to an account—should be registered using the /registrations REST API in the Notification Server.)



Task To verify the update

1. In FlexNet Operations Producer Portal click **Devices > Devices**. The Producer Portal opens the **Devices** page.
2. In the Search field, enter your device name and click **Search**.



Tip - The Device name is typically the first Ethernet ID for the device making the request or the first custom Ethernet ID defined for the device.

The Producer Portal returns the result:

Devices

Create device

1 Results Device name Search

Name	ID	Type	Account	Licenses	Updates	Last Modified
UAIC8FE03A7	UAIC8FE03A7 (STRING)	Standalone Device	BarryPhoto (Barry Photography Studio)	No licenses	Update info	May 09, 2018

3. Hover over the **Update Info** hyperlink to see up to the last five activities for the device:

4

Device name Search

Account	Licenses	Updates	Last Modified
		Update Info	May 09, 2018

Update name	Id	Status	Last activity
PhotoPrint-Update	PhotoPrint-Update-V12.1	Install completed	May 9, 2018 18:02:22
PhotoPrint-Update	PhotoPrint-Update-V12.1	Install started	May 9, 2018 18:01:49
PhotoPrint-Update	PhotoPrint-Update-V12.1	Download completed	May 9, 2018 18:01:48
PhotoPrint-Update	PhotoPrint-Update-V12.1	Download started	May 9, 2018 18:01:44
PhotoPrint-Update	PhotoPrint-Update-V12.1	Message delivered	May 9, 2018 18:01:44



Note ▪ Update details are also available on the **Updates** tab of a specific anonymous device.

Getting Started with FlexNet Customer Growth

The section *Getting Started with FlexNet Customer Growth* presents customer health visualization and entitlement renewal concepts and includes instructions for viewing customer health information as well as exercises for performing basic renewal tasks.

The intended audience for this getting started section is the first-time Producer Portal user, or one without FlexNet Operations training or experience, but one who has previously completed the exercises in the section [Getting Started with Entitlement Management](#).

Section	Description
Introduction	<p>Overview of this getting started section as well as a brief discussion of the licensing lifecycle, a summary of the features available with the FlexNet Customer Growth module, and a list of prerequisites for the exercises in this getting started section.</p> <ul style="list-style-type: none"> • The License Lifecycle: FlexNet Customer Growth • The FlexNet Customer Growth Module • Exercise Prerequisites
FlexNet Customer Growth Concepts	<p>A discussion of basic FlexNet Operations customer health and renewal management concepts. This section describes the customer health and renewal features and their components and controls.</p>
Visualizing Customer Health	<p>Instructions for navigating to and working with the Customer Growth dashboard and related account health pages in the Producer Portal to see the account health, renewal health, and consumption scores for your customers.</p>

Section	Description
Notifying End Users about Expiring Entitlements	A series of exercises that demonstrate how to create renewals for expiring entitlements, how to activate email templates used to send renewal-related messages, how to set up the Expiring Entitlements job in the Producer Portal, and how to see Renewal Reminder email messages and view expiring entitlements in the End-User Portal, and how to send an intent-to-renew message from the End-User Portal.
Notifying End Users About Expired Entitlements	A series of exercises that demonstrate how to set up the Expired Entitlements job and how to see the results of that job in the Producer Portal, End-User Portal, and Renewal Reminder messages.

Introduction

This section provides a brief discussion of the licensing lifecycle, a summary of the features available with the FlexNet Customer Growth module, and a list of prerequisites for the exercises in this getting started section.

- [The License Lifecycle: FlexNet Customer Growth](#)
- [The FlexNet Customer Growth Module](#)
- [Exercise Prerequisites](#)

The License Lifecycle: FlexNet Customer Growth

The FlexNet Operations license lifecycle is a repeating process of producer and customer activities, as depicted in the figure and described below.



Figure 19-1: FlexNet Operations License Lifecycle

- **Create Products**—Create product definitions that are used to generate licenses.
- **Order/Entitle**—Define an account’s rights to obtain licenses for your products.
- **Deliver/Install**—Deliver the application software to the customer and install that software.
- **Activate**—Deliver licenses to the customer.
- **Return/Rehost**—Manage license transfers from one user or system to another.
- **Maintain/Update**—Deliver software updates to the customer.
- **Upsell/Renew**—Renew customer licenses, or sell the customer additional product functionality.

This getting started section focuses on FlexNet Customer Growth features in the Upsell/Renew phase.

The FlexNet Customer Growth Module

The intent of the FlexNet Customer Growth module is to improve the end-customer nurturing process and reduce churn through visual account health indicators and automated renewal alerts.

The FlexNet Customer Growth module provides a dashboard, donut charts, and pages to highlight the health of your accounts and adds more robust support for the renewals process to FlexNet Operations. Producers who use FlexNet Operations with the FlexNet Customer Growth module can configure FlexNet Operations to automatically identify expiring entitlements and send renewal reminder messages to those accounts with licenses that are nearing their expiration date. In addition, the End-User Portal gains a new **Expiring Entitlements** page. This page lists an end user’s entitlements by their expiration date and gives special emphasis to those entitlements that

have expired or that are nearing their expiration date. On the **Expiring Entitlements** page, end users can select entitlements they want to renew and click a **Request** button to send a message to the producer about their intent to renew.

The Exercise Prerequisites section, below, identifies what producers need in order to complete the exercises in this getting started section.

To read more about FlexNet Customer Growth features and concepts, see [FlexNet Customer Growth Concepts](#). (See [Visualizing Customer Health](#) for instructions on the use of these pages and features.)

To walk through exercises that illustrate the process of setting up FlexNet Operations to automatically alert end users about expiring or expired entitlements, see [Notifying End Users about Expiring Entitlements](#) or [Notifying End Users about Expiring Entitlements](#).

Exercise Prerequisites

Two areas of this getting started section provide exercises basic renewal tasks. The exercises show how to create renewal entitlements, set up the Expiring Entitlements and Expired Entitlements jobs, customize the Renewal Reminder email template, view Expiring Entitlements in the End-User Portal, view a Renewal Reminder message, and send an intent-to-renew message from the End-User Portal.

Before you begin the exercises in this getting started section, verify that you meet the following prerequisites:

- The FlexNet Operations demonstration database and seed data must be loaded. (Revenera loads this data as part of the on-boarding process.)
- You must have a FlexNet Operations Producer Portal login.
- End-User Portal users must have the View Expiring Entitlements permission to see the **Expiring Entitlements** page or to elect to receive renewal reminders.

Additionally, the exercises in this getting started section make use of the account, user, product, features, and entitlement created in the early exercises of the section [Getting Started with Entitlement Management](#). Any product will suffice, as a sample to which expiring entitlements and renewals can be linked, but the exercises here use the product created in that getting started section.

FlexNet Customer Growth Concepts

This section introduces FlexNet Customer Growth concepts.

Section	Description
The Customer Growth Dashboard	Explains how to read the Account Health, Renewal Health, and Consumption charts and also covers the Account KPIs list on the dashboard page and the Watchlist functionality.
Account Health Pages	Describes the main Accounts Health page as well as the Account Health detail pages for a particular account.

Section	Description
Renewals	Briefly discusses how renewals fit in the license lifecycle, describes renewal jobs, renewal reminder email messages, and the End-User Portal's Expiring Entitlements page. This section also provides more detailed examples of how FlexNet Operations handles the display of and messaging for expiring entitlements.
Next Steps	Briefly discusses how to proceed in this getting started section according to your own needs and interests.

The Customer Growth Dashboard

The Customer Growth Dashboard shows charts for the three customer health scores above a list of accounts that shows the Key Performance Indicators (KPIs) for each account. By default, the charts and the account list include all of your accounts. If you select one or more accounts for more regular observation and add them to your watchlist, you can use the Watchlist toggle switch to include only the watched accounts in the charts and the list.

The following sections have more detail about the charts, the KPI scores, and account list, and the watchlist.

Section	Description
About the Dashboard Charts	Describes how the dashboard charts are composed, what they show, and how the interactive elements of the chart function. This section also explains how account health-related system configuration settings affect how the charts are rendered.
Key Performance Indicator (KPI) Scores	Discusses the KPI scores in more detail. For each chart—Account Health, Renewal Health, and Consumption—this section describes how the scores are calculated and how they are rendered on the Account Health pages.
About the Dashboard Account List	Describes how the accounts are listed on the Customer Growth Dashboard page and what the trend lines represent.
Watched and Unwatched Accounts	Explains what the watchlist is, how you can add or remove accounts from the watchlist, and how the Watchlist toggle alters the content of the account health charts and lists.
Alerts	Explains what triggers an alert and what type of alerts are generated.

About the Dashboard Charts

Visible from both the FlexNet Operations Home page and the **Customer Growth Dashboard** page, the Customer Growth Dashboard provides an at-a-glance view of overall health scores. This information is an aggregation of all the producer's accounts, by default. It shows the number of healthy, warning and at risk items for account health, renewal health, and consumption, each in its own donut chart.



For each chart, the overall score for all your accounts is represented by the number in the center. The arrows indicate trends, whether the scores are ascending or descending. Hover over the colored chart segments to find the number of accounts in that category. Click on a segment to be taken to the Accounts Health page with filters set for the score type and condition to match the segment you clicked.

Customer Growth Charts

The donut charts on the **Customer Growth Dashboard** page primarily show the Account Health, Renewal Health, and Consumption scores for your accounts—either all your accounts or all your watched accounts, depending on your Watchlist setting. (See [Watched and Unwatched Accounts](#) for information about using the Watchlist.)

- **Account Health**—The Account Health score is a weighted combination of the other account metrics (Renewal Health and Consumption).
- **Renewal Health**—The Renewal Health score provides an overall rating for your accounts based mainly on how close the accounts' entitlements are to their expiration dates. The chart also indicates the number of entitlements in each category (healthy, warning, and at risk) with the overall score of those accounts in the center.
- **Consumption**—The Consumption score represents the ratio of products, features, or licenses used to the total number products, features, or licenses to which the accounts are entitled. Higher scores are better and indicate healthy consumption rates. Lower scores indicate that your accounts are further away from consuming the quantities to which they are entitled.

When the Producer Portal renders the chart segments, it applies the health threshold values in the system configuration settings.

System Configuration Settings for Customer Health Scores

The following system configuration settings play a role in determining whether an account's condition is considered healthy, warning, or at risk.

Table 19-1 ▪ Customer Health-related System Configuration Settings

Name	Possible Values	Description
Consumption Thresholds (Low,High)	0-100,0-100 Default: 30,70	The low and high markers for service consumption levels. Consumption is considered unhealthy if below the low threshold and very healthy if at or above the high threshold.
Renewal Health Thresholds (Low,High)	0-100,0-100 Default: 30,70	The low and high markers for a customer's renewal health. A low renewal health score is indicative of a risky renewal. A renewal health at or above the high mark translates to a high probability of the renewal.
Account Health Thresholds (Low,High)	0-100,0-100 Default: 30,70	The low and high markers for an account's overall health. The account is considered unhealthy if below the low threshold and very healthy if at or above the high threshold.



Tip ▪ Producers can set the threshold values in their system configuration settings. In the Producer Portal, click **System > Configure > FlexNet Operations > Health**.

Key Performance Indicator (KPI) Scores

The scores shown on the customer health pages indicate the fitness of your customer accounts by helping you visualize the accounts that are healthy, at risk, or in between. The Customer Growth Dashboard shows three scores:

- The Consumption score shows the ratio of products, features, or licenses used to the total number of products, features, or licenses entitled expressed on a 100-point scale.
- The Renewal Health score provides a weighted score to highlight accounts with entitlements that are approaching their expiration date.
- The Account Health score is simply a combination of Consumption and Renewal Health scores: $(\text{Renewal Score} + \text{Consumption Score}) / 2$.

These scores appear in the dashboard charts, the dashboard's account list, the Accounts Health page, and the account details pages.

Consumables Counted Towards the Consumption Score

The items that count towards consumption depend on the type of licensing used. When FlexNet Operations calculates the Consumption score, it counts the following items:

- FlexNet Publisher—fulfillments generated from entitlements
- FlexNet Embedded (Standalone device)—licenses mapped from entitlements

- FlexNet Embedded (Local or Cloud license server)—features checked out by served devices
- Third part license technology—fulfillments generated from entitlements

This number is based on the number of consumed versus total available consumable features or licenses for that product to which the account is entitled. The number is then assigned a status of **healthy**, **warning** or **at risk** depending on the system configuration setting for the consumption threshold.

In the Producer Portal, click **System > Configure > FlexNet Operations > Health** to set **Consumption Threshold** values.

Renewal Health Calculation

The formula for calculating the Renewal Score is based on two factors:

1. How far the products are from their expiration dates (for subscription or maintenance lines).
2. The Consumption value which is a score of consumed quantities of what an account has purchased.

For the first factor, there are three weighted renewal periods, based on how close the entitlements are to their expiration dates: Renewal Look Ahead, Expiring Window, and Renewal Critical. These renewal periods are labels for how close an entitlement is to its expiration date.

Table 19-2 • Weights and Thresholds for Each Renewal Period

Renewal Period	Weight	Default Threshold
Renewal Look Ahead	.25	200 days
Expiring Window	.50	90 days
Renewal Critical	.90	30 days

The renewal period *weights* are fixed and not configurable; however, producers can configure the renewal period *threshold* values in their system configuration settings. In the Producer Portal, click **System > Configure > FlexNet Operations > Renewals**.

The complete formula for the renewal score is

$$(1 - ((\text{Renewal Look Ahead} * .25) + (\text{Expiring Window} * .50) + (\text{Renewal Critical} * .90) + \text{Consumption Score})) / 2$$

where the value for each renewal period is either 0 or 1.

Using the renewal period values, only one renewal period (Renewal Look Ahead, Expiring Window, and Renewal Critical) is factored in to the score at a time. Once a product enters a specific renewal period, that renewal period gets a value of 1 and all other renewal periods get a value of zero.

About the Dashboard Account List

The **Customer Growth Dashboard** page also lists your accounts below the charts. The account list displays the overall health score, the account name, and a 30-day trend for each account shown.

Customer Growth Dashboard



The Accounts list shows up to 20 accounts. Clicking **Show More** adds 20 more accounts to the list for each click until you reach the end of the list.



Tip - The **Accounts** list on the **Customer Growth Dashboard** page shows either all accounts or watched accounts. When showing all accounts, the Accounts list shows any watched accounts at the top of the list.

Watched and Unwatched Accounts

The Producer Portal includes a Watchlist to which you can add or remove the accounts you want to follow most closely on the Customer Growth pages. Initially, the Watchlist is empty, but you can manage your Watchlist on the Accounts Health page by clicking the Watch/Unwatch icon. Then, on the Customer Growth Dashboard, you can switch between All Accounts and Watchlist, depending on whether you want to see metrics for all accounts or focus in on only the watched accounts.

The accounts in your Watchlist and the setting of the Watchlist toggle on the Customer Growth Dashboard determine which accounts are included in the Customer Growth charts and related pages. The Watchlist toggle affects which account are included in the Customer Growth charts, scores, and account lists. This setting has an impact on the following Producer Portal pages:

- **Customer Growth Dashboard**—Charts, scores, and accounts include just the watched accounts or all accounts. Also, if you have one or more watched accounts, these accounts appear at the top of the list when the Watchlist toggle is set to All Accounts.
- **Accounts Health**—Lists only watched accounts or all accounts.
- **Producer Portal Home**—Charts and scores include just the watched accounts or all accounts.

See [Watching and Unwatching Accounts](#) to see how to add or remove accounts from your Watchlist.

Alerts

The **Customer Growth Dashboard** page also displays a list of alerts, the accounts, and type of alerts. Alerts are only displayed if the watched accounts are selected by clicking the **Watchlist** button. An alert is generated when either a renewal or consumption score crosses a threshold: Healthy, Warning, or At Risk—in either direction.

The alert shows:

- How long ago the alert was triggered
- The score when the alert was triggered
- The type of change, i.e. from Warning to At Risk

Clicking on an alert notice takes you to the Alerts tab for that account and filters the results based the type of alert selected (i.e. Renewal Health or Consumption).

Account Health Pages

In the Producer Portal, you can get lists of your accounts that show the scores for each account. These pages can be searched and filtered in various ways so that you can better track the health of your accounts. You can also see details about a particular account including its specific KPIs, its product consumption, and its renewal health.



Section	Description
Accounts Health Page	Discusses the Accounts Health page and its functionality.
Account Detail Pages	Describes the account detail pages and what information is included on each tab.

Accounts Health Page

The Accounts Health page lists your accounts, and you can filter, sort, and search that list in many different ways. The Accounts Health page is also the best place to watch or unwatch multiple accounts.

- You can sort the list by the account name, the account ID, or by their Consumption, Renewal Health, or Account Health scores.
- You can filter the list by watched/unwatched setting, the score type, and the status condition.
- You can search the list for a particular account by its account name or its account ID.
- On the Accounts Health page, you can also click an account name to see the account details page for that account.

The Accounts Health page shows the following information for each account listed:

Column	Description
Account Name	The account name.
Account ID	Unique identifier of the account.
Products	The number of products to which the account is entitled.
Consumption	Total of all consumed products or licenses or features versus the quantity to which the account is entitled.
Renewal Health	The Renewal Health score is a weighted calculation of days until expiration and the consumption value.
Account Health	The Account Health score is a weighted combination of the other account metrics.
Watchlist	Select the icon to add or remove an account from the Watchlist.  - Unwatched  - Watched

See the section [Visualizing Customer Health](#) for information about filtering and searching account list or viewing details about a particular account.

Account Detail Pages

The account detail pages in the Producer Portal show more detailed information about the health of a particular account. These pages are titled, Account <AccountName>. You get to them by clicking on an account name on the dashboard or on the Accounts Health page.



Tip - You can click Watch on an account's detail page to add it to your Watchlist.

The in-depth information on the account detail page is divided into three tabs:

- **Overview**—shows a summary of health scores for the current account. This tab is the default tab for the account details page.

- **Products**—shows product, feature, and license consumption for the current account.
- **Renewals**—shows the renewal health of each product for which the account is licensed.

Overview Tab

The **Overview** tab is displayed by default. It displays the **Account KPIs** (Key Performance Indicators)—the account health, renewal health, and consumption scores—related to that account. Other tabs include Products and Renewals.

There is also a health meter line graph showing the trends for that health metric. Hover over the points on the graph to see the date and its related health score for that metric.

Products Tab

The **Products** tab to see the list of products for the current account. Products are listed by their consumption scores, and show the current consumed quantity and total available quantity along with the product name and description. Producers can click on the consumed quantity number of any product to see feature consumption details for that product in the current account.

The list contains the following information:

Column	Description
Score	The calculated health score. See Key Performance Indicator (KPI) Scores for details on how this score is derived.
Consumed quantity	The total number of licenses or features that have been consumed. If feature consumption exists, the Producer Portal renders this number as a link.
Total quantity	The sum of all possible features or licenses plus all possible quantities not mapped to a server.
Product name	The name of the product.
Description	A description of the product.

On the Products tab, you can filter the list and view feature-usage details for a particular product. See [Working with the Products Tab on the Account Details Page](#) for instructions.

Renewals Tab

The **Renewals** tab to see the renewal health of each product for which the account has licenses.

The list contains the following information:

Column	Description
Score	A calculated value based the number of days until the product expires and the consumption value. See Key Performance Indicator (KPI) Scores for details on how this score is derived.
Days remaining	The number of days before the license expires.
Expiration	The date the license expires.
Product name	The name of the product.
Type	The type of product. Options include <ul style="list-style-type: none"> • Subscription • Maintenance
Activation ID	The activation ID of the product. Click the Activation ID to see the entitlement details.

On the Renewals tab, you can filter the list and view details for a particular entitlement. See [Working with the Renewals Tab on the Account Details Page](#) for instructions.

Renewals

Producers that issue subscription licenses or perpetual licenses with expiring maintenance typically create additional line items for their existing customers to extend the duration of the customer’s license. When these renewal line items are created, a producer specifies the relationship between the initial subscription or maintenance. Customers can then activate the renewal line item when their existing line item is due to expire.

The FlexNet Customer Growth module brings greater visibility to expiring entitlements and renewals. With this module, the End-User Portal includes a new **Expiring Entitlements** page on which the customer’s entitlements are listed by their expiration date with special emphasis on those that are expired or soon to expire. In addition, the FlexNet Customer Growth module helps producers automate messaging about expiring entitlements to their customers who subscribe to receive renewal reminders.

Separate jobs automate messaging for expiring entitlements and expired entitlements, and producers can customize the content and frequency of the automated messaging.

The following sections cover renewal concepts in greater detail.

Section	Description
Renewal Jobs	Describes the Expiring Entitlements job and the Expired Entitlements job, how they operate, and how they are configured.

Section	Description
Renewal Reminder Email Messages	Describes the renewal notifications FlexNet Operations sends for expiring and expired entitlements and how end users can subscribe to these notifications.
Expiring Entitlements Page	Describes the End-User Portal's Expiring Entitlements page and what features end users can employ there.
More About the Expiring Lines Shown on the Expiring Entitlements Page	Provides a more detailed example to explain how the End-User Portal displays expiring entitlements on the Expiring Entitlements page.
More About How Expiring Lines Are Selected for the Renewal Reminder Email Message	Provides an example to illustrate how FlexNet Operations selects entitlements to include in its renewal reminder email messages.

Renewal Jobs

The automation of renewal messaging hinges on two jobs you administer through the Producer Portal's **Configure Alerts/Jobs** page: the Expiring Entitlements job and the Expired Entitlements job.

Producers can schedule these jobs and subscribe to their alerts in the Producer Portal.

Expiring Entitlements Job

The Expiring Entitlements job finds entitlements that are nearing their expiration date and generates email messages to end user accounts with expiring entitlements.

When the Expiring Entitlements job finds entitlements that are soon to expire for an account, FlexNet Operations generates an email message about that account's expiring entitlements and attempts to send the message to the account's users. End users who elect to receive renewal notifications will get an email message when their account's entitlements are nearing their expiration date.

For producers, a number of system configuration settings determine when email messages are triggered, which entitlements are included in the Renewal Reminder message, whether or not an email is to be sent, and how frequently an account may receive such email messages. Producers can also customize the email template FlexNet Operations uses when it sends these renewal notifications.

Expired Entitlements Job

This job controls how often FlexNet Operations checks for entitlements that have recently expired. When it finds entitlements that have expired since the last time the job was run, it generates email messages to end user accounts with expired entitlements.

When the Expired Entitlements job finds entitlements that are expired for an account, FlexNet Operations generates an email message about that account's expired entitlements and attempts to send the message to the account's users. End users who elect to receive renewal notifications will get an email message when their account's entitlements have expired.

For producers, system configuration settings help determine how frequently an account may receive such email messages as well as which expired entitlements appear in the End-User Portal's **Expiring Entitlements** page. Producers can also customize the email template FlexNet Operations uses when it sends these renewal notifications.

Job Configuration

The operation of these jobs is configurable with both the standard job scheduling controls and with the renewal-specific configuration settings.

Job scheduling controls are the same as those shared by other FlexNet Operations jobs, like the User Deactivated job, the Product/Version Upgrade job, and the numerous data-extract jobs. These controls allow you to set the status of the job (active or inactive), specify the frequency with which the job runs, and limit the subscription to the alerts spawned by the job to specific Producer Portal user roles.

System configuration settings for FlexNet Customer Growth behavior appear on the FlexNet Operations system configuration page (**System > Configure > FlexNet Operations**). These include settings that govern the time ranges the Expiring Entitlements and Expired Entitlements jobs use to determine which entitlements qualify for renewal reminders or expired entitlement messages. System configuration settings also specify email addresses to receive renewal request messages from end users and to receive notifications when there are no end users who have opted to receive expiring entitlements messages.

- In determining when to send an Renewal Reminder email message, FlexNet Operations uses the system configuration settings **Renewal Look Ahead** (default: 200 days), **Expiring Window** (default: 90 days), and **Expiring Email Frequency** (default: 30 days).
- In determining when to send an Expired Entitlements email message, FlexNet Operations uses the system configuration setting, **Expired Email Frequency** (default: 30 days).

For details about these system configuration settings, see the Renewals settings in [Configuring System Settings](#).

Renewal Reminder Email Messages

FlexNet Customer Growth introduces three new email templates.

- **Renewal Reminder**—Used to send Renewal Reminder email messages generated as a result of the Expiring Entitlement job.
- **Renewal Reminder for Expired Entitlements**—Used to send expired entitlement email messages generated as a result of the Expired Entitlements job.
- **Renewal Intent for End Customer**—Used to send intent-to-renew email messages generated when a customer clicks the **Request** button on the **Expiring Entitlements** page in the End-User Portal. FlexNet Operations sends copies of the intent-to-renew message to the end user who clicked the **Request** button and also to the producer at the address specified for the system configuration setting, **Request Renewal Notification Email**.



Tip ▪ For both the renewal reminder messages, end users must meet the following conditions to receive messages:

- An end user must have the *View Expiring Entitlements* permission.
- An end user's account must have **Expiring Entitlements Email** marked in his or her user profile.

Expiring Entitlements Page

The End User Portal includes an **Expiring Entitlements** page (**Activations & Entitlements > Expiring Entitlements**). This page shows the expiring and expired entitlements for the accounts to which the current user belongs and gives special emphasis to those that are soon to expire. (Expired entitlements are not shown by default. End users can use on-page filters in the End-User Portal to include expired entitlements in the list.)



Tip - Lines that expire more than 200 days from the current date are not shown on the **Expiring Entitlements** page. Similarly, when expired entitlements are included, those lines that expired more than 200 days ago are not shown. This limit is configurable on the Producer Portal by changing the value for **Renewal Look Ahead (System > Configure > FlexNet Operations > Renewals)**.

Highlight Colors on the Expiring Entitlements Page

The entitlement lines and maintenance lines closest to their expiration date are highlighted on the **Expiring Entitlements** page.

Producers determine which lines get special emphasis by specifying values for the system configuration settings, **Renewal Critical** (default: 30 days) and **Expiring Window** (default: 90 days). By default, expired lines and lines that expire in the next 30 days are highlighted in red, those that expire between 31 and 90 days are highlighted in yellow, and those that expire further out than 90 days are not highlighted.

End Users Can Send a Renew Request to Producers from the Expiring Entitlements Page

On the End-User Portal's **Expiring Entitlements** page, end users can click a **Request** button to send an email message to the producer about their intent to renew selected entitlements. The intent-to-renew message is generated by the End-User Portal using the default variation of the email template, **Renewal Intent for End Customer**. The End-User Portal sends a copy of this message to the end user who clicked the **Request** button and to the producer at the address specified in the system configuration setting, **Request Renewal Notification Email (System > Configure > FlexNet Operations > Renewals)**.



Important - The intent-to-renew email message is for communication purposes only; FlexNet Operations does not automatically renew the selected entitlements.

More About the Expiring Lines Shown on the Expiring Entitlements Page

FlexNet Operations determines what to show in this page according to the lines' expiration dates, the current date, and the system configuration settings, **Renewal Critical**, **Expiring Window**, and **Renewal Look Ahead**. The graphic below illustrates how three entitlement lines with different expiration dates are shown on the **Expiring Entitlements** page.



Note - The start date and expiration dates shown below are the same as those for the lines used in the exercises in the next section, [Notifying End Users about Expiring Entitlements](#). See [Preparing Entitlement Line Items for Renewal Exercises](#) for more information on these entitlement lines.




Figure 19-2: Entitlement lines shown on the **Expiring Entitlements** page include ACT-01 and ACT-02. ACT-03 expires outside the Renewal Look Ahead range (default: 200 days).

The **Expiring Entitlements** page lists all the entitlement and maintenance lines to which the end user is entitled and that are due to expire within the Renewal Look Ahead range (default: 200 days from the current date). This page also highlights lines with different background colors if their expiration dates fall within the Renewal Critical (default: 30 days) or the Expiring Window (default: 90 days).

- ACT-01 expires on 7 May 2017, which occurs within the Renewal Critical range (default: 30 days). Therefore, it appears on the **Expiring Entitlements** page and is highlighted in red to indicate it is 30 days or fewer until its expiration date.
- ACT-02 expires on 7 August 2017, which occurs outside the Renewal Critical range and outside of the Expiration Window range (default: 90 days). Therefore, it appears on the **Expiring Entitlements** page but is not highlighted. (If its expiration date fell within 30-90 days from the current date, it would have a yellow highlight to indicate its expiration date fell within the Expiring Window.)
- ACT-03 expires on 7 November 2017. Because its expiration date happens outside the Renewal Look Ahead range (default: 200 days), it is not shown on the **Expiring Entitlements** page. (There are 204 days between 17 April 2017 and 7 November 2017. If its expiration date fell within the Renewal Look Ahead range, this line would be included on the **Expiring Entitlements** page.)

More About How Expiring Lines Are Selected for the Renewal Reminder Email Message

FlexNet Operations determines what to include in the renewal reminder about expiring entitlements based on the lines' expiration dates, the date the Expiring Entitlements job runs, and the system configuration settings, **Expiring Window**, and **Renewal Look Ahead**. The graphic below illustrates how three entitlement lines with different expiration dates are shown on the **Expiring Entitlements** page.



Note - The start date and expiration dates shown below are the same as those for the lines used in the exercises in the next section, [Notifying End Users about Expiring Entitlements](#). See [Preparing Entitlement Line Items for Renewal Exercises](#) for more information on these entitlement lines.




Figure 19-3: When a renewal reminder is generated for expiring entitlements, that email message includes entitlement lines and maintenance lines that expire within the Expiring Window (default: 90 days) as well as any that are due to expire within the Renewal Look Ahead range (default: 200 days).

The renewal reminder message lists all the entitlement and maintenance lines to which the end user is entitled and that are due to expire within the Renewal Look Ahead range (default: 200 days from the current date). Given the expiring entitlement lines ACT-01, ACT-02, and ACT-03, a renewal reminder generated on 17 April 2017 would include ACT-01 and ACT-02:

- ACT-01 expires on 7 May 2017, which occurs within the Expiring Window (default: 90 days), and causes the Expiring Entitlements job to begin the generation of the renewal reminder message. It is included in the renewal reminder email message.

- ACT-02 expires on 7 August 2017, which occurs outside the Expiring Window but within the Renewal Look Ahead range (default: 200 days). Therefore, it does not expire soon enough to cause the FlexNet Operations to generate a renewal reminder email message but it is included in the list of expiring entitlement lines.
- ACT-03 expires on 7 November 2017. Because its expiration date happens outside the Renewal Look Ahead range, it is excluded from the renewal reminder email message. (There are 204 days between 17 April 2017 and 7 November 2017. If its expiration date fell within the Renewal Look Ahead range, this line would be included in the renewal reminder.)

Additional information about the processing of the Expiring Entitlements job appears in the section [More About the Expiring Entitlements Job](#). Likewise, you can find information about the Expired Entitlements job in [More About the Expired Entitlements Job](#).

Next Steps

The next section, [Visualizing Customer Health](#), provides instructions for navigating to the Customer Growth Dashboard and Accounts Health pages, filtering and otherwise manipulating page content, and viewing the account details for a particular account.

The renewal exercises in this getting started section walk through the processes of setting up renewals and seeing the results of the renewal jobs in the End-User Portal and in email messaging.

- [Notifying End Users about Expiring Entitlements](#)
- [Notifying End Users about Expiring Entitlements](#)

To learn more about handling the dashboard and account health pages, continue reading the next section. To get started with the renewal exercises, skip ahead to [Notifying End Users about Expiring Entitlements](#).

Visualizing Customer Health

This section provides brief instructions for viewing the Customer Growth pages on the Producer Portal and managing the content there.

Section	Description
Viewing the Customer Growth Dashboard	Describes how to see the Customer Growth Dashboard.
Toggling Between All Accounts and the Watchlist	Explains how to set the Watchlist Toggle to show all accounts or only watched accounts.
Viewing the Accounts Health Page	Describes how to see the Accounts Health page.
Filtering the Accounts Health List	Explains how to filter the account list on the Accounts Health page.
Searching the Accounts Health List	Explains how to search the account list on the Accounts Health page.
Watching and Unwatching Accounts	Explains how to add or remove accounts from the Watchlist.

Section	Description
Viewing Account Details	Shows how to view the account details page for an account listed on the Accounts Health page.
Working with the Products Tab on the Account Details Page	Discusses how to filter the products list and see feature-consumption details for a particular product on the Products tab.
Working with the Renewals Tab on the Account Details Page	Discusses how to filter the entitlements list and view details for a particular entitlement on the Renewals tab.
Next Steps	Briefly discusses how to proceed in this getting started section according to your own needs and interests.

Viewing the Customer Growth Dashboard

You can view the dashboard using the Producer Portal menus.



Task *To view the Customer Growth Dashboard*

- In the Producer Portal, click **Accounts & Users > Dashboard**.

The Producer Portal shows the Customer Growth Dashboard for all accounts or for watched accounts, depending on your current Watchlist Toggle setting.

For more information about the dashboard page features, see [The Customer Growth Dashboard](#).

Toggling Between All Accounts and the Watchlist

You can use the Watchlist Toggle to configure the Producer Portal to show either all accounts or only watched accounts. This control affects the content of the dashboard page, the Accounts Health page, and the health charts on the Producer Portal home page.



Task *To show all accounts*

- On the Customer Growth Dashboard, click **All Accounts**.

The Customer Growth components include data for all accounts.



Task *To show Watchlist accounts*

- On the Customer Growth Dashboard, click **Watchlist**.

The Customer Growth components include data only for watched accounts.

To learn more about the Watchlist feature, see [Watched and Unwatched Accounts](#).

Viewing the Accounts Health Page

You can view the Accounts Health page using the Producer Portal menus.



Task To view Accounts Health page

- In the Producer Portal, click **Accounts & Users > Accounts**.

See [Accounts Health Page](#) for more information about the content of this page.

See [Filtering the Accounts Health List](#) and [Searching the Accounts Health List](#) for instructions on how to work with the lists on these tabs.


See [Watching and Unwatching Accounts](#) for instructions on how to add or remove accounts from your Watchlist.

Filtering the Accounts Health List

By default, the account list defaults to display all account types (watched and unwatched) by their account health score and shows accounts with any health condition (At Risk, Warning, or Healthy). To quickly reduce the number of accounts listed on the Accounts Health page, filter it by type, score and health condition.



Task To filter the accounts list

1. On the **Accounts Health** page, hover the cursor over the  filter icon to display the filter selection list.
2. To change the default filter setting, do one of the following:

- **Type:** Check **Watched Accounts** to only view accounts on the Watchlist.
- **Score:** Uncheck the **Account Health** and check either **Renewal Health** or **Consumption**.



Note - At least one of the scores must be selected: Account Health, Renewal Health or Consumption. Only one score can be checked at a time.

- **Condition:** Uncheck one or more of the conditions.



Note - If all the conditions are unchecked, the Producer Portal behaves as if all conditions are checked. (Accounts with all health conditions are shown.)

3. Click **Apply**.

The Producer Portal shows the account list with the new filter settings applied. Notice that the number in the red bubble indicates how many filters are active.

Searching the Accounts Health List

You can search the account list on the Accounts Health page.



Task **To search the accounts list**

1. On the Accounts Health page, choose what to search for. Use the menu to search by **Account name** or **Account ID**.
2. Enter your search criteria.
3. Click **Search**.

The Accounts Health list shows accounts that match your search criteria.

Watching and Unwatching Accounts

You can add or remove accounts from the Watchlist using the controls on the Accounts Health page.



Task **To add an account to your Watchlist**

- On the Accounts Health page, click the Watch icon for that account.

The Producer Portal adds the account to your Watchlist.



Task **To remove an account from your Watchlist**

- On the Accounts Health page, click the Unwatch icon for that account.

The Producer Portal removes the account from your Watchlist.

To learn more about the Watchlist feature, see [Watched and Unwatched Accounts](#).

Viewing Account Details

You can view details about a particular account from the Accounts Health page.



Task **To view account details**

- On the **Accounts Health** page, click the account name of the account for which you want to view.

See [Account Detail Pages](#) for more information about the content of this page and its Overview, Products, and Renewals tabs.

See [Working with the Products Tab on the Account Details Page](#) and [Working with the Renewals Tab on the Account Details Page](#) for instructions on how to work with the lists on these tabs and get more information about the renewal conditions of entitlements or feature consumption for the current account's products.



Tip ▪ You can add or remove an account from the Watchlist by clicking the **Watch** or **Unwatch** button on the account details page.



Tip - Click the **Back to List** link to go to the **Accounts Health** page.

Working with the Products Tab on the Account Details Page

On the account details page's Products tab, you can filter and search the product list. You can also view feature consumption for a product listed on the Products tab and filter the results in that feature list.

See instructions for these activities in the sections below:

- [Filtering the Product List](#)
- [Searching the Products List](#)
- [Viewing Feature Consumption](#)
- [Filtering the Feature Consumption List](#)

Filtering the Product List


Follow the steps, below, to change the filter settings for the product list.

By default the **Products** tab filter values are set to display the product health score with all conditions: **At risk**, **Warning**, or **Healthy**.



Task

To filter the products list

1. On the **Products** tab, hover the cursor over the  filter icon to display the filter selection list.
2. To change the default filter setting, uncheck one or more of the conditions.
3. Click **Apply**.

Notice that the number in the red bubble indicates how many filters are active. If all the condition boxes are cleared, the Producer Portal warns that at least one condition must be checked.

You can also sort the products list by score (default), consumed quantity, or total quantity.

Searching the Products List

You can search the list of products on the Products tab of account details pages.



Task

To search the products list

1. On the account details page, choose what to search for. Use the menu to search by **Product Name** or **Description**.
2. Enter your search criteria.
3. Click **Search**.

The shows products that match your search criteria.

Viewing Feature Consumption

Follow the steps, below, to see feature consumption details for a product.



Task

To view Feature Consumption

- Click the **Consumed quantity** value for a product in the product list to see its **Feature Consumption** details.

The **Feature Consumption** window displays the consumption of features attached to the current product, if there are any. Any feature with an embedded license model, and mapped to a license server, is included in the consumption numbers.


Filtering the Feature Consumption List

Follow the steps, below, to filter settings for the feature list. By default the **Feature Consumption** window filter is set to display the feature health score for products with all condition values: **At risk**, **Warning**, and **Healthy**.



Task

To filter the feature list

1. In the **Feature Consumption** window, hover the cursor over the  filter icon to display the filter selection list.
2. Check the check boxes for the status, types, and conditions you want to show.
3. Click **Apply**.

Notice that, for the filter, the number in the red bubble indicates how many filters are active. If all the condition boxes are unchecked, the Producer Portal warns that at least one condition must be checked.

You can also search a filtered feature list. Use the menu to target your search to for a feature by **Name** or **Description**.

Working with the Renewals Tab on the Account Details Page

You can filter and search the entitlements list on the Renewals tab. You can also view details about the entitlements listed on this tab.

See instructions for these activities in the sections below:


- [Filtering the Renewal Health List](#)
- [Searching the Renewal Health List](#)
- [Viewing Entitlement Details](#)

Filtering the Renewal Health List

Follow the instructions below to filter the renewals list. By default the filter for this page includes all types, status values, and conditions except **Expired**. Therefore, the renewals list includes products in all conditions, **At risk**, **Warning**, and **Healthy**; with types, **Subscription** and **Maintenance**; and with a status of **Expiring**.



Task To filter the renewals list

1. On the **Renewals** tab, hover the cursor over the  filter icon to display the filter selection list.
2. Select the check boxes for the status values, types, and conditions you want to show.
3. Click **Apply**.

Notice that, for the filter, the number in the red bubble indicates how many filters are active. If all the status boxes are unchecked, the Producer Portal warns that at least one status must be checked. If all the types are unchecked, the filter behaves as if all types are checked.

You can also sort the entitlements list by score (default), days remaining, expiration date, or product name.

Searching the Renewal Health List

You can search the list of entitlements on the Renewals tab of account details pages.



Task To search the entitlements list

1. On the account details page, choose what to search for. Use the menu to search by **Product name** or **Activation ID**.
2. Enter your search criteria.
3. Click **Search**.

The shows entitlements that match your search criteria.

Viewing Entitlement Details

Follow the instructions below to view entitlement details for an entitlement on the Renewals tab.



Task To view Entitlement details

- Click on the **Activation ID** to open the **Entitlement Details** window.

The **Entitlement Details** window displays the information for a particular entitlement including ID information (Entitlement ID, state, sold-to, description and activation ID), the name and description of the products with which the entitlement is associated, and the activation information.

Next Steps

The next two sections provide exercises for working with expiring entitlements and expired entitlements—from setting up the necessary entitlements and configuring FlexNet Operations to viewing entitlements in the End-User Portal and receiving notifications.

For expiring entitlements notifications, see [Notifying End Users about Expiring Entitlements](#).

For expired entitlements notifications, see [Notifying End Users about Expiring Entitlements](#).

Notifying End Users about Expiring Entitlements

This section walks through the process of configuring FlexNet Operations to send renewal reminders to end users who have expiring entitlements. In these exercises, you use the account, user, product, and entitlement created in the early exercises of the section [Getting Started with Entitlement Management](#), and add expiring and renewal line items to see how the job operates.

Remember to check the prerequisites in the Introduction before starting these exercises. See [Exercise Prerequisites](#).

Topic	Description
Preparing Entitlement Line Items for Renewal Exercises	Creates three line items on ENT-PhototPrint to illustrate how the FlexNet Customer Growth module enhances the handling of and communication about expiring entitlements.
Activating the Renewal Email Templates	For notifications about expiring entitlements, producers must have the following email templates in active status: Renewal Reminder and Renewal Intent for End Customer . This exercise walks you through that process.
Setting Up the Job	This exercise activates and schedules the Expiring Entitlements job.
Viewing the Expiring Entitlements Page and Receiving Renewal Notifications	To understand what is sent to the end user, this exercise uses an end-user account to see the entitlements approaching their expiration dates on the Expiring Entitlements page, see the emailed renewal notification for those entitlements, and send a request to renew selected entitlements to the producer.
Next Steps	Discusses the possibilities of moving on to the exercises for notifying users about expired entitlements or reading more about viewing sent emails in the Producer Portal, customizing email templates, and configuring jobs schedules and subscriptions.

Preparing Entitlement Line Items for Renewal Exercises

As you start the exercises in this section, take a moment to review the product, entitlement, and other entities you created in the section [Getting Started with Entitlement Management](#). Then, for the exercises in this section, create three line items on ENT-PhototPrint.

Starting Account, User, Product, Product Line, and Entitlement

Remember that these exercises start with the expectation that you have already completed the exercises in the section [Getting Started with Entitlement Management](#), and have continuing access to the system on which those entities were defined. In those exercises, you create the following entities:

Entity Type	Entities
Customer Account	Barry Photography Studio
Customer User	Lisa Barry
Product	<p>PhotoPrint</p> <p>This product includes the following features:</p> <ul style="list-style-type: none"> • Print • PrintHighQualityColor • PrintToPDF <p>As indicated in the section Getting Started with Entitlement Management, the features, above, are among those pre-defined in your environment's demo data.</p>
Product Line	LargeFormat
Entitlement	ENT-PhotoPrint

If these entities, such as the entitlement, ENT-PhotoPrint, do not yet exist in your FlexNet Operations instance, be sure you have loaded the demo data; then follow the exercises in the section [Getting Started with Entitlement Management](#) to create the necessary entities.



Tip • Take a moment to verify that the user profile for Lisa Barry has the check box for **Expiring Entitlements Email** selected. To verify this in the End-User Portal, log in and click the user name, **Lisa Barry**, at the top right of the page, and then click **Profile**. (If the user profile page does not show the **Expiring Entitlements Email** check box, then Lisa Barry may still need to be granted the **View Expiring Entitlements** permission.)



Important • If the customer user, Lisa Barry, already exists but is not associated with an email address you control, you must create another customer user in the Barry Photography Studio account with the Portal User role. Use an email address you control for this new user so that you will be able to use that user account to log in to the End-User Portal and see the downloads.

Create the New Line Items

To illustrate FlexNet Customer Growth module feature, you must create three line items: one that is nearly expired, one that expires within the Renewal Look Ahead window, and one that expires on a date that falls outside the Renewal Look Ahead time frame. (See [Renewal Jobs](#) for more information about the system configuration settings and how they affect the Expiring Entitlements job.)



Task *To create the new line items*

1. In the Producer Portal, find ENT-PhotoPrint.
 - a. Click **Entitlements > List Entitlements by Order**.
 - b. On the List Entitlements by Order page, search for **ENT-PhotoPrint**.
2. On the Entitle Customers to Licenses page for ENT-PhotoPrint, create three new line items:
 - ACT-PhotoPrint-01
 - ACT-PhotoPrint-02
 - ACT-PhotoPrint-03

Use the following settings for these line items:

ACT-PhotoPrint-01

Attribute	Value
Product	PhotoPrint
License Model	NodeLocked Uncounted
Qty	1
Start Date	Expiration date minus three months
Expiration Date	Current date plus twenty days
Activation ID	ACT-PhotoPrint-01

ACT-PhotoPrint-02

Attribute	Value
Product	PhotoPrint
License Model	NodeLocked Uncounted
Qty	1
Start Date	Current date plus twenty days
Expiration Date	Start date plus three months
Activation ID	ACT-PhotoPrint-02

ACT-PhotoPrint-03

Attribute	Value
Product	PhotoPrint
License Model	NodeLocked Uncounted
Qty	1
Start Date	Current date plus three months and twenty days
Expiration Date	Start date plus three months
Activation ID	ACT-PhotoPrint-03

For example, if the current date is 17 April 2017, you have the following line items in ENT-PhotoPrint:

- ACT-PhotoPrint-01—starts on 7 February 2017; ends on 7 May 2017.
- ACT-PhotoPrint-02—starts on 7 May 2017; ends on 7 August 2017.
- ACT-PhotoPrint-03—starts on 7 August 2017; ends on 7 November 2017.

3. Click **Save & Deploy** to update ENT-PhotoPrint with the new line items.

With these entitlement lines in place, we can activate the renewal-related email templates and setup the Expiring Entitlements job to see how the FlexNet Customer Growth module operates to highlight expiring entitlements and automate the communication about renewal opportunities to your end users.

Activating the Renewal Email Templates

In this exercise, you activate the Renewal Reminder and Renewal Intent for End Customer email templates.

- The Renewal Reminder template is used by FlexNet Operations to send email messages to end users about their expiring entitlements. (A separate email template is used for expired entitlements as identified by the Expired Entitlements job.) The default version of this template lists all the account's entitlements that are due to expire within the Renewal Look Ahead window.
- The Renewal Intent for End Customers template is used by FlexNet Operations to send intent-to-renew email messages when an end user selects an expiring entitlement and clicks the **Request** button on the End-User Portal's **Expiring Entitlements** page.

If these templates are not already in an active status, follow the instructions below to activate them.



Task To activate the Renewal Reminder email template

1. In the Producer Portal, click **Administer > Templates**.
2. On the Templates page, find the **Renewal Reminder** template and click its **Template ID**.
3. On the View Email Template page, click **Edit > Edit Active Content**.

4. Click **Validate Template**.
5. Click **Save Active**.

This activates the Renewal Reminder template. Repeat these steps for the Renewal Intent for End Customer template.

When both email templates are active, you are ready to setup the Expiring Entitlements job.

Setting Up the Job

The Expiring Entitlements job drives the notification process for the renewal reminders about expiring entitlements. In this exercise, you activate and schedule the Expiring Entitlements job.



Task *To set up the Expiring Entitlements job*

1. In the Producer Portal, click **Administer > Configure Alerts/Jobs**. This link opens the **Configure Alerts/Jobs** page.
2. On the **Configure Alerts/Jobs** page, click the **Configure** button for the Expiring Entitlements job. This button opens the Configure Alert/Job Schedule for the Expiring Entitlements job.
3. Set **Status** to **Active** and keep the default schedule (30 days).
4. Click **Save**.

The Producer Portal saves your job configurations and returns to the **Configure Alerts/Jobs** page.

The Expiring Entitlements job is now active and set to run once every 30 days.

Using the default job schedule and the default system configuration settings for renewal settings, FlexNet Operations checks for expiring entitlements once every 30 days and sends renewal reminders to subscribed users in accounts with one or more entitlements that expire in the next 90 days (Expiring Window). And, when assembling the renewal reminder email, FlexNet Operations includes a list of all entitlements for that account that are due to expire within the next 200 days (Renewal Look Ahead).

With the renewal email templates active, the Expiring Entitlements job can send renewal reminders to end users and to send intent-to-renew email messages from the End-User Portal's **Expiring Entitlements** page.

Viewing the Expiring Entitlements Page and Receiving Renewal Notifications

With the Expiring Entitlements job activated, you can log in to the End-User Portal as Lisa Barry and review the contents of the **Expiring Entitlements** page. In addition, FlexNet Operations has sent Lisa Barry a renewal reminder about those entitlements due to expire in the next 200 days. After logging in to the End-User Portal as Lisa Barry, you can also send a renewal request message from her right from the **Expiring Entitlements** page.

- [Viewing the Expiring Entitlements Page](#)
- [Viewing the Renewal Notification](#)
- [Sending a Renewal Request from the End-User Portal](#)



Tip - Remember that Lisa Barry is the end user account for these exercises. If you are using a different end user for these exercises, log in as that user.

Viewing the Expiring Entitlements Page

The End-User Portal's **Expiring Entitlements** page shows two of the three line items you created at the start of these exercises.

In order to see the **Expiring Entitlements** page, the end user account must have the View Expiring Entitlements permission. Otherwise, there is no link to the **Expiring Entitlements** page in the End-User Portal.



Task To view the Expiring Entitlements page

1. Log in to the End-User Portal using the credentials for Lisa Barry.
2. In the End-User Portal, click **Activation & Entitlements > Expiring Entitlements**.

Notice that the **Expiring Entitlements** page shows the line items ACT-PhotoPrint-01 and ACT-PhotoPrint-02. ACT-PhotoPrint-03 does not appear because its expiration date is outside the Renewal Look Ahead window—greater than 200 days in this case.

The screenshot shows the 'Expiring Entitlements' page with a 'Request' button and a table of results. The table has columns for Total quantity, Days remaining, Expiration, Product, Version, Activation ID, Type, and Account. Two results are shown: ACT-PhotoPrint-01 (20 days remaining, expires May 7, 2017) and ACT-PhotoPrint-02 (112 days remaining, expires Aug 7, 2017).

	Total quantity	Days remaining	Expiration	Product	Version	Activation ID	Type	Account
<input type="checkbox"/>	1	20	May 7, 2017	PhotoPrint	12.0	ACT-PhotoPrint-01	Subscription	Barry Photography Studio
<input type="checkbox"/>	1	112	Aug 7, 2017	PhotoPrint	12.0	ACT-PhotoPrint-02	Subscription	Barry Photography Studio

Figure 19-4: The **Expiring Entitlements** page shows the line items that meet requirements expressed in the Renewal settings in the FlexNet Operations system configurations.

Viewing the Renewal Notification

When the Expiring Entitlements job runs, it finds ACT-PhotoPrint-01 within the Expiring Window. It then looks for any line items in Barry Photography Studio that are expiring within the Renewal Look Ahead window (200 days from the current date) and finds ACT-PhotoPrint-02. It includes both line items in the renewal reminder message and sends it to the end user, Lisa Barry, because she has opted in to receive expiring entitlements email messages.



Task To view the renewal notification email message

Log in to the email account you set up for Lisa Barry, and open the Renewal Reminder message.




Figure 19-5: A sample renewal reminder email message showing the two line items that are included by the Expiring Entitlementment job (ACT-PhotoPrint-01 and ACT-PhotoPrint-02). ACT-PhotoPrint-03 is not included because its expiration date is further away than 200 days.

In order to receive renewal reminder email messages, the end user must have the Expiring Entitlements Email check box selected on their user profile. And to see that check box, the end user must have the View Expiring Entitlements permission.



Tip - Another way to verify that FlexNet Operations has sent an renewal reminder is to check the **Sent Messages** page in the Producer Portal. To do so, click **Administer** > **Sent Emails**.

Sending a Renewal Request from the End-User Portal

When you have a valid email address specified in the Producer Portal system configuration setting, Request Renewal Notification Email, the **Expiring Entitlements** page in the End-User Portal includes a **Request** button. End users can click the **Request** button to send an email message to that address when they see entitlements on the **Expiring Entitlements** page they want to renew.



Task To set a Request Renewal Notification Email address

1. In the Producer Portal, open the system configuration page for FlexNet Operations and show the Renewals group.
 - a. Click **System** > **Configure** > **FlexNet Operations**.
 - b. Expand the **Renewals** settings on the FlexNet Operations system configuration page.
2. In the Renewals settings find **Request Renewal Notification Email** and enter an email address for an email account at which you can receive messages.
3. Click **Save Configs**.

If you log in, again, to the End-User Portal as Lisa Barry and refresh the End-User Portal's **Expiring Entitlements** page, the **Request** button appears above the list of entitlements.



Task *To send a renewal request from the Expiring Entitlements page*

1. In the End-User Portal, click **Activation & Entitlements > Expired Entitlements**. This link opens or re-opens the **Expiring Entitlements** page that now shows the **Request** button.
2. Select the check box to select ACT-PhotoPrint-01.
3. Click **Request**.

The End-User Portal sends an email message to the address you specified for Request Renewal Notification Email using the Renewal Request for End Customer email template.

For end users, it reports the result of this process in a message on the **Expiring Entitlements** page. For producers, a message is sent to the Request Renewal Notification Email address. (Check your email account to see the resulting email message or check the Sent Messages page in the Producer Portal.)

Next Steps

While the Expiring Entitlements job sends email messages about line items and maintenance lines that are approaching their expiration date, the Expired Entitlements job sends email messages about line items and maintenance lines that have already expired. To walk through the process of setting up the Expired Entitlements job to send messages about those entitlements, see [Notifying End Users about Expiring Entitlements](#).

Consider also reading [Managing Email Templates](#) to learn about how to customize email templates. For instance, you may want to apply your account's branding to the Renewal Reminder email template or alter the message content in the Renewal Intent for End Customer email template.

Producer administrators may also be interested in customizing the job schedule for FlexNet Operations background jobs and subscribing to the alerts that are generated when such jobs run. For more information, see [Administering Alerts](#).

Notifying End Users About Expired Entitlements

This section walks through the process of configuring FlexNet Operations to send renewal reminders to end users who have expired entitlements. In these exercises, you use the account, user, product, and entitlement created in the early exercises of the section [Getting Started with Entitlement Management](#), and add expired line items to see how the job operates.

Remember to check the prerequisites in the Introduction before starting these exercises. See [Exercise Prerequisites](#).

Topic	Description
Preparing Entitlement Line Items for Renewal Exercises	Creates three line items on ENT-PhototPrint, including one that has recently expired. These line items are essential to illustrate how the FlexNet Customer Growth module enhances the handling of and communication about expired entitlements.
Activating the Renewal Email Templates	For notifications about expired entitlements, producers must have the following email templates in active status: Renewal Reminder for Expired Entitlements and Renewal Intent for End Customer . This exercise walks you through that process.
Setting Up the Job	This exercise activates and schedules the Expired Entitlements job.
Viewing the Expiring Entitlements Page and Receiving Renewal Notifications	To understand what is sent to the end user, this exercise uses an end-user account to see entitlements that have passed their expiration dates on the Expiring Entitlements page, see the emailed renewal reminder about those entitlements, and send a request to renew selected entitlements to the producer.
Next Steps	Discusses additional concepts related to sending expired entitlement messages—such as viewing sent emails in the Producer Portal, customizing email templates, and configuring jobs schedules and subscriptions—and where to find more information about them.

Preparing Entitlement Line Items for Renewal Exercises

If you have not already done so in the previous section, take a moment to review the product, entitlement, and other entities you created in the section [Getting Started with Entitlement Management](#). Then, create three line items used in these exercises on the entitlement, ENT-PhototPrint.

Starting Account, User, Product, Product Line, and Entitlement

Remember that these exercises start with the expectation that you have already completed the exercises in the section [Getting Started with Entitlement Management](#), and have continuing access to the system on which those entities were defined. In those exercises, you create the following entities:

Entity Type	Entities
Customer Account	Barry Photography Studio
Customer User	Lisa Barry

Entity Type	Entities
Product	<p>PhotoPrint</p> <p>This product includes the following features:</p> <ul style="list-style-type: none"> ● Print ● PrintHighQualityColor ● PrintToPDF <p>As indicated in the section Getting Started with Entitlement Management, the features, above, are among those pre-defined in your environment's demo data.</p>
Product Line	LargeFormat
Entitlement	ENT-PhotoPrint

If these entities, such as the entitlement, ENT-PhotoPrint, do not yet exist in your FlexNet Operations instance, be sure you have loaded the demo data; then follow the exercises in the section [Getting Started with Entitlement Management](#) to create the necessary entities.



Tip • Take a moment to verify that the user profile for Lisa Barry has the check box for **Expiring Entitlements Email** selected. To verify this in the End-User Portal, log in and click the user name, **Lisa Barry**, at the top right of the page, and then click **Profile**. (If the user profile page does not show the **Expiring Entitlements Email** check box, then Lisa Barry may still need to be granted the **View Expiring Entitlements** permission.)



Important • If the customer user, Lisa Barry, already exists but is not associated with an email address you control, you must create another customer user in the Barry Photography Studio account with the Portal User role. Use an email address you control for this new user so that you will be able to use that user account to log in to the End-User Portal and see the downloads.

Create the New Line Items

To illustrate FlexNet Customer Growth module feature, you must create a line item that is just past its expiration date plus a second line item that expired sometime within the Expiring Window. A third line item expires well outside the default Expiring Window and, as a result, is not included in the renewal reminder. (See [Renewal Jobs](#) for more information about the system configuration settings and how they affect the Expired Entitlements job.)



Task

To create the new line items

- In the Producer Portal, find ENT-PhotoPrint.
 - Click **Entitlements > List Entitlements by Order**.
 - On the List Entitlements by Order page, search for **ENT-PhotoPrint**.
- On the Entitle Customers to Licenses page for ENT-PhotoPrint, create three new line items:

- ACT-PhotoPrint-11
- ACT-PhotoPrint-12
- ACT-PhotoPrint-13

Use the following settings for these line items:

ACT-PhotoPrint-11

Attribute	Value
Product	PhotoPrint
License Model	NodeLocked Uncounted
Qty	1
Start Date	Current date minus three months
Expiration Date	Yesterday's date
Activation ID	ACT-PhotoPrint-11

ACT-PhotoPrint-12

Attribute	Value
Product	PhotoPrint
License Model	NodeLocked Uncounted
Qty	1
Start Date	Current date minus six months
Expiration Date	Current date minus three months
Activation ID	ACT-PhotoPrint-12

ACT-PhotoPrint-13

Attribute	Value
Product	PhotoPrint
License Model	NodeLocked Uncounted
Qty	1
Start Date	Current date minus nine months

Attribute	Value
Expiration Date	Current date minus six months
Activation ID	ACT-PhotoPrint-13

For example, if the current date is 20 April 2017, you have the following line items in ENT-PhotoPrint:

- ACT-PhotoPrint-11—started on 20 January 2017; ended on 19 April 2017.
- ACT-PhotoPrint-12—started on 20 October 2016; ended on 20 January 2017.
- ACT-PhotoPrint-13—started on 20 July 2016; ended on 20 October 2016.

3. Click **Save & Deploy** to update ENT-PhotoPrint with the new line items.

With these entitlement lines in place, we can activate the renewal-related email templates and setup the Expired Entitlements job to see how the FlexNet Customer Growth module operates to highlight expired entitlements and automate the communication about renewal opportunities to your end users.

Activating the Renewal Email Templates

In this exercise, you activate the Renewal Reminder for Expired Entitlements email template and Renewal Intent for End Customer email template.

- The Renewal Reminder for Expired Entitlements template is used by FlexNet Operations to send email messages to end users about their expired entitlements. (This is a separate email template from the one used for expiring entitlements identified by the Expiring Entitlements job.) The default version of this template lists all the account's entitlements that have expired within the days specified for the system configuration setting, Expiring Window.
- The Renewal Intent for End Customer template is used by FlexNet Operations to send intent-to-renew email messages when an end user selects an entitlement and clicks the **Request** button on the End-User Portal's **Expiring Entitlements** page.

If these templates are not already in an active status, follow the instructions below to activate them.



Task To activate the Renewal Reminder for Expired Entitlements email template

1. In the Producer Portal, click **Administer > Templates**.
2. On the Templates page, find the **Renewal Reminder for Expired Entitlements** template and click its **Template ID**.
3. On the View Email Template page, click **Edit > Edit Active Content**.
4. Click **Validate Template**.
5. Click **Save Active**.

This activates the template. Repeat these steps for the Renewal Intent for End Customer template, if necessary.

When both email templates are active, you are ready to setup the Expired Entitlements job.

Setting Up the Job

The Expired Entitlements job drives the notification process for renewal reminders for expired entitlements. In this exercise, you activate and schedule the Expired Entitlements job.



Task *To set up the Expired Entitlements job*

1. In the Producer Portal, click **Administer** > **Configure Alerts/Jobs**. This link opens the **Configure Alerts/Jobs** page.
2. On the **Configure Alerts/Jobs** page, click the **Configure** button for the Expired Entitlements job. This button opens the Configure Alert/Job Schedule for the Expired Entitlements job.
3. Set **Status** to **Active** and keep the default schedule (30 days).
4. Click **Save**.

The Producer Portal saves your job configurations and returns to the **Configure Alerts/Jobs** page.

The Expired Entitlements job is now active and set to run once every 30 days.

Using the default job schedule and the default system configuration settings for renewal settings, FlexNet Operations checks for expired entitlements once every 30 days and sends renewal reminders to subscribed users in accounts with one or more entitlements that have expired since the last time an email message was sent for expired entitlements. And, when assembling the expired entitlements email, FlexNet Operations includes a list of all entitlements for that account that have expired.

With the renewal email templates active, the Expired Entitlements job can send renewal reminders to end users and end users can send intent-to-renew email messages from the End-User Portal's **Expiring Entitlements** page.

Viewing the Expiring Entitlements Page and Receiving Renewal Notifications

With the Expired Entitlements job activated, you can log in to the End-User Portal as Lisa Barry and review the contents of the **Expiring Entitlements** page. In addition, FlexNet Operations has sent Lisa Barry a renewal reminder about those entitlements that expired in the last 90 days. After logging in to the End-User Portal as Lisa Barry, you can also send a renewal request message from her right from the **Expiring Entitlements** page.

- [Viewing the Expiring Entitlements Page](#)
- [Viewing the Renewal Notification](#)
- [Sending a Renewal Request from the End-User Portal](#)



Tip • Remember that Lisa Barry is the end user account for these exercises. If you are using a different end user for these exercises, log in as that user.

Viewing the Expiring Entitlements Page

The End-User Portal's **Expiring Entitlements** page shows two of the three line items you created at the start of this section's exercises.

In order to see the **Expiring Entitlements** page, the end user account must have the View Expiring Entitlements permission. Otherwise, there is no link to the **Expiring Entitlements** page in the End-User Portal.



Task **To view the Expiring Entitlements page**

1. Log in to the End-User Portal using the credentials for Lisa Barry.
2. In the End-User Portal, click **Activation & Entitlements > Expiring Entitlements**.

Notice that the **Expiring Entitlements** page shows the expired line items ACT-PhotoPrint-11, ACT-PhotoPrint-12, and ACT-PhotoPrint-13. (Line items that expired more than 200 days ago do not appear because that span exceeds the default Renewal Look Ahead setting of 200 days.)



Tip ▪ The default filter settings on the **Expiring Entitlements** page prevents the page from showing expired entitlements. If you do not see expired entitlements on the page, use the on-page filter controls to include expired entitlements. (Select the **Expired** check box in the filter to include expired entitlements.)

Viewing the Renewal Notification

When the Expired Entitlements job runs, it finds ACT-PhotoPrint-11, ACT-PhotoPrint-12, and ACT-PhotoPrint-13 have expired. It includes all three line items in the renewal reminder message and sends it to the end user, Lisa Barry, because she has opted in to receive expired entitlements email messages.



Task **To view the renewal notification email message**

- Log in to the email account you set up for Lisa Barry, and open the Renewal Reminder message.

In order to receive renewal reminder email messages, the end user must have the Expiring Entitlements Email check box selected on their user profile. And to see that check box, the end user must have the View Expiring Entitlements permission.



Tip ▪ Another way to verify that FlexNet Operations has sent an renewal reminder is to check the Sent Messages page in the Producer Portal. To do so, click **Administer > Sent Emails**.

Sending a Renewal Request from the End-User Portal

When you have a valid email address specified in the Producer Portal system configuration setting, Request Renewal Notification Email, the **Expiring Entitlements** page in the End-User Portal includes a **Request** button. End users can click the **Request** button to send an email message to that address when they see entitlements on the **Expiring Entitlements** page they want to renew. (If you have already completed the exercises in the previous section, then the Request Renewal Notification Email address is likely already set.)



Task **To set a Request Renewal Notification Email address**

1. In the Producer Portal, open the system configuration page for FlexNet Operations and show the **Renewals** group.
 - a. Click **System > Configure > FlexNet Operations**.
 - b. Expand the **Renewals** settings on the FlexNet Operations system configuration page.
2. In the **Renewals** settings find **Request Renewal Notification Email** and enter an email address for an email account at which you can receive messages.
3. Click **Save Configs**.

If you log in, again, to the End-User Portal as Lisa Barry and refresh the End-User Portal's **Expiring Entitlements** page, the **Request** button appears above the list of entitlements.



Task **To send a renewal request from the Expiring Entitlements page**

1. In the End-User Portal, click **Activation & Entitlements > Expired Entitlements**. This link opens or re-opens the **Expiring Entitlements** page that now shows the **Request** button.
2. Select the check box to select ACT-PhotoPrint-11.
3. Click **Request**.

The End-User Portal sends an email message to the address you specified for Request Renewal Notification Email using the Renewal Request for End Customer email template.

For end users, it reports the result of this process in a message on the **Expiring Entitlements** page. For producers, a message is sent to the Request Renewal Notification Email address. (Check your email account to see the resulting email message or check the Sent Messages page in the Producer Portal.)

Next Steps

Assuming you have already completed the exercises for sending messages about expiring entitlements, the exercises in this section for sending messages about expired entitlements complete the available activities in this getting started section.

Consider reading [Managing Email Templates](#) to learn about how to customize email templates. For instance, you may want to apply your account's branding to the Renewal Reminder for Expired Entitlements email template or alter the message content in the Renewal Intent for End Customer email template.

Producer administrators may also be interested in customizing the job schedule for FlexNet Operations background jobs and subscribing to the alerts that are generated when such jobs run. For more information, see [Administering Alerts](#).

Getting Started with Advanced Organization Management

This section *Getting Started with Advanced Organization Management* presents fundamental FlexNet Operations concepts and uses exercises to lead a Producer Portal user through basic account, user and partner creation and management. The intended audience for this getting started section is the first-time Producer Portal user, or one without FlexNet Operations training or experience.

Topic	Description
Introduction	List of prerequisites, introduction to FlexNet Operations license lifecycle, and description of how to perform searches in the FlexNet Operations Producer Portal user interface.
Managing Accounts	FlexNet Operations account and account management concepts and exercises that demonstrate how to browse, create, edit, and delete accounts. Brief descriptions of advanced account management topics with references for more information.
Managing Users	FlexNet Operations user and user management concepts and exercises that demonstrate how to browse, create, edit, deactivate/reactivate, and delete users. Brief descriptions of advanced user management topics with references for more information.
Managing Channel Partners	FlexNet Operations partner tier management concepts and exercises that demonstrate how to create tiers and channel partners. Brief descriptions of advanced partner management topics with references for more information.

Introduction

This section includes a list of prerequisites, an introduction to the FlexNet Operations license lifecycle, and a description of how to perform searches in the FlexNet Operations Producer Portal user interface.

Prerequisites

Before you begin the exercises in this getting started section:

- FlexNet Operations must be properly installed and configured
- The FlexNet Operations demonstration database and seed data must be loaded
- You must have a FlexNet Operations Producer Portal login and System Administrator role

The License Lifecycle: Advanced Organization Management

The FlexNet Operations license lifecycle is a repeating process of producer and customer activities, as depicted in the figure and described below.



Figure 20-1: Software License Lifecycle Stages

- **Create Products** – Create product definitions that are used to generate licenses.
- **Order/Entitle** – Define an account's rights to obtain licenses for your products.
- **Deliver/Install** – Deliver the application software to the customer and install that software.
- **Activate** – Deliver licenses to the customer.
- **Return/Rehost** – Manage license transfers from one user or system to another.

- **Maintain/Update** – Deliver software and license updates to the customer.
- **Upsell/Renew** – Renew customer licenses, or sell the customer additional product functionality.

Performing Searches in the FlexNet Operations Producer Portal User Interface

Performing Searches

The Producer Portal includes powerful search functionality on most pages. You can use the search functionality to filter lists of entitlements, fulfillments, devices, machines, accounts, and so forth by a wide variety of criteria. Refer to the following subsections for instructions:

- [Performing Simple Searches](#)
- [Performing Advanced Searches](#)



Tip ▪ The search results from most pages can be exported as comma-separated value (CSV) files. You can export all the entities in the search results or only selected entities. For more information about exporting to CSV, see [Importing and Exporting Entities](#).

Performing Simple Searches

You can perform simple searches on any page that has search controls. The search controls appear near the top of the page.




Figure 20-2: The search controls for the Manage Entitlements page

Table 20-1 ▪ Simple Search Controls

Control	Description
Search For	<p>A drop-down menu that contains short list of the most common elements to search for on the current page. For example, on the Support Licenses page, the Search For menu includes Activation ID, Product, Part Number, Sold To Account Name, Sold To Account ID, Host ID, Fulfillment ID, and Trusted Client Platform Type.</p> <p>If the element you want to search on does not appear in the Search For menu, it may be available as part of an advanced search.</p>

Table 20-1 • Simple Search Controls

Control	Description
Search Operator	<p>A drop-down menu that contains a short list of possible search operators. These operators specify how the Producer Portal conducts the search. Operators include Contains (default), Equals, Starts With, and Ends With.</p> <ul style="list-style-type: none">● Contains matches any entity for which the search value appears in the Search For element. The search value can occur anywhere in the element that is searched.● Equals matches only entities for which the search value exactly matches the entirety of the Search For element. Partial matches are not included.● Starts With matches any entity for which the search value occurs at the start of the Search For element.● Ends With matches any entity for which the search value occurs at the end of the Search For element.
Search Value	<p>A text field where you can enter the value you want to find in the Search For element. (Wild card characters are not necessary nor permitted. Spaces can be used.)</p>
Search Button	<p>The first button in the search controls, the Search button has a magnifying glass icon. Click the Search button to search the entities on the current page for elements that match the contents of the Search Value field.</p>
Clear Search Button	<p>The Clear Search button is the second button in the search controls. It has an icon that shows an pencil eraser being used on a document. The Clear Search button immediately clears the search criteria—both for simple searches and advanced searches. When you click Clear Search, the current page reloads with no search criteria applied.</p>
Advanced Search Button	<p>The Advanced Search button is the third button in the search controls. It has an icon that shows a magnifying glass with a plus sign on it. When you click the Advanced Search button, the portal opens the Advanced Search page in a new window.</p>



Task

To perform a simple search

1. In the **Search For** menu, choose an element to search. The elements available depend on the Producer Portal page you are currently using.
2. In the **Search Operator** menu, choose a search operator. Default: **Contains**.
3. In the **Search Value** field, type the characters you want to search for.
4. Click **Search**.

The Producer Portal searches the entities that correspond to the current page for instances where the search value occurs in the search element according to the method specified by the search operator. It then reloads the current page showing only those entities that matched the search criteria.

**Task****To clear a search**

- Click the **Clear Search** button.

The Producer Portal clears the search criteria and reloads the current page showing all entities (no search criteria applied) for that page.

Performing Advanced Searches

While the simple search controls provide quick access to the most commonly searched elements on a given Producer Portal page, the advanced search controls offer a wider selection of elements to search on and the ability to search multiple elements for multiple values. When you click the **Advanced Search** button, the Producer Portal opens the **Advanced Search** page in a new window.

The **Advanced Search** page lists every element that can be searched for in the context of the main entity of the page on which you clicked the **Advanced Search** button. An advanced search from the **Manage Accounts** page allows you to search on Account ID, Account Name, Description, City, State/Province, Zip, Country, and Region. All elements meaningful to searches of accounts. An advanced search from the **Support Licenses** page, in contrast, shows a wide array of elements—from common elements like Entitlement ID and Activation ID, to date elements like Start Date and Expiration date, to detailed elements like individual Custom Attributes and Custom Host Attributes. You can search for multiple elements using various search operators. Search results reflect all the entities that match all the search criteria.

**Task****To perform an advanced search**

1. Click **Advanced Search**. This button opens the **Advanced Search** page in a new window. Searchable elements depend on the context of the page on which you initiated the advanced search. An advanced search from the **Package Products** page shows different searchable elements than an advanced search from the **Entitle Customers** page.
2. For the elements you want to search, set the search operator and type a search value. Operators vary by the element type. For textual elements, the typical search operators are the same as the simple search operators: Contains, Equals, Starts With, and Ends With. For date elements, the common search operators are Before, After, and On.



Tip • You can also search on producer-defined custom attributes. To use multiple attributes, select an attribute, a search operator and search value, then click **Add Custom Attribute**. Continue adding attributes as needed. Click the **X** after a custom attribute or custom host attribute to remove only that attribute from the search criteria.

3. Click **Search**.

The Producer Portal closes the **Advanced Search** page and reloads the current Producer Portal page to show only entities that match all the search criteria in the advanced search. When looking at the search results, you can clear the search criteria in the same way you clear a simple search: Click the **Clear Search** button.

You can also clear the search criteria in the **Advanced Search** page. Clearing the search criteria in the **Advanced Search** page only clears the fields on that page. It does not clear the current query, if one has been applied.



Task **To clear advanced search criteria**

- On the **Advanced Search** page, click **Clear**.

Searchable Entities and Elements

The following entities and elements are searchable in the Producer Portal:

Features	Feature bundles
Products	Suites
Maintenances	License models
Transaction keys	Entitlements
Activatable items	Fulfillments
Accounts	Custom attributes
Part numbers	Product lines
ASRs	Devices
Custom host attributes	Machines

Managing Accounts

This topic introduces accounts and account management. Account management includes creating, editing, and deleting an account.

The exercises in this topic guide you through basic FlexNet Operations account management tasks.

Accounts Key Concepts

FlexNet Operations provides a set of flexible tools that enable you to define account relationships that reflect your customer and distribution partner relationships.

- Provide producers and their customers the ability to define and manage their account hierarchies.
 - Provide a true representation of “who owns what” within a large corporation.
 - Be able to share/redistribute entitlements throughout the customer account.
- Even if a large enterprise account buys via different sources and via multiple accounts, the total number of entitlements they own can be easily tracked.



Note ▪ *Not all users have access to the account pages.*

About Accounts

An account is an entity in FlexNet Operations. Accounts can represent the structure of a customer enterprise, the internal structure of a software producer or device manufacturer and, optionally, the relationships between the producer and its distribution chain. To be associated with an entitlement, a company must be entered as an account in FlexNet Operations.

Accounts can have sub-accounts, which can be used to reflect the hierarchical nature of corporate structures. Accounts and sub-accounts are defined in a parent-child relationship. For example, you could create account Eclipse SunShades and set up Eclipse NA and Eclipse EMEA as sub-accounts.

An account hierarchy can have multiple levels to flexibly accommodate different account models. For example, a single account can have multiple sub-accounts that would share a sibling relationship. Sub-accounts can themselves have sub-accounts. In addition, accounts can have multiple parents. It is recommended that the total number of associated sub-accounts for any given account does not exceed 1000.

Account Types

A FlexNet Operations account is one of four types: Producer, Customer, Partner, or Self Registered. On the **Manage Accounts** page, each of these types has a tab as described below.

- **Producers** – Software producers or intelligent device manufacturers. Producers can create multiple sub-accounts for their producer account.
- **Customers** – End users of your software or device. This category includes **PORTAL_ORG_UNIT**—the default account that maps to users who choose to self-register through the End-User Portal. A customer account can have sub-accounts.
- **Partners** – Distribution partners like wholesalers, distributors, resellers, and retailers. Producers can map their distribution tiers by defining their distribution partners as partner accounts. A partner account can have sub-accounts. Refer to [Managing Channel Partners](#) for more information about channel partners and tiers.
- **Self Registered** – Users who self-register by logging in to the FlexNet Operations End-User Portal with an entitlement ID or activation ID and set up their own user account. Optionally, users can select to be associated with an existing Self-Registered account by providing the account ID upon self-registration, instead of creating a new account.

Default Accounts

The following accounts are available in FlexNet Operations by default:

- **My Organization (MYORG)** – The producer account. Only the account display name (**My Organization**) is editable on the **Edit Account** page. This account cannot be deleted.
- **Information Not Available (UNKNOWN_ORG_UNIT)** – The account set as **Sold To** for any web register keys when account information is not provided and as the end customer or channel partner for entitlements and devices that have not been assigned an owner account.

UNKNOWN_ORG_UNIT is a temporary holding account used by FlexNet Operations, internally, when no owner account is assigned. When UNKNOWN_ORG_UNIT is the owner of an entitlement or a device, the Producer Portal shows **Information Not Available** for End Customer or Channel Partner.

This account cannot be updated or deleted.

- **Organization for Portal Accounts (PORTAL_ORG_UNIT)** – The account that maps to users who choose to self-register through the End-User Portal. Users who log in to the portal with an entitlement ID or activation ID can

subsequently choose to self-register, set up a user account, or be associated with an existing Self-Registered account.

This account cannot be updated or deleted.

Account Hierarchies

The Advanced Organization Management module enables users to create multi-level account hierarchies for producers, customers and partners within FlexNet Operations to manage entitlements.

The following is an example of an account hierarchy created using the Advanced Organization Management module. It includes several branches and levels of a customer account.




Figure 20-3: Example Account Hierarchy

Management Tasks

Management tasks include the following activities:

- [Browsing Accounts and Sub-Accounts](#)
- [Creating, Editing, or Deleting an Account](#)

Browsing Accounts and Sub-Accounts

Accounts and sub-accounts are displayed, one type at a time, on tabs labeled **Producers, Customers, Partners,** and **Self Registered** on the **Manage Accounts** page. If you are assigned a role with the **View Accounts** or **View and Manage Accounts** permission, you can browse accounts in the Producer Portal. You can also view an account's hierarchy—the parent account and any sub-accounts associated with it. To view any sub-accounts of an account, click the **+** icon to expand the tree view in the Manage Accounts list.

The **Manage Accounts** page provides the following information:

- **Account ID:** Unique identifier of the account
- **Account Name:** User-friendly name of the account
- **Created By, Created On:** User name of the creator and date of creation
- **Description, City, State, Country:** If included in the account settings, these columns are also populated in the accounts list.

Creating, Editing, or Deleting an Account

To be associated with an entitlement, a company must be entered as an account in FlexNet Operations.

If you are assigned a role with the **View and Manage Accounts** permission, you can add, edit, or delete accounts and sub-accounts.

After you have created an account, you can create sub-accounts for it. It is recommended that the total number of associated sub-accounts for any given account does not exceed 1000.

You can edit an account or sub-account to change its name; to add, edit, or delete users; or to delete its sub-accounts.



Important - Do not enter a colon (:) character in the **Account Name** field.

To delete an account or sub-account from FlexNet Operations, use the **Delete Account** or the **Delete Subtree** button on the **Manage Accounts** page:

- **Delete Account**—removes the selected accounts. If the account has sub-accounts, those sub-accounts no longer have a parent account. The sub-accounts are retained but become top-level accounts. (For example, any sub-accounts of a deleted customer account become customer accounts.) Any sub-accounts that were also parents of sub-accounts retain the hierarchy of sub-accounts beneath them.
- **Delete Subtree**—removes the selected account and all of the sub-accounts in its hierarchy.

Account Management Exercises

These exercises use examples to guide you through the following account management tasks:

Exercise	Description
Browsing Accounts	Browse the Producers, Customers, Partners, and Self Registered account types.

Exercise	Description
Creating a Customer Account and User	Create customer account Eclipse SunShades and customer user Laurie Larson, and add existing user Lisa Barry.
Creating a Customer Sub-Account	Create sub-accounts Eclipse NA and Eclipse EMEA for customer account Eclipse SunShades.
Creating a Producer Sub-Account	Create producer sub-account Beta Software.
Editing an Account	Edit the display name for account Eclipse SunShades and remove user Lisa Barry.
Deleting an Account	Delete the sub-account Eclipse NA of customer account Eclipse SunShades.

Browsing Accounts

In this exercise, you browse accounts to become familiar with the **Producers**, **Customers**, **Partners**, and **Self Registered** tabs on the **Manage Accounts** page of the FlexNet Operations Producer Portal.



Task

To browse existing accounts

1. Log in to the FlexNet Operations Producer Portal if you have not already done so. The **Producer Portal Home** page appears.
2. Click **Accounts & Users > All Accounts**. The **Manage Accounts** page appears with the **Customers** tab selected.
3. Click the **Account** link for any of the customers listed on the tab. The **Create An Account** page appears with details such as the customer's account type, name, description, and address. Click **Cancel** to return to the **Manage Accounts** page.



Note - When there are several pages of accounts to browse, you can use the search feature to locate a specific account. However, Search and Advanced Search are applied only on the currently selected account tab.

4. Repeat **Step 3** for the **Producers**, **Partners**, and **Self Registered** account tabs.

Creating a Customer Account and User

In this exercise, you create customer account Eclipse SunShades and customer user Laurie Larson, and you add existing user Lisa Barry.



Task To create customer account Eclipse SunShades and add customer users

1. Click **Accounts & Users > Create Account**. The **Create An Account** page appears. Note that the **Account Type** is set to **CUSTOMER**.
2. Enter the account information:
 - **Account ID:** Type Eclipse_SunShades
 - **Account Name:** Type Eclipse SunShades



Important - Do not enter a colon (:) character in the **Account Name** field.

- Add additional description and address information as desired.
3. To create a user for this customer account, click **Create a User**. The **Create A User** page appears.
 4. Under **User Details**, enter the FlexNet Operations user information:
 - a. **End-User Portal Access?:** Select **Yes**
 - **Yes** allows the user to log in to FlexNet Operations. **Time Zone**, **Status**, and **Shared Login** attributes are shown when this is selected.
 - **No** maintains the user as a contact only. **Time Zone**, **Status**, and **Shared Login** are hidden when this is selected.
 - b. **User Name:** FlexNet Operations users always use their email address to log in.
 - c. **Time Zone:** Select a time zone from the drop-down list
 - d. **Status:** Leave the status set to **Active**. The records of an inactive user remain on file, but the user no longer has access to FlexNet Operations.



Note - Multiple unsuccessful login attempts automatically set the user's status to Inactive. The user can be reactivated by an administrator after confirming the user's legitimacy.

- e. **Shared Login:** Select **No**
 - **Yes** means this account is shared by a group of users.
 - **No** means this account has only one user.
5. Under **Contact Details**, enter the contact information:
 - **First Name:** Type Laurie
 - **Last Name:** Type Larson
 - **Email Address:** Type llarson@eclipsesunshades.com
 6. Under **Accounts**, select **Portal User Role**, then click **Save**. This message appears: User Laurie Larson successfully added. Click **Cancel** to return to the **Create An Account** page.
 7. To link an existing user to this customer account, click **Link Existing Users**. The **Select User** window opens.

8. In the **Select User** window, select **Display Name** Lisa Barry and **Portal User Role**, then click **OK** to close the window. This message appears: Users have been linked to the account Eclipse_SunShades successfully.
9. Click **Accounts & Users > All Accounts** to verify that Eclipse_SunShades appears on the **Customers** list of the **Manage Accounts** page.

Creating a Customer Sub-Account

In this exercise, you create sub-accounts Eclipse NA and Eclipse EMEA for customer account Eclipse SunShades.



Task To create customer sub-accounts Eclipse NA and Eclipse EMEA

1. Click **Accounts & Users > All Accounts**. The **Manage Accounts** page appears with the **Customers** tab open.
2. Select the Eclipse_SunShades check box and click **Create a Sub Account**. The **Create An Account** page appears with **Parent Account** set to Eclipse_SunShades and **Account Type** set to CUSTOMER.
3. Enter the account information:
 - **Account ID:** Type Eclipse_NA
 - **Account Name:** Type Eclipse NA



Important • Do not enter a colon (:) character in the **Account Name** field.

- **Country:** Select **United States**

Click **Save**. This message appears: Account Eclipse_NA has been successfully added.

4. Repeat **Step 1** through **Step 3** to create another sub-account:
 - **Account ID:** Type Eclipse_EMEA
 - **Account Name:** Type Eclipse EMEA



Important • Do not enter a colon (:) character in the **Account Name** field.

- **Country:** Select **Netherlands**

Click **Save**. This message appears: Account Eclipse_EMEA has been successfully added.

5. Click **Accounts & Users > All Accounts** and search for Eclipse_SunShades.
6. Click the Eclipse_SunShades account's **+** icon to expand the tree and verify that sub-accounts Eclipse_NA and Eclipse_EMEA appear on the **Customers** list. Note the information that appears in the **Created By**, **Created On**, and **Country** columns for Eclipse_SunShades and its sub-accounts.

Creating a Producer Sub-Account

In this exercise, you create producer sub-account Beta Software.



Task **To create a producer sub-account**

1. Click **Accounts & Users > All Accounts**. The **Manage Accounts** page appears.
2. Select the **Producers** tab and select the check box next to **MYORG** then click **Create a Sub Account**. The **Create An Account** page appears.
3. Enter the account information:
 - **Account ID:** Type Beta_Software
 - **Account Name:** Type Beta Software



Important - Do not enter a colon (:) character in the **Account Name** field.

4. Click **Save**. This message appears: Account Beta_Software has been successfully added.

Editing an Account

In this exercise, you edit the display name for account Eclipse SunShades and remove user Lisa Barry.



Task **To edit the Eclipse SunShades account**

1. Click **Accounts & Users > All Accounts**. The **Manage Accounts** page appears with the **Customers** tab selected.
2. In the **Manage Accounts** list, click Eclipse_SunShades, the account you want to edit. The **Create An Account** page appears.
3. Change the **Account Name** from Eclipse SunShades to Eclipse SunShades, Inc. then click **Save**. This message appears: Account Eclipse_SunShades has been successfully edited.



Important - Do not enter a colon (:) character in the **Account Name** field.

4. On the user list, select the Lisa Barry check box. Click **Remove Users** then click **OK** in the confirmation message. User Lisa Barry is removed from the Eclipse SunShades, Inc. account and this message appears: Removed Users Lisa Barry for the account successfully.

Deleting an Account

In this exercise, you delete the Eclipse NA sub-account of customer account Eclipse SunShades, Inc.



Task **To delete the Eclipse NA sub-account**

1. Click **Accounts & Users > All Accounts**. The **Manage Accounts** page appears with the **Customers** tab selected.
2. In the **Manage Accounts** list, click the Eclipse_SunShades account's **+** icon to expand the tree then select the Eclipse_NA account's check box.
3. Click **Delete Account** and click **OK** in the confirmation message. The Eclipse_NA account is deleted and this message appears: Account(s) Eclipse_NA have been deleted successfully.



Task **To delete an account and all its sub-accounts**

1. Click **Accounts & Users > All Accounts**. The Producer Portal opens the **Manage Accounts** page.
2. Click the tab for the Account Type (**Producers, Customers, Partners, or Self Registered**) of the accounts you want to delete.
3. In the **Manage Accounts** list, select the parent account to delete.
4. Click **Delete Subtree**.



Note - If the *Delete Subtree* option is not selected, only the parent account is deleted. The sub-accounts are promoted to root accounts.

5. Click **OK** to confirm deletion.

The Producer Portal deletes the selected account along with its account hierarchy and refreshes the **Manage Accounts** page.



Note - Not all accounts are eligible for deletion. If an account owns entitlements it cannot be deleted.

Account Management Next Steps

In this topic, you performed basic FlexNet Operations account management tasks such as browsing accounts, creating a customer account and sub-accounts, and editing and deleting an account. In the next topic, you perform basic user management tasks.

Account Management Advanced Topics

For more information about this advanced account management topic, refer to [Managing Accounts](#).

Activations of Entitlements Across Multiple Accounts on a Single Device

Producers with the FlexNet Advanced Organization Management module who use FlexNet Embedded licensing technology can take greater advantage of their account hierarchies and channel partner sets during entitlement mapping operations. This capability also supports producers who want end users to be able to activate entitlements on any device.

FlexNet Operations enables accounts, other than the device owner, to map entitlements to a device. Producers can map entitlements from the device owner's sub-accounts to any device, and End-User Portal users can map entitlements from their account, or its sub-accounts, to any device visible to them.

Managing Users

This topic introduces users and user management. User management includes creating, editing, deactivating/reactivating, and deleting users, and assigning/removing user roles.

The exercises in this topic guide you through basic FlexNet Operations user management tasks.

Users Key Concepts

FlexNet Operations provides a set of flexible tools that enable you to define and manage users and their roles.



Note - Not all users have access to the user and role pages.

About Users

A FlexNet Operations user is an individual or group account that appears on the **Manage Users** page and has all or some of its user information stored in the FlexNet Operations database.

To log in to FlexNet Operations, a user must provide a user name and password. Revenera creates the initial user account for a producer's FlexNet Operations system administrator, then the system administrator (or other users) creates any additional users required for the producer's account and for the producer's customers (end users).

Beyond the ability to simply log in, the activities a user can perform are based on the permissions that user has been granted. However, permissions are not assigned to users directly. Instead, permissions are grouped into roles and FlexNet Operations users are assigned one or more roles. FlexNet Operations users belong to either a producer account or a customer account. Users who self-register through the End-User Portal belong to the account for Portal Accounts. If a self-registered user supplies a company name while registering, a new account will be created corresponding to the new company name and the user assigned to it. Optionally, users can select to be associated with an existing Self-Registered account by providing the account ID upon self-registration, instead of creating a new account.

To log in to FlexNet Operations, a user must provide a user name and password. Users can get access to FlexNet Operations by being either:

1. A FlexNet Operations user, meaning that all or some information for that user, whatever its source, is stored in the FlexNet Operations database. FlexNet Operations users appear under one of the tabs in the **Manage Users** page of FlexNet Operations and are members of the Home account or one of the Customer accounts. A FlexNet Operations user can be in the FlexNet domain or a directory service domain and can be added

through the Producer Portal or Web services. Users who can log into FlexNet Operations by virtue of being a member of a domain or directory service that has been assigned a role will not appear in the **Manage Users** page. To be visible they must also be added individually as a user.

2. A user in a configured directory service who is not a FlexNet Operations user. Any user in a configured directory service domain can log in to FlexNet Operations. However, to perform a task in FlexNet Operations, a non-FlexNet domain user must belong to a group that has been granted a role that can perform the task. These users appear in the Users page of FlexNet Operations and are indicated by the non-FlexNet domain name in the domain column.

FlexNet Operations users entered manually into the application are users in the FlexNet domain. Authentication information for a user in the FlexNet domain is stored in the FlexNet Operations database. FlexNet Operations users imported from a directory service are users in that directory service domain. Authentication information for a user in a directory service domain is maintained in the directory service.

Users can be members of FlexNet groups. Groups cannot be entered manually through FlexNet Operations, but can only be imported from a directory service. Membership in a group is managed entirely in the directory service.

Some user names are designed to be used as shared logins, such as proxy users rather than users who log in directly. For example, when a customer logs in to the End-User Portal with an activation ID, a shared login called `portaluser` logs in on behalf of the customer. A shared login is also useful for setting up group user accounts. For example, Revenera recommends creating a user who submits web service requests as a shared login.

Shared logins are indicated on the **Manage Users** page with an icon showing several people. Shared logins do not appear in the **Logged-In Users** page, their last login date is not recorded, nor are they deactivated automatically after a number of unsuccessful logins. The profile of a shared login cannot be edited. Both shared and non-shared users can log in to FlexNet Operations from multiple browsers simultaneously.

Users and Accounts

Each FlexNet Operations user must be linked to at least one account—either a Producer account to log in to the Producer Portal, or a Customer or Partner account to log in to the End-User Portal. A user can belong to multiple accounts, but all of the accounts must be of the same type and must not be in the same vertical hierarchy as shown in the following diagram:




Figure 20-4: Example User Assignments in a Multi Layered Account

User B can not be assigned to Acme Massachusetts, Acme East or Acme North America because they are all in the same vertical hierarchy. However, User B can be assigned to Special Operations because it is not a sub-account of Acme North America.

What a user can see and do in the End-User portal is dependent on the permissions granted them and their location in the hierarchy.

In the above scenario, User A can see all the entitlements associated with the Acme Massachusetts account and its sub-accounts as well as Acme New York because User A has been assigned the Portal Administrative User role which, by default, comes with all the permissions to see and manage entitlements in sub-accounts. User B can only see the entitlements in the Acme Boston and Special Operations accounts because, by default, the Portal User role does not have permission to see any entitlements beyond their own account(s).

A user who self-registers through the End-User Portal provides a company name, a new account is created to correspond to the new company name, and the user is assigned to it. Optionally, users can select to be associated with an existing Self-Registered account by providing the account ID upon self-registration, instead of creating a new account.

A user belongs to one of four types. On the **Manage Users** page, each of these types has a tab as described below.

- Customer Users – End users of a producer’s software or device
- Producer Users – Software producer or intelligent device manufacturer users
- Partner Users – Distribution partner users like wholesalers, distributors, resellers, and retailers

- Self-Registered Users – Users who self-register by logging in to the End-User Portal with an entitlement ID or activation ID and set up their own user account

Default Users

By default, the following users are provided with FlexNet Operations:

Table 20-2 • FlexNet Operations Users

User Name	Description
admin	Non-shared login with the System Administrator role. This user cannot be deactivated.
portaluser	Shared login for End-User Portal users who log in with an entitlement ID or activation ID. This user is assigned the Portal User role.
trustedstorageuser	Shared login that does not appear in any of the user management pages. It is displayed in the fulfillment history as the user who performs trusted transactions.
legacyuser	Shared login that does not appear in any of the user management pages. It is displayed in the fulfillment history as the user who imported legacy fulfillments from another system.

Your User Profile and Password

Each FlexNet Operations account has a user profile that includes details about the user’s name, email address, password, phone number, and postal address.

For producer users with the "View and Manage Download Packages" permission, the profile also displays a container registry secret. This secret is required to log in to the Revenera registry, which is used for the distribution of containerized software.

You can view your own user profile from the **User** menu—the name of the current user next to the **System** menu at the top right corner of the **Producer Portal** page—by selecting **My Profile**. If you are not a shared user, you can edit your user profile. A shared user can only view the profile.

Whenever you enter your user name and a system-generated FlexNet password to log in to FlexNet Operations, you are directed to the **Change Password** page to change your system-assigned password to one that you choose. You can also change your password or select a secret question and answer at a later time by editing your user profile.



Note • To change your password from the **My Profile** page, enter the old password then enter and confirm the new password. No email message is sent to remind you of your new password. The next time you log in, enter your new password.

If you forget your password and have selected a secret question and answer, you can have a system-generated password emailed to you. If you did not select a secret question and answer, you must contact the FlexNet Operations administrator to request a new system-generated password.

Browsing Users

If you are assigned a role with **View Users** permission, you can browse users in the Producer Portal. Click on a user to view details of the user's account.



Note ▪ To locate a difficult to find user, use the search feature on the **Manage Users** page.

Creating, Editing, or Deleting a User

Information for a FlexNet Operations is typed manually into FlexNet Operations. FlexNet Operations users are in the FlexNet domain. Authentication information is stored in the FlexNet Operations database.

If you are assigned a role with the **View and Manage Users** permission, you can view, add, and edit all types of users. If you are assigned a role with the **View and Manage Customer Users** permission or **View and Manage Partner Users** permission, you can view all types of users but you can add and edit only customer users or partner users, respectively. The **Create a User** page displays the creation and last login dates for non-shared users.

When you create a new user account, an email containing a system-generated password and login instructions is sent to the user's email address. The user logs in for the first time with the system-generated password and is immediately prompted to change the password.

You can edit a user to change the user's details, contact information, or account.

You can delete a user from FlexNet Operations if the user has no dependencies (such as, for example, line items, entitlements, or alert subscriptions). This permanently removes that user from the database. If you want to keep the user in the database but want to restrict access, consider deactivating the user instead.

You cannot permanently delete a user from the database who has dependencies. However, you can perform a force delete. The force delete ensures that the user record and its dependencies are retained but placed in an inactive state. In this state, all fields on the user record are rendered obsolete, login-credential resets for the user are prohibited, and no further access to the user record is allowed.

Note that this option applies only to the forced deletion of non-producer users with dependencies.

Resetting a User Password

When you reset a non-shared user's password, an email is sent to the user with a new system-generated password. The user logs in with the new password and is immediately prompted to change the password.

If the user is shared, the email containing a system-generated password is sent to a FlexNet Operations administrator (if you specified the administrator's email address when the user was created). The administrator logs in to FlexNet Operations with the system-generated password, changes the password and keeps a record of it, then sends the new password to all users of the shared login.

Deactivating and Reactivating a User

If you are assigned a role with **View and Manage Users** permission, you can deactivate and reactivate all types of users manually. If you are assigned a role with the **View and Manage Customer Users** permission or **View and Manage Partner Users** permission, you can deactivate and reactivate only customer users or partner users, respectively. User activation status is shown on the **Create A User** page.

Users can be deactivated manually or automatically. Deactivated users remain in the FlexNet Operations database, but they cannot log in.

Non-shared users are deactivated automatically after too many consecutive failed login attempts.



Note - The default number of consecutive failed authentications is 3; this number can be configured in the FlexNet Platform Server configuration. When a user is deactivated automatically, the User Deactivated alert is triggered if it has been configured.

Deactivated users must be reactivated manually. A reactivated user is informed by email, and if the reactivated user is shared, an administrator receives the email stating that the user has been reactivated. Reactivation does not affect a user's password.

About Roles and Permissions

The activities a FlexNet Operations user can perform are based on the permissions that user has. However, permissions are not assigned to users directly. Instead, sets of permissions are grouped into roles and users are assigned one or more roles.

Permissions

FlexNet Operations permissions are organized into the following categories. For more information about the permissions in these categories, refer to [FlexNet Operations Permissions](#).

- Alert Management
- System Administration
- Operations Feature Bundles
- Operations License Models
- Operations Entitlements - Producer Portal
- End-User Portal
- End-User Portal Trusted Storage Licensing
- Web Services
- Operations Export Import
- User Management
- Account Management
- Operations Features
- Operations Products, Suites, and Maintenance
- Operations Part Numbers
- Operations License Management
- Operations Policies
- Operations Trusted Storage Licensing
- Operations Sub-Accounts
- License Technologies
- FlexNet Embedded

Roles

By default, the following producer and end-user roles are available in FlexNet Operations. For more information about these roles, refer to [FlexNet Operations Roles](#).

- Customer Support Representative
- Executive
- IT Back Office Manager
- Order Entry
- Portal Administrative User (end-user role)
- Portal User (end-user role)
- Product Manager
- Sales Operations Manager
- System Administrator
- Super Administrator—This role is reserved for Revenera administrators.

Browsing Roles

Roles for FlexNet Operations are displayed in the **Roles** page. If you are assigned a role with the **View Roles** or **View and Manage Roles** permission, you can view a summary of roles.

Assigning a Role to a User

You can assign a role to a user, if the user is able to log in to FlexNet Operations, on the user's **Create A User** page. Role assignments are made per account in the **Accounts** table near the end of the page.



Note - Not all users have sufficient permissions to assign or remove a user's role(s).

Browsing Users with a Role

If you are assigned a role with **View Users** and **View Roles** permissions, you can view users who have been assigned a particular role. In addition, you can determine whether a user is shared; shared users are marked with an icon showing several people. The following summary information is displayed on the **Users for Role** page:

- **User Name:** Login name of the user
- **Display Name:** Full name of user
- **Date Created:** Date the user was created
- **Date of Last Login:** Date of last login by the user (not recorded for shared users)
- **Status:** Whether the user is active or inactive

User Management Exercises

These exercises use examples to guide you through the following user management tasks:

Exercise	Description
Browsing Users	Browse the Customer Users , Producer Users , Partner Users , and Self Registered Users types.
Creating a User	Create a customer user named William Barry and link him to account BarryPhoto .
Editing a User	Change the name of customer user William Barry to Warren Barry.
Resetting a User's Password	Reset the password of customer user Warren Barry.
Changing a User's Account	Change the account a user is linked to.
Deactivating or Reactivating a User	Deactivate and reactivate customer user Warren Barry.
Deleting a User	Delete customer user Warren Barry.
Browsing Roles	Browse the existing user roles on your system.
Browsing Users with a Role	Browse users who are assigned a particular role.
Assigning or Removing a User's Role	Assign the Portal Admin User Role to Lisa Barry and remove the Portal User Role .

Browsing Users

In this exercise, you browse FlexNet Operations users to become familiar with the **Customer Users**, **Producer Users**, **Partner Users**, and **Self Registered Users** tabs on the **Manage Users** page of the Producer Portal.



Task

To browse existing users

1. Click **Accounts & Users > All Users**. The **Manage Users** page appears with the **Customer Users** tab selected. On a **Manage Users** page tab, you can view the following information:
 - Whether a user is a shared user (a shared user has an icon depicting several people)
 - **Display Name**: User's full name
 - **User Name**: User's login name
 - **Email Address**: User's email address
 - **Type**: User or Contact. A contact is a user account that cannot log in, and is maintained for account contact purposes.
 - **Accounts**: All accounts to which the user belongs

2. Click on the **Producer Users** tab to view the producer users. Note that **Portal User** is a shared user.
3. Click on the **Partner Users** tab to view the partner users.
4. Click on the **Self Registered Users** tab to view the self registered users.
5. Click on the **Customer Users** tab, then click the Lisa Barry **Display Name** link to view the details on the **Create A User** page that appears. When you are done, click **Cancel** to close the **Create A User** page.

Creating a User

In this exercise, you create a customer user named William Barry and link him to account **BarryPhoto**.



Task

To create user William Barry and link him to account BarryPhoto

1. Click **Accounts & Users > Create User**. The **Create A User** page appears.
2. Under **User Details**, enter the FlexNet Operations user information:
 - a. **End-User Portal Access?:** Select **Yes**
 - **Yes** allows the user to log in to FlexNet Operations. **Time Zone**, **Status**, and **Shared Login** attributes are shown when this is selected.
 - **No** maintains the user as a contact only. **Time Zone**, **Status**, and **Shared Login** are hidden when this is selected.
 - b. **User Name:** FlexNet Operations users always use their email address to log in.
 - c. **Time Zone:** Select a time zone from the drop-down list
 - d. **Status:** Leave the status set to **Active**. The records of an inactive user remain on file, but the user no longer has access to FlexNet Operations.



Note - Multiple unsuccessful login attempts automatically set the user's status to Inactive. The user can be reactivated by an administrator after confirming the user's legitimacy.

- e. **Shared Login:** Select **No**
 - **Yes** means this account is shared by a group of users.
 - **No** means this account has only one user.
3. Under **Contact Details**, enter the user's contact information:
 - a. **First Name:** Type William
 - b. **Last Name:** Type Barry
 - c. **Email Address:** Type WBarry@barryphoto.com
4. Under **Accounts**, click **Link Accounts**. The **Select Account** window opens with the **Customers** tab selected. Search for and select the **BarryPhoto** and **Portal User Role** check boxes, then click **OK** to close the window. An email containing a system-generated password and login instructions is sent to the user's email address, and this message appears: User William Barry successfully added.



Note - Users can be assigned to more than one account, provided those accounts are parallel to one another or are in a different vertical hierarchy. For example, user can not be assigned to both a parent and child account because they are vertical to one another in the hierarchy.

Editing a User

In this exercise, you change the name of customer user William Barry to Warren Barry.



Task To edit existing user William Barry

1. Click **Accounts & Users > All Users**. The **Manage Users** page appears with the **Customer Users** tab selected.
2. In the **Users** list, click the **William Barry** link to view the user and contact details on the **Create A User** page that appears.
3. Change the user's **First Name** from **William** to **Warren**, then click **Save**. This message appears: User Warren Barry successfully edited.

Resetting a User's Password

In this exercise, you reset the password of customer user Warren Barry.



Task To reset Warren Barry's password

1. Click **Accounts & Users > All Users**. The **Manage Users** page appears with the **Customer Users** tab selected.
2. In the **Users** list, click the **Warren Barry** link to open the **Create A User** page.
3. On the **Create A User** page, click **Reset Password** to send an email to the user with a new system-generated password. This message appears: Password has been reset and emailed to the user.

Changing a User's Account

Use the following to change the account to which a user is linked.



Task To move a user from one account to another.

1. Click **Accounts & Users > All Users**. This opens up the **Manage Users** page.
2. On the **Manage Users** page, click the name of a user.
3. On the **Create a User** page, scroll down to the **Accounts** heading and click **Link Accounts**. This opens the **Select Account** page.

4. On the **Select Account** page, select the user's new account and select a role, for example: Portal Admin User or Portal User, then click **OK** to close the window. A message like the following appears: User John Doe successfully edited.



Note - A user can only be moved to an account of the same type (i.e. end customer or channel partner)

5. On the **Create a User** page, scroll down to the **Account** heading and select the account to remove, then click the **Remove** button.



Note - A user must have at least one account associated with it. You can only assign accounts that are parallel to one another or in a different vertical hierarchy. You cannot move a user from a child account to a parent account or vice versa through the UI. It can only be done through Web Services. For more information, refer to the Web Services Guide.

Deactivating or Reactivating a User

In this exercise, you deactivate and reactivate customer user Warren Barry.



Task To deactivate user Warren Barry

1. Click **Accounts & Users > All Users**. The **Manage Users** page appears with the **Customer Users** tab selected.
2. In the **Users** list, click the **Warren Barry** link to open the **Create A User** page.
3. On the **Create A User** page, in the **Status** drop-down list, select **Inactive**, then click **Save**. User Warren Barry is deactivated and this message appears: User Warren Barry successfully edited.



Task To reactivate user Warren Barry

1. Click **Accounts & Users > All Users**. The **Manage Users** page appears with the **Customer Users** tab selected.
2. In the **Users** list, click the **Warren Barry** link to open the **Create A User** page.
3. On the **Create A User** page, in the **Status** drop-down list, select **Active**, then click **Save**. User Warren Barry is reactivated and this message appears: User Warren Barry successfully edited.

Deleting a User

In this exercise, you delete customer user Warren Barry.



Task To delete a user

1. Click **Accounts & Users > All Users**. The **Manage Users** page appears with the **Customer Users** tab selected.
2. In the **Users** list, search for and select the **Warren Barry** check box.

3. Click **Delete** and click **OK** in the confirmation message. **Warren Barry** is deleted from the **Customer Users** list and this message appears: User(s) Warren Barry have been deleted successfully.



Note ▪ If the user Warren Barry has dependencies (such as, for example, line items, entitlements, or alert subscriptions), you are prompted to confirm the deletion in an additional dialog. When you confirm the deletion, all fields in the user record are changed to `Obsolete`. This means that this user record is no longer accessible.

Browsing Roles

In this exercise, you browse the existing user roles on your FlexNet Operations system.



Task To view a list of existing roles

1. Click **Accounts & Users > All Roles**. The **Roles** page appears with the following information:
 - **Role Name:** Name of the role, which links to its **Edit Role** page
 - **Status:** Whether the role is active or inactive and whether it is a system-defined role
 - **Mapped Users:** Links to users who are assigned the role
2. Click one of the roles in the list. When the **Edit Role** page appears, review the different categories and permissions included in each. When you are done, click **Cancel** to return to the **Roles** page.

Browsing Users with a Role

In this exercise, you browse users who are assigned a particular role.



Task To browse users with a particular role

1. Click **Accounts & Users > All Roles**.
2. To see the users with a **Portal User Role**, click the **users** link for that role under **Mapped Users**. The **Users For Role** page appears with the following information about the users who are assigned this role:
 - **User Name:** Login name of the user and whether the account is shared (portaluser is shared)
 - **Display Name:** Full name of the user
 - **Date Created:** Date the user was created
 - **Date of Last Login:** Date of user's last login (not recorded for shared users)
 - **Status:** Whether the user is active or inactive
3. Review the information and note that **portaluser** is a shared user.
4. Use your browser's Back button to return to the **Roles** page, then repeat **Step 2** and **Step 3** for the **System Administrator** role. Note that **legacyuser** and **trustedstorageuser** are also shared users.

Assigning or Removing a User's Role

In this exercise, you assign the **Portal Admin User Role** to Lisa Barry and you remove the **Portal User Role**.



Task

To assign a role to a user

1. Click **Accounts & Users > All Users**. The **Manage Users** page appears with the **Customer Users** tab selected.
2. On the **Manage Users** page, search the user list for the Lisa Barry **Display Name**.



Note ▪ Users can appear on different tabs. Be sure you are looking for the user on the correct tab.

3. Click the Lisa Barry link to view her **Create A User** page.
4. On the **Create A User** page, under **Accounts**, select the **Portal Admin User Role** box to assign it to Lisa Barry. (Possible roles appear in the **Role** column of the **Accounts** table—one set per account.)



Note ▪ A user must have at least one role assigned for each account to which he or she belongs.

5. Click **Save**. The role assignment is saved and this message appears: User Lisa Barry successfully edited.



Task

To remove a role from a user

1. Click **Accounts & Users > All Users**. The **Manage Users** page appears with the **Customer Users** tab selected.
2. On the **Manage Users** page, search the user list for the Lisa Barry **Display Name**.



Note ▪ Users can appear on different tabs. Be sure you are looking for the user on the correct tab.

3. Click the Lisa Barry link to view her **Create A User** page.
4. On the **Create A User** page, under **Accounts**, uncheck the **Portal User Role** box to remove it from Lisa Barry. (Possible roles appear in the **Role** column of the **Accounts** table—one set per account.)



Note ▪ A user must have at least one role assigned for each account to which he or she belongs.

5. Click **Save**. The role removal is saved and this message appears: User Lisa Barry successfully edited.

User Management Next Steps

In this topic, you performed basic FlexNet Operations user management tasks such as browsing users, creating and editing a user, resetting a user's password, deactivating and reactivating a user, deleting a user, browsing roles, browsing users assigned a particular role, and assigning or removing a user's role.

In the next topic you will perform channel partner management, including creating tiers and adding channel partners.

User Management Advanced Topics

For more information about this advanced account management topic, refer to [Managing Users](#).

Activations of Entitlements Across Multiple Accounts on a Single Device

Producers with the FlexNet Advanced Organization Management module who use FlexNet Embedded licensing technology can take greater advantage of their account hierarchies and channel partner sets during entitlement mapping operations. This capability also supports producers who want end users to be able to activate entitlements on any device.

FlexNet Operations enables accounts, other than the device owner, to map entitlements to a device. Producers can map entitlements from the device owner's sub-accounts to any device, and End-User Portal users can map entitlements from their account, or its sub-accounts, to any device visible to them.

Managing Channel Partners

This topic discusses the management of channel partner tiers. Channel Partner management includes adding tiers and channel partner accounts.

Channel Partner Key Concepts

- Create distribution tiers for classification of distributors and resellers.
 - Represent non-flat channel distribution structures in FlexNet Operations as they exist in an enterprise resource planning system.
- Allow multiple accounts from different distribution tiers to be associated with an entitlement.
 - Build a complete distribution list through the entire entitlement sale.
 - Split entitlements, bulk entitlements and maintenance between partners and customers.
 - Pool entitlements to existing line items to minimize proliferation of line items.
 - Self-service for channel partners to split entitlements
- Partner, such as a system integrator, can manage licensing on behalf of the end customer.
 - Visibility, roles, and permissions allow/prevent information about the partner tier account to be seen by others, as appropriate.

Partners and Distribution Tiers

Partner accounts identify accounts in your distribution chain—those accounts that act as distributors of your products and entitlements. Partner accounts exist in distribution tiers between your producer account and your end customers. You can add multiple partner accounts on the **Manage Accounts** page. Unless additional tiers are added, these partner accounts all occupy the default distribution tier.

By default, FlexNet Operations provides a **Distributor** tier and an **End Customer** tier for entitlements. The distribution chain allows entitlements and devices to move from the producer account to a distributor (partner account) to an end user (customer account). However, you can customize the distribution chain and add multiple tiers. Changes to the tiers in the distribution chain require the intervention of Revenera support.

Unique to partner accounts is their relationship to the producer account. Information about the transactions in the partner accounts flows up through the distribution chain so that these transactions are visible on the Producer Portal.

Some FlexNet Operations features are only available to the producer account and partner accounts. For example, only partner and producer accounts (if the current owner is set to a partner account) can split entitlements.

Architecture Overview

By default, FlexNet Operations supports a single distribution tier:




Figure 20-5: Default Tier Structure

The Advanced Organization Management module supports multiple distribution tiers:




Figure 20-6: Sample Custom Tier Structure

Built-In Tiers

The built-in tiers are **End Customer** and **Distributor**.

End Customer Tier

- All simple entitlements must have the End Customer tier populated (analogous to SoldTo).
- If the end customer account is not known, the End Customer tier can be populated with Info Not Available (UNKNOWN_ORG_UNIT) until a known account claims the entitlement.
- Additional tiers can be populated for simple entitlements, but the End Customer tier is always required.
- End Customer tier is not supported for bulk entitlements.
- Partner accounts cannot be specified in the End Customer tier of an entitlement.

Distribution Tier

- All bulk entitlements must have the Distributor (tier1) tier populated (analogous to SoldTo).
- Additional tiers can be populated for bulk entitlements but the Distributor tier is always required.

Custom Tiers

Custom tiers have no enforced hierarchy and their presence does not change the functional requirements of the built-in tiers. Creation of the custom tiers requires direct access to the database (there is no UI for creating custom tiers) so for cloud users, custom tiers are added as part of onboarding the tenant. A channel partner set contains one or more partner tiers, each tier populated by exactly one account.

Designing Channel Partner Tiers

The first step in setting up tiers for channel partners is to sketch out what the distribution channel looks like and plan for the partner tiers to accommodate that. You need to decide how rights pass from a producer to a first level distributor, to their distributors and finally to end customers. Add enough partner tiers in the database to address the demand chain.

Tracking Entitlements Through a Demand Chain

Unlike account hierarchies, there is no one direct chain between the producer and the end customer. Entitlements may be split multiple times between partner accounts before an entitlement is assumed by an End Customer. The following diagram demonstrates how a bulk entitlement can be split through several tiers of distributors and resellers to the final end customers.




Figure 20-7: Example Demand Chain

In this example, Distributor tiers are in blue and the End Customer tier is in green.

When setting up the channel partner tiers for this example, a user would need to add one reseller tier and four channel partner accounts. The remaining tiers are already populated by default (distributor and end customer).

Accounts are not assigned to Channel Partner Tiers until you have an entitlement since the appropriate partner tier may change depending on the entitlement and the deal. See [Getting Started with Entitlement Management](#).

Partner Relationships

Partner relationships between accounts can be defined to allow a Partner to split or sell entitlements along a distribution chain. Relationships can be set up between two Partner accounts or between a Partner account and a Customer account and can be set either by a Producer or by a Partner user.

A Partner user with the equivalent of a Portal Administrative User role can create other Partner accounts and users as well as other Customer accounts and users. Accounts created by a Partner user are automatically related to the user's account.

In [Figure 20-7](#), accounts in blue represent Channel Partner tiers while the Customer tier is in green. Partner relationships exist between Distributor 1 and Reseller 1 as well as between Distributor 1 and Reseller 2. Likewise, Reseller 2 has partner relationships with both End Customer 1 and End Customer 2. Entitlements passing between partner accounts are split whereas entitlements from End Customer 2 to Business Unit 1 and Business Unit 2 are transferred since they are part of the same account hierarchy within the Customer tier.

Splitting Entitlements

One of the partner tiers (either the partner account or one of its sub-accounts) of an entitlement must be set as Current Owner before an entitlement can be split. A Producer user can also split an entitlement on behalf of a Partner account, however, the Current Owner must still be set. Only unactivated entitlements or web register keys can be split.

If a bulk entitlement has several layers of Channel Partners, one layer can split off some of the web register keys to another bulk entitlement to another related Channel Partner account.

Once a known End Customer is identified on the entitlement, it will be set as the current owner and the current owner cannot be changed to another tier.

If the Current Owner setting is set to a tier other than End Customer, it indicates only that a user in the account in that tier, or a producer user, can split that entitlement. It has no additional significance.

Transferring vs Splitting Entitlements

Entitlement transfers happen primarily within a customer account hierarchy because entitlements can only be transferred to a customer account. An End Customer account can transfer entitlements to a parent or child account of itself whereas a Channel Partner can only transfer an entitlement to a related customer account. To move an entitlement to a related Channel Partner account, the entitlement must be split. Producer users can transfer or split entitlements on behalf of the customer or partner users.

Information Visibility

To control visibility there is a flag on the **Create An Account** page called **Visible to other Partners**. If the flag is set to false, it will prevent distributors or resellers higher up the chain from seeing the name of the Current Owner of an entitlement. The account name will be displayed as Name Withheld. If the flag is set to true, all partner accounts directly related to the account can view the account name on visible entitlements.

Creating a Partner Account

Partners are special accounts in FlexNet Operations. (See [Partners and Distribution Tiers](#) for more information.)

Users assigned a role with the **View and Manage Accounts** permission can view, add, and edit accounts.



Task

To create a partner account

1. Click **Accounts & Users > Create Partner Account**.
2. On the **Create An Account** page:
 - a. Enter the **Account ID** (required).
 - b. Enter the **Account Name** of the account (required).



Important - Do not enter a colon (:) character in the **Account Name** field.

- c. Add a description and address information as desired.
 - d. Set the **Visible to other Partners** check box (it is selected by default).
 - To prevent partners in different distribution tiers from seeing information about this account, uncheck **Visible to other Partners**.
 - To allow partners to see information about this account, check **Visible to other Partners**.
3. If you want to link users to the account, do one of the following:
 - Click **Create a User** to link a new user to the account. Then follow the steps outlined in [Creating, Editing, or Deleting a User](#) to create the new user account.
 - Click **Link Existing Users** to link existing users to the account. Select the users (and roles, if applicable) you want to link and click **OK**.
 4. Click **Next**. On the **Linked Sub-Accounts** page, select any sub-accounts you want to link to this account. (Optional)



Note - Only parent accounts can set up links to sub-accounts.

5. Click **Next**. On the **Relate Accounts** page, select any partners you want to relate to this account. (Optional)



Note - Relationships between Channel Partners and End Customers must be set up from the Channel Partner or Producer end. Producers can set up relationships between Channel Partners and End Customers but they don't participate in the relationships.

6. Click **Complete**.

Channel Partner Next Steps

In this topic, you performed the basic FlexNet Operations partner management task creating Channel Partner Accounts.

Product ordering and entitlement is the stage of the FlexNet Operations license lifecycle that follows.

Refer to these getting started sections for concepts and exercises that guide you through electronic software delivery, usage management, and cloud licensing service tasks:

- [Getting Started with Electronic Software Delivery](#) (requires the Software Delivery module)
- [Getting Started with Usage Management](#)
- [Getting Started with Cloud Licensing Service](#)

Refer to this getting started section for concepts and exercises that guide you through entitlement management tasks:

- [Getting Started with Entitlement Management](#)

Refer to this section for detailed information on transferring and splitting entitlements:

- [Entitling Customers and Activating Licenses](#)

Refer to these getting started guides for concepts and exercises that guide you through licensing activation and support tasks:

- [Getting Started with FlexNet Embedded Licensing](#)
- [Getting Started with FlexNet Publisher License File-Based Licensing](#)
- [Getting Started with FlexNet Publisher Trusted Storage-Based Licensing](#)
- [Getting Started with Non-FlexNet Licensing Technologies](#)

Channel Partner Advanced Topics

Activations of Entitlements Across Multiple Accounts on a Single Device

Producers with the FlexNet Advanced Organization Management module who use FlexNet Embedded licensing technology can take greater advantage of their account hierarchies and channel partner sets during entitlement mapping operations. This capability also supports producers who want end users to be able to activate entitlements on any device.

FlexNet Operations enables accounts, other than the device owner, to map entitlements to a device. Producers can map entitlements from the device owner's sub-accounts to any device, and End-User Portal users can map entitlements from their account, or its sub-accounts, to any device visible to them.

Part 3

Administrator Reference

This part of the FlexNet Operations User Guide includes the following sections:

- [Configuring FlexNet Operations](#)
- [Performing Administrative Tasks](#)

21

Configuring FlexNet Operations

This chapter discusses how to configure FlexNet Operations using the links in the System menu.

Table 21-1 •

Topic	Description
Using the System Menu	View system configuration settings, custom content, recent news, and link to your end-user portal, your reports, system uptime statistics, and FlexNet Operations' customer community via the System menu.
Performing System Configuration	Administer system configuration settings for FlexNet Operations Producer Portal, End-User Portal, FlexNet Platform server, embedded devices, and more via the options in System > Configure .
Secure Token Single Sign-On	Configure the FlexNet Operations end-user portal to interface with a separate application, such as a corporate portal or intranet.
Viewing Transaction Histories	Describes how to search for and view transaction histories and transaction details.
Managing Custom Content	Create and manage custom HTML and text snippets to be rendered in your End-User Portal pages.

See Also

[Managing Accounts and Users](#)

Using the System Menu

Users assigned a role with the **View System Information** permission can view system information.

The System menu includes a number of links for viewing system information as well as a number of links for managing system configuration settings and custom content and the like. The system information links are covered here. The other activities, such as system configuration, are covered in their own sections.

System information links in the System menu include the following:

Table 21-2 •

Link	Description
Configure	Opens the System Configuration page. For details about changing system configuration settings, see Performing System Configuration .
Custom Content	Opens the Custom Content page. For more information about administering custom content, see Managing Custom Content .
End-User Portal	A shortcut for opening your End-User Portal in a separate tab or window. Click System > End-User Portal to open your End-User Portal to the login page.
Transaction History	Opens the Search Transaction History page. For more information about searching and viewing transaction histories, see Viewing Transaction Histories .
Reports	Launches the Reporter. See the Reporter Quick Reference and Reporter Standard Reports for more information.
Application Log	<p>Opens the View FlexNet Application Log page. The FlexNet Operations application log contains useful information for debugging problems with the application, and technical support may ask you to send all or part of the log to help solve any problems you report.</p> <p>Click System > Application Log to view the log entries.</p> <p>You can also download the application log entries by clicking the Download button on the View FlexNet Application Log page.</p>
About Advanced Lifecycle Management Module	Opens a page to give version information—versions, build numbers, patch levels, and license status—about the FlexNet Operations base module. Click System > About Advanced Lifecycle Management Module to show module-specific information.
About Electronic Software Delivery Module	Opens a page to give version information—versions, build numbers, patch levels, and license status—about the FlexNet Operations electronic software delivery module. Click System > About Electronic Software Delivery Module to show module-specific information.
Uptime	Shows basic uptime information for cloud-hosted FlexNet Operations components and environments. Click System > Uptime to show uptime information.
Latest News	Shows information about the current year’s release schedule and the timing for the environment update. Click System > Latest News to show the Latest News page.

Table 21-2 ▪

Link	Description
Customer Community	Opens the Revenera Customer Community home page in a new window. Click System > Customer Community to show customer community portal.

See Also

[Performing System Configuration](#)
[Managing Custom Content](#)

Performing System Configuration

A user must be assigned a role with the **View and Manage Configurations** permission to view system configuration and to modify any configuration settings through the Producer Portal.

To change configuration settings through the FlexNet Operations Producer Portal, click **System > Configure** to open the **System Configuration** page.



Note ▪ Configuration changes made in the FlexNet Operations System Configuration page could take a few minutes to take effect on the system, typically 1-2 minutes.

Table 21-3 ▪ System Configuration Page

Topic	Description
Configuring the FlexNet Platform Server	Customize outbound email settings, logging, timeouts, and other FlexNet Platform Server settings.
Configuring the Producer Portal User Interface	Alter user interface settings for the Producer Portal. The System Configuration > User Interface page allows you to specify settings such as the number of records per page and log lines per page.
Configuring Validators	Customize the validation of user name and password fields.
Configuring System Settings	Customize a wide range of FlexNet Operations settings. These include URLs for support and user communities, classnames for ID and fulfillment ID generators, host ID validators, as well as many other default settings and settings for optional features.
Configuring Trusted Activation Settings	Configure settings to activate or deactivate trusted storage features and specify generators for custom attributes in online responses and short code responses.
Configuring Public Services Settings	Configure settings to activate or deactivate public services.

Table 21-3 • System Configuration Page

Topic	Description
Configuring End-User Portal Settings	Customize settings for the FlexNet Operations End-User Portal. This page enables you to customize logos, colors, and page footer content; hide various page elements, links, fields, buttons, and views; and otherwise control the appearance and behavior of the portal.
Activating and Licensing FlexNet Operations	Activate your account's FlexNet Operations license. You must activate your FlexNet Operations license to enable the FlexNet Operations features your account purchased.
Importing a Configuration	Import a previously exported configuration file.
Exporting a Configuration	Export the current system configuration settings as a zip file. This exported zip file can be used to restore FlexNet Operations system configuration settings.
Configuring Embedded Devices Settings	Fine tune features related to devices and specify classnames for request handlers and device handlers.

Configuring the FlexNet Platform Server

A user must be assigned a role with the **View and Manage Configurations** permission to modify configuration settings for the FlexNet Platform Server through the Producer Portal.



Note • Before changing any configuration settings in a working FlexNet Operations instance, it is advisable to [export the working configuration settings](#). If there is a problem with the new settings, you have a backup of working settings to restore.



Task **To change FlexNet Platform Server configuration settings through the FlexNet Operations Producer Portal**

1. Click **System > Configure**.
2. Click **FlexNet Platform Server** to open the configuration page for the FlexNet Platform Server.
3. View or change the values of the settings below.
4. Click **Save Configs** to save changes.

The Producer Portal saves your configuration changes.

The platform server settings include the following. Note that default values are listed as the first choice. Also, required fields are indicated with an asterisk.

Table 21-4 • FlexNet Platform Server Configurations


Name	Possible Values	Description
Outbound Mail Server Host	mail or specify	The name of the machine that hosts the mail server for mail sent from FlexNet Operations. Default: fnosmtp  <hr/> Note • You must provide a value.
Outbound Mail Security	None or SSL	Type of security set for mail sent from FlexNet Operations.
Outbound Mail Server Port	0 or specify	The port on which the outbound mail server runs: Set to 0 to use the default port determined by security: SMTP/None: 25 SMTP/SSL: 587  <hr/> Note • You must provide a value.
Outbound Mail Logging Detail	Brief or Verbose	Level of detail of outbound mail written to the FlexNet Operations application log. Default: Brief
Outbound Mail Account		Mail account to use for mail sent from FlexNet Operations: Typically left blank. Value needed only if outbound mail server requires account authentication.
Outbound Mail Password (Confirm)		Password to use for Outbound Mail Account : Provide confirmation for the password.
From-Address for Outbound Mail	flexnet-server or specify	Email sent from FlexNet Operations is sent from this email address. (Should be an actual account in the email system.) Default: flexnet-server@myorg.com  <hr/> Note • You must provide a value.

Table 21-4 • FlexNet Platform Server Configurations




Name	Possible Values	Description
FlexNet Application Logging Threshold	Debug Messages Informational Messages Warnings Errors	The maximum level of detail for the messages written to the FlexNet Operations application log file <i>after</i> FlexNet Operations starts: Only messages at or below the selected level of detail are displayed in the log.
FlexNet Application Performance Logging	Selected or unselected	Select to enable performance logging in the application. Default: Unselected
Session Timeout	30 or specify	If a user has been inactive for the specified amount of time (minutes), the user must log in to FlexNet Operations again.
		 Note • <i>By default, this option is hidden and not editable. Contact Revenera support if you want to change the session timeout value.</i>
		 Note • <i>You must provide a value.</i>
Consecutive Failed Authentications	3 or specify	Number of consecutive failed attempts to log in before a user is deactivated. These attempts are counted over the Time Period for Failed Authorizations .
		For a non-shared user, the specified value applies.
		For a shared user, the specified value is multiplied by 2. (Example: 3 x 2 = 6; a shared user is deactivated after 6 consecutive failed login attempts within the Time Period for Failed Authorizations .)
		 Note • <i>You must provide a value.</i>
Minutes for re-enabling a shared login after deactivation	3 or specify	The number of minutes after which a shared user account will be reactivated after it has been deactivated due to the number of Consecutive Failed Authentications having been reached.

Table 21-4 • FlexNet Platform Server Configurations



Name	Possible Values	Description
Recaptcha Site key		<p>The site key used to invoke the Google reCAPTCHA service on the End-User Portal. The site key is programmatically validated by the Google API.</p> <p>The Google reCAPTCHA mechanism can be used for the following:</p> <ul style="list-style-type: none"> • To enable a shared user whose account is locked (due to too many consecutive failed login attempts) to have their account reactivated before the Minutes for re-enabling a shared login after deactivation timeout has elapsed. In this case, the login screen of the End-User Portal shows the “I’m not a robot” check box which enables the user to validate their account. • To re-authenticate a user when sending entitlement emails (if the Use Recaptcha validation when sending entitlement emails option is selected).
Recaptcha Secret key		<p>The secret key that authorizes communication between FlexNet Operations and the Google reCAPTCHA server to verify the shared user’s response or to verify the user when sending entitlement emails. It is essential that the secret key be kept secure.</p>
Time Period for Failed Authorizations	1440 or specify	<p>Amount of time (minutes) during which Consecutive Failed Authentications are allowed before the user is deactivated.</p> <p></p> <p>Note • You must provide a value.</p>
Default Account for External Domain	MYORG or specify	<p>Name of the default account to be used when the account of the external domain user does not map to any account in the FlexNet Operations application. The default account for a user belonging to an external domain is MYORG. This can be changed.</p> <p></p> <p>Note • You must provide a value.</p>
HTTP Response Header X-FRAME-OPTIONS	SAMEORIGIN DENY	<p>A value for X-Frame-Options in the HTTP response header. Check browser support for specified value.</p> <p>Default: SAMEORIGIN</p>
HTTP Response Header P3P		<p>A value for P3P in the HTTP response header. Specify an appropriate P3P value if a browser privacy policy is required.</p>

Table 21-4 • FlexNet Platform Server Configurations







Name	Possible Values	Description
Number of Days Email Copies retained	1 or specify	The total number of days the email history is retained. The Purge Email History job reads this configuration and based on the number of days set, deletes all the email copies.
 <p>Note • You must provide a value.</p>		
Log emails in history, do not send them	Selected or unselected	When selected, emails are be logged to the email history but only reset password emails are sent.
Default: Unselected		
		
<p>Note • For emails generated by Order Media requests, there are two emails that are triggered. One uses the template and is sent to the end user. The other does not use the template and is sent to the producer. Because this configuration setting only applies to emails generated from templates, the email sent to the producer is still sent.</p>		
Maximum Batch sizes for create / update Webservice requests	25 or specify	The batch-size maximum for requests issued from SOAP and REST web services.
<p>The value indicates the maximum number of records allowed in a single web services batch request that results in a write. Specifying a request with a batch size greater than the limit results in an error.</p>		
		
<p>Note • By default, this option is hidden and not editable. Contact Revenera support if you want to change this value.</p>		
Maximum Batch sizes for read Webservice requests	2000 or specify	The batch-size maximum for requests issued from SOAP and REST web services.
<p>The value indicates the maximum number of records allowed in a single web services batch request for a read. Specifying a request with a batch size greater than the limit results in an error.</p>		
		
<p>Note • By default, this option is hidden and not editable. Contact Revenera support if you want to change this value.</p>		

Table 21-4 • FlexNet Platform Server Configurations

Name	Possible Values	Description
Consecutive attempts to provide correct security answer	3 or specify	Number of consecutive failed attempts to provide the correct answer to the security question after which the user will be locked out. Minimum value: 1.
Prevent multiple browser sessions	Selected or unselected	 <p>Important • This functionality is currently available only for FlexNet Operations deployments in AWS.</p> <p>When selected, concurrent sessions in the Producer Portal and End-User Portal are not allowed.</p> <p>Default: Unselected</p>  <p>Note • When multiple browser sessions are disallowed, users can still open multiple tabs.</p>

See Also

- [Configuring the Producer Portal User Interface](#)
- [Configuring Validators](#)
- [Configuring System Settings](#)
- [Exporting a Configuration](#)

Configuring the Producer Portal User Interface

A user must be assigned a role with the **View and Manage Configurations** permission to modify configuration settings for the Producer Portal.



Note • Before changing any configuration settings in a working FlexNet Operations instance, it is advisable to [export the working configuration settings](#). If there a problem with the new settings, you have a backup of working settings to restore.



Task *To change user interface configuration settings for the Producer Portal*


1. Click **System > Configure**.
2. Click **User Interface**.
3. View or change the values of the settings below.
4. Click **Save Configs** to save changes.

The Producer Portal saves your configuration changes.

The user interface settings include the following. Note that default values are listed as the first choice. Also, required fields are indicated with an asterisk.

Table 21-5 • User Interface Configurations

Name	Possible Values	Description
Records Per Page	20 or specify	Number of records displayed on a page that implements pagination (For example, Users page implements pagination; Roles and Alert Types pages do not.)


Note • You must provide a value.

See Also

- [Configuring the FlexNet Platform Server](#)
- [Configuring System Settings](#)
- [Exporting a Configuration](#)
- [Importing a Configuration](#)

Configuring Validators

A user must be assigned a role with the **View and Manage Configurations** permission to modify configuration settings for configuring validators through the Producer Portal.



Note • Before changing any configuration settings in a working FlexNet Operations instance, it is advisable to [export the working configuration settings](#). If there is a problem with the new settings, you have a backup of working settings to restore.



Task **To change validators configuration settings through the FlexNet Operations Producer Portal**

1. Click **System > Configure**.
2. Click **Validators** to open the configuration page for validators.
3. View or change the values of the settings below.
4. Click **Save Configs** to save changes.

The Producer Portal saves your configuration changes.

The validator settings include the following. Note that default values are listed as the first choice. Also, required fields are indicated with an asterisk.

Table 21-6 • Validator Configurations

Name	Possible Values	Description
User Password Length	4 or specify	Minimum number of characters allowed for a user password by default implementation.  <hr/> Note • You must provide a value.
User Password Requires Uppercase Character	Selected or unselected	Select to enable uppercase character requirement for a user password by default implementation. Default: Unselected
User Password Requires Numeric Character	Selected or unselected	Select to enable the requirement that a user password requires a number. Default: Unselected
Temporary Password Timeout	240 or specify	The amount of time, in minutes, for which a system-generated, temporary password is valid. (FlexNet Operations generates temporary passwords for new users and for users who forget their password.) The timeout period starts when the password is generated. For permanent (non-expiring) temporary passwords, set Temporary Password Timeout to 0. Default: 240 minutes (4 hours).  <hr/> Note • You must provide a value.
Lock out user upon repeated password reset attempts	Selected or unselected	Select to lock out a user for a set amount of time after successive failed password reset attempts. The number of consecutive failed attempts is defined under FlexNet Platform Server > Consecutive Failed Authentications . Default: Unselected
Lockout period after failed password reset attempts	30 or specify	The number of minutes a user is locked out before being allowed to reset their password. Default: 30 minutes

Table 21-6 • Validator Configurations

Name	Possible Values	Description
Lock out user upon repeated security question attempts	Selected or unselected	Select to lock out a user for a set amount of time after successive failed security question attempts. The number of consecutive failed attempts is defined under FlexNet Platform Server > Consecutive attempts to provide correct security answer . Default: Unselected
Lockout period after failed security question attempts	30 or specify	The number of minutes a user is locked out before allowed to answer the security question again. Default: 30 minutes

See Also

- [Configuring the FlexNet Platform Server](#)
- [Exporting a Configuration](#)
- [Importing a Configuration](#)

Configuring System Settings

A user must be assigned a role with the **View and Manage Configurations** permission to modify configuration settings for FlexNet Operations settings through the Producer Portal.



Note • Before changing any configuration settings in a working FlexNet Operations instance, it is advisable to [export the working configuration settings](#). If there is a problem with the new settings, you have a backup of working settings to restore.



Task *To change FlexNet Operations-specific configuration settings through the FlexNet Operations Producer Portal*

1. Click **System > Configure**.
2. Click **FlexNet Operations** to open the configuration page for FlexNet Operations-specific settings.
3. View or change the values of the settings below.
4. Click **Save Configs** to save changes.

The Producer Portal saves your configuration changes. Keep in mind that before certain settings are active in the Producer Portal, FlexNet Operations must be restarted.

Configuration options for FlexNet Operations appear in the following groups:

- [General Options](#)
- [External Services Configuration](#)

- [Embedded Device Settings](#)
- [Renewals](#)
- [Customer Growth](#)
- [Updates](#)

Required fields are indicated with an asterisk. Fields marked with the  icon require that the FlexNet Platform Server be restarted for their changes to take effect.

General Options

These settings correspond to the **General Options** section of the **FlexNet Operations** configuration page in **System > Configure**.

Table 21-7 ▪ FlexNet Operations: General Option Configurations





Name	Possible Values	Description
Max Recently Used Records	4 or specify	The number of recently used items to display in the product packaging pages.  Note - You must provide a value.
Description Max Length	15 or specify	Maximum number of characters in the description field displayed in tables.  Note - You must provide a value.
ID Generator Classname	com.flexnet.operations.generator.OpsEsnGenerator or specify	Set this parameter to the class that implements the com.flexnet.operations.publicapi.IDGenerator interface: It is used to generate entitlement IDs, activation IDs, and web register keys.  Note - You must provide a value.
Fulfillment ID Generator Classname	com.flexnet.operations.generator.OpsFIDGenerator or specify	Set this parameter to the Java class that implements com.flexnet.operations.publicapi.FulfillmentIDGenerator interface: It is used to generate fulfillment IDs and consolidated license IDs.  Note - You must provide a value.

Table 21-7 • FlexNet Operations: General Option Configurations

Name	Possible Values	Description
Host ID Validator	com.flexnet.operations. publicapi.HostIDValidator or specify	Set this parameter to the Java class that implements custom validations of host IDs.
Basic IP Address Host ID Validation	Selected or unselected	<p>Permits or prohibits basic validation of IP address values by FlexNet Operations.</p> <p>Default: Selected.</p> <p>When selected, FlexNet Operations and the VCG validate the octet values of IP addresses according to the special host id types validation rules.</p> <p>To disable IP address validation, unselect this setting and use a version 12.8.0.1 or later VCG configured to disable validation for internet host IDs. (Some minimal validation—requiring numeric values or asterisks—still occurs based on FlexNet Publisher requirements.)</p>
License File Name	license or specify	<p>This is the base name used to generated names for license files based on a custom license technology that is saved to disk or sent as an email attachment. These types of license files do not incorporate FlexNet capabilities. The default setting is license. If this field is left blank, the file name for a non-FlexNet license file or email attachment is license.lic.</p> <p>If the file name is set by the CustomGenerator class in the GeneratorResponse object, the system uses that file name.</p>
Allow License Headers and Trailers	Selected or unselected	Selecting this allows header and trailer text to be entered for products.
Always Display Page Count of Search Results	Selected or unselected	<p>Determining the number of pages of search results is often time consuming. Deselect this box to prevent automatic display of the number of pages returned. This reduces the time needed to load the landing pages for Entitle Customers, Activate Licenses, and Support Licenses.</p>

Table 21-7 • FlexNet Operations: General Option Configurations


Name	Possible Values	Description
Entitlement Records per Page	Number of records	Number of records displayed on the Entitle Customers landing page. This setting overrides the Default Records Per Page setting in the user interface configuration. Default: 10. 
		Note - You must provide a value.
Use SUPERSEDE or SUPERSEDE_SIGN Keyword	<p>None</p> <p>Use SUPERSEDE for Upgrade</p> <p>Use SUPERSEDE for Renewal</p> <p>Use SUPERSEDE for upgrade and renewal</p> <p>Use SUPERSEDE_SIGN for Upgrade</p> <p>Use SUPERSEDE_SIGN for Renewal</p> <p>Use SUPERSEDE_SIGN for upgrade and renewal</p>	<p>Select to use either SUPERSEDE or SUPERSEDE_SIGN for upgrade or renewal of licenses. You must carefully evaluate the risks before setting this flag. Refer to Using the SUPERSEDE and SUPERSEDE_SIGN Keywords to understand the risks.</p> <p>Default: None.</p> <p></p> <p>Note - By default, this option is hidden and not editable. Contact Reverera support if you want to change this value.</p>
Show Consolidate Licenses Functionality	Selected or unselected	Selecting this allows users to see functionality related to Consolidate Licenses. If you change the flag, you must log out and re-login for the changes to be effective.
Override Older Fulfillments on Host Using SUPERSEDE_SIGN Keyword	Selected or unselected	When fulfillment A is upgraded or renewed to create fulfillment B, if SUPERSEDE_SIGN keyword is enabled, licenses in fulfillment B supersede signatures in fulfillment A. If fulfillment B is upgraded or renewed to fulfillment C and this is selected, fulfillment C supersedes signatures from fulfillments A and B. Ensures that counts provided by fulfillment A are disabled even if user removes fulfillment B license from their server. However, this increases length of license line (limited to 4096 bytes).
Enable Host ID Policies	Selected or unselected	Selecting this allows host ID policies to be configured and enforced.

Table 21-7 • FlexNet Operations: General Option Configurations


Name	Possible Values	Description
Number of Allowed Retries	Number of retries	For the createLicense web service only: enter an integer value greater than zero to retry the createLicense transaction if there is a failure due to concurrent modification exception.
Allow Multiple Owners	Selected or unselected	If selected, multiple users are able to map a line item, web register key, or entitlement to themselves.
Do Not Sort Results by Default	Selected or unselected	If selected, search results are not sorted by Last Modified Date on Operations landing pages.
Show Line Items with Zero Copies by Default	Selected or unselected	Configures the End-User Portal to show line items with zero copies remaining on the Activatable Items and the Manage Entitlements pages. Default: Unselected.
Entitlement Certificate File Name	EntitlementCertificate.html or specify	Default file name used for the HTML entitlement certificate. The file extension should be either .html or .htm for browser display.
Email for On-Hold Fulfillments or On-Hold Entitlements	Valid email address	Enter an email address to notify when On-Hold fulfillment or On-Hold Entitlement is generated.
Send Email on Set License for On-Hold Fulfillments	Selected or unselected	Determines whether to send email to an end user while a license is set for on-hold fulfillments.
Drop Existing Supersede Signatures	Selected or unselected	When selected, drops old SUPERSEDE_SIGN signatures and ensures that license length cannot exceed 4096 bytes. This feature is available in VCG 12.0 or later.
Mapped Users or Account Records in Create Account and User Page	Number of records	Number of Mapped User or Account records displayed on the Create Account and User Page. This setting overrides the default Records Per Page setting in the User Interface configuration.
 Note • You must provide a value.		

Table 21-7 • FlexNet Operations: General Option Configurations

Name	Possible Values	Description
Filter UMN1 Keys	One or more UMN1 values	In some rare scenarios (For example, client machines using RAID disks), the UMN1 value is not unique. In these cases, UMN1 value is being set as the model type of the client machine, rather than its disk serial number. As UMN1 is treated as a primary identifier for re-installation requests, non-unique UMN1 values can lead to problems during reinstalls, returns and rehosts. In these cases, the machine identifier (MID) is a better host identifier. This parameter can be set to a comma separated list of UMN1 values. If the trusted storage activation request contains any of these values, FlexNet Operations ignores the UMN1 value and uses the MID instead.
Add Default Comment Line in License File	Selected or unselected	For FlexNet license files containing non-ASCII characters, the first line in the license file must be a comment line. This comment line is added by default by FlexNet Operations. If this comment line is causing issues with downstream applications, deselect this setting.
Enable Product Lines for Products, Users, and Accounts	Selected or unselected	<p>If selected, the Product Line feature is enabled for products, users, and accounts, including visibility restrictions for users and accounts.</p> <p>Producers can define product lines, assign products to product lines, and link producer accounts and customer user accounts with those product lines.</p> <p>When this setting is enabled, End-User Portal views are filtered to show only entitlement line items for products in product lines to which the user's account is linked.</p> <p>To enable product lines functionality without enforcing visibility restrictions, deselect this setting and check Enable Product Lines for Products, instead.</p> <p>Default: Unselected.</p>
Bulk Operation Batch Size	Number of records	<p>The number of SQL statements to group as a batch during a bulk operation.</p> 
<p>Note - You must provide a value.</p>		

Table 21-7 • FlexNet Operations: General Option Configurations





Name	Possible Values	Description
Bulk Operation 'Select All Line Items' Batch Size	Number of records	The number of entitlement line items to group as a batch.  <hr/> Note • You must provide a value.
Bulk Operation Retry	Number of attempts	Number of times to retry a bulk operation.  <hr/> Note • You must provide a value.
Bulk Operation Retry Sleep Interval	Number of seconds	The time, in seconds, to sleep before retrying a bulk operation.  <hr/> Note • You must provide a value.
Default Country for Users and Account Addresses	Unspecified or a two-letter country code (as specified by ISO 3166 guidelines)	A two-character country code that FlexNet Operations uses as the default country for users and accounts. Use Unspecified if you do not want FlexNet Operations to supply a default value.  <hr/> Note • You must provide a value.

Table 21-7 • FlexNet Operations: General Option Configurations

Name	Possible Values	Description
Allow Editing of Deployed Entities	Selected or unselected	<p>Permits some modification of product, suite, feature bundle, entitlement, and line item attributes post-deployment.</p> <p>Default: Unselected.</p> <p>When enabled, editing of the following elements is possible:</p> <ul style="list-style-type: none"> ● Products: name, version, package name, package version, feature/feature bundle list (can add to, or remove from list), and Can be used on a device? setting. ● Suites: name, version, package name, package version, product list (can add to, or remove from list), and Can be used on a device? setting. ● Feature bundles: name, version, and feature list (can add to, or remove from list). ● Entitlements ● Line items ● Custom attributes for license models <p>Note that inactive or obsolete entities cannot be changed.</p>
Send Email When New Entitlement Is Created After Split	Selected or unselected	<p>Configures FlexNet Operations to send a notification email when a new entitlement is created as the result of a split. (Entitlements can be split, by publisher and partner users, on the End-User Portal.)</p> <p>Default: Selected.</p>
By Default Show Product Information in the Select Host Page	Selected or unselected	<p>Shows product information on the Select License Host page (part of the Generate License wizard), both in the Producer Portal and in the End-User Portal. When you hide the product information FlexNet Operations still provides a link that, when clicked, shows the product information for a specific host.</p> <p>Default: Selected.</p>
Default Operator Used for Simple Search	Contains Equals Starts With Ends With	<p>Sets the default operator for simple searches in the Producer Portal.</p> <p>Default: Contains.</p>

Table 21-7 • FlexNet Operations: General Option Configurations


Name	Possible Values	Description
Always Attach Entitlement Certificate in Email	Selected or unselected	<p>Select to always attach an entitlement certificate to entitlement certificate emails.</p> <p>Default: Selected.</p>  <p>Note - When using the option Attach Entitlement Certificate for the Entitlement email template, Always Attach Entitlement Certificate in Email must be unselected.</p>
Enable Product Lines for Products	Selected or unselected.	<p>Show or hide product lines functionality for products only. No visibility restrictions for users and accounts are applied.</p> <p>When this setting is selected, producers can define product lines, assign products to product lines</p> <p>Requires that the configuration setting for Enable Product Lines for Products, Users, and Accounts be unselected.</p> <p>Default: Selected.</p>
Cloud License Service URL	test or specify	<p>The URL used when auto-provisioning a Cloud Licensing Service instance during entitlement creation. Intended to be used in entitlement creation emails.</p>
Data Extract File Location	flexnet-data\site or specify	<p>The relative path to the location where the output (artifact files) of optional data extract jobs are stored.</p> <p>For Data Extract File Location, specify a valid path on the local file system.</p> <p>For more information about scheduling data extract jobs, see Administering Alerts.</p>
Auto upgrade batch size	10 or specify	<p>Number of line items to be processed in a single transaction during automatic product upgrade. Defaults to 10.</p>

Table 21-7 • FlexNet Operations: General Option Configurations

Name	Possible Values	Description
Highlight Latest Upgrade Line Items	Selected or unselected	<p>By default, show only line items for the most recent version in the End-User Portal’s List Entitlements page and Map Entitlements page. Related, older version are grouped under the most recent version when related, older versions are available.</p> <p>When Highlight Latest Upgrade Line Items is unselected, the List Entitlements page and Map Entitlements page show a mixed, flat list of line items—including parent line items and older versions along with the most recent version.</p> <p>Default: Selected.</p>
Enable User Expiration	Selected or unselected	<p>Enables an expiration date when a user no longer has access to an account. This is applicable to all users except:</p> <ul style="list-style-type: none"> ● Contacts ● Shared login users <p>To disable the expiration date for all users, unselect the box. This prevents all users’ account access from expiring.</p>
Show environment with email subject	Selected or unselected	<p>Enables the addition of the environment in the subject of the email. If selected the name of the environment (UAT, CI, QA, etc., except PROD or DR) that triggered the email will be included in the subject line.</p> <p>Default: Unselected.</p>
Show maintenance line items custom attributes in Entitlements Page	Selected or unselected	<p>Controls whether custom attributes for maintenance lines are visible in the Producer Portal and End-User Portal in the following locations:</p> <ul style="list-style-type: none"> ● on the List Entitlements and List Entitlements By Order pages ● on the Maintenance Line Item Details panel <p>Default: Unselected (custom attributes for maintenance lines are not visible).</p>

Table 21-7 • FlexNet Operations: General Option Configurations

Name	Possible Values	Description
Apply Manage Users permission to users in shared accounts	Selected or unselected	<p>Manages the behavior when a customer user belongs to more than one account.</p> <p>If unselected, a customer user logged in at the End-User Portal cannot manage other customer users that belong to the same account. The List Users page in the End-User Portal lists the logged-in user's account, the accounts that the user has in common with other users as well as those users' other accounts (even if those are not shared with the logged-in user).</p> <p>If selected, a customer user logged in at the End-User Portal has Manage Users permissions (view, edit, reset password, link or remove an account) for other customer users that belong to the same account. The List Users page in the End-User Portal lists only accounts that the logged-in user has in common with users listed on the page.</p> <p>Default: Unselected</p>
Verify user ID validity during password reset	Selected or unselected	<p>If selected, the validity of the user ID is verified, and the user is only prompted to reply to a security question if they entered a valid user ID. If the entered user ID is invalid, an error is displayed.</p> <p>If unselected, the behavior is the same for valid and invalid user IDs: the user is prompted to select the answer to a security question. (If the entered user ID is invalid, a random question is displayed.)</p> <p>Default: Unselected</p>
Allow used entitlement/line item state change to Inactive or Obsolete	Selected or unselected	<p>Controls whether entitlements or line items that have been activated on a device can have their state changed to Inactive or Obsolete.</p> <p>When not selected, attempting to change such an entitlement's or line item's state to Inactive or Obsolete triggers an error message. The state can only be changed after the entitlement or line item has been unmapped from the device.</p> <p>When this configuration option is selected, an entitlement or line item that has been activated on a device can still be used until the license expires, even if the entitlement or line item has been deactivated or made obsolete.</p> <p>Default: Selected.</p>

Table 21-7 • FlexNet Operations: General Option Configurations

Name	Possible Values	Description
Preserve Product Custom Attributes when changing a Product Line	Selected or unselected	<p>Manages the behavior when a product line for a given product is changed.</p> <p>If selected, all custom attributes for a given product are preserved if the product line for the product is changed.</p> <p>Default: Selected.</p>
Remove licenses from CLS when line item state is changed to Inactive/Obsolete	Selected or unselected	<p>If selected, licenses mapped to CLS are removed when a line item's state is changed to Inactive or Obsolete (using the setLineItemState SOAP request).</p> <p>Requires that the configuration setting for Allow used entitlement/line item state change to Inactive or Obsolete be unselected.</p> <p>Default: Unselected.</p>
Process all line items in an Entitlement during Batch Rehost	Selected or unselected	<p>If selected, all line items in the entitlement are included for processing during batch rehost. In scenarios where a large number of line items are associated with a single entitlement, selecting this option might significantly increase the time required for processing the batch rehost.</p> <p>If unselected, only the default number of 10 line items are included for processing during batch rehost.</p> <p>Default: Unselected.</p>
Use Recaptcha validation when sending entitlement emails	Selected or unselected	<p>If selected, entitlement emails will only be sent after re-authentication using the Google reCAPTCHA mechanism.</p> <p>Requires that the configurations for Recaptcha Site key and Recaptcha Secret password be set.</p> <p>In this case, the List Entitlements email preview page of the Producer Portal shows the "I'm not a robot" check box which enables the user to send an entitlement email.</p> <p>Default: Unselected.</p>

Table 21-7 • FlexNet Operations: General Option Configurations

Name	Possible Values	Description
Show upgrade/upsell line items related to the license (activation ID)	Selected or unselected	<p>Enables producers to control which line items are displayed on the Support Licenses And Maintenance page in the Producer Portal and End-User Portal.</p> <ul style="list-style-type: none"> ● Unselected—During an upgrade or upsell operation, the Support Licenses And Maintenance page lists all upgrade or upsell line items that belong to a specified activation ID. ● Selected—During an upgrade or upsell operation, only child line items that are related to the upgraded or upsold activation ID are displayed on the Support Licenses And Maintenance page. <p>Default: Unselected.</p>
Send email when user is reactivated via web services	Selected or unselected	<p>Controls whether a notification email should be automatically triggered when a user is reactivated using the SOAP web services updateUser or createUser operation.</p> <p>Producers who enable this option should ensure that the User Enabled email template contains appropriate content, that it is active and that its Send Indicator is set to true.</p> <p>Default: Unselected.</p>
Show renew line items related to the license	Selected or unselected	<p>Controls which line items are displayed on the Support Licenses and Maintenance page for renewal operations in the FlexNet Operations Producer Portal and End-User Portal.</p> <p>If selected, only child line items that are related to the activation ID that is being renewed are displayed on the Support Licenses and Maintenance page in the Producer Portal and End-User Portal.</p> <p>Default: Unselected.</p>
Sort items on List Entitlements by Order page by creation date	Selected or unselected	<p>Enables producers to change the sort order of items displayed on the List Entitlements by Order page.</p> <p>If selected, the items on the List Entitlements by Order landing page are sorted by the date they were created. Producers who want items on the List Entitlements by Order landing page to be sorted by their last modified date (the default behavior) should leave the option unselected.</p> <p>Default: Unselected.</p>

Table 21-7 • FlexNet Operations: General Option Configurations

Name	Possible Values	Description
Display Password in Welcome Email Template	Selected or unselected	<p>Controls the use of the [[Password]] merge tag in the Welcome Email for Producer and Welcome Email for End User email templates.</p> <hr/> <p>Note - For security reasons, the welcome email should not contain a plain text password. Instead, it should contain a URL which enables the user to set (or reset) their password.</p> <p>If selected, the merge tag section in the welcome email templates displays the [[Password]] merge tag and allows the use of the merge tag. When a welcome email containing the [[Password]] merge tag is sent, the merge tag is substituted with the password.</p> <p>If unselected, the [[Password]] merge tag is not displayed in the merge tag section of the welcome email templates. In addition, if the [[Password]] merge tag is manually added to the welcome email, the merge tag is not substituted by the password.</p> <p>Default: Selected.</p>
Use ISO 8601 time format in extracts	Selected or unselected	<p>If selected, the date and time information in extracts is displayed using ISO 8601 format (YYYY-MM-DD"TT"hh:mm:ssZ).</p> <p>Default: Unselected.</p> <hr/> <p>Note - The configuration option applies to all data extract jobs with the exception of device data extracts. Date and time for this extract is presented in Pacific Standard Time (PST), even if Use ISO 8601 time format in extracts is enabled.</p>
Send entitlement email only for deployed entitlements	Selected or unselected	<p>If selected, an entitlement email is sent only if the entitlement and its line item(s) are in a Deployed state. If a deployed entitlement has line items in any other state (Inactive, Draft, Obsolete, or Test), only the deployed line items are included in the entitlement email.</p> <p>Default: Unselected.</p>

External Services Configuration

These settings correspond to the **External Services Configuration** section of the **FlexNet Operations** configuration page in **System > Configure**.

Table 21-8 • FlexNet Operations: External Service Configurations

Name	Possible Values	Description
Use Soap Service for VCG	Selected or unselected	Select to use the SOAP service for secure license generation, instead of the Windows VCG Service or the Linux VCG Service. Default: Unselected.
VCG Service soap URL	Valid URL	The URL of the SOAP service hosted by the producer. FlexNet Operations must be able to access this over the internet.
VCG Service User Name	Valid user name in the format domain/username	The user name used to authenticate the SOAP service for generating the secure license.
VCG Service User Password (Confirm)		The password for the user name used to authenticate the SOAP service for generating the secure license.
VCG service credential in SOAP request header		If selected, users are authenticated using SOAP header-based authentication instead of basic http authentication. Only available if Use Soap Service for VCG is selected. Default: Unselected.

Embedded Device Settings

These settings correspond to the **Embedded Device Settings** section of the **FlexNet Operations** configuration page in **System > Configure**.

Table 21-9 • FlexNet Operations: Embedded Device Settings

Name	Possible Values	Description
Allow Adding Backup Server for Producer	Selected or unselected	Allow or prevent adding backup servers via web services and Producer Portal.
Server Deployment Choice	Local Cloud Both	Select whether FlexNet Embedded server deployments can be local, cloud, or both.
Skip Account Check – for hosts (see next row for devices)	Selected or unselected	Hosts: If selected, allows a host to have line items belonging to multiple accounts.

Table 21-9 • FlexNet Operations: Embedded Device Settings

Name	Possible Values	Description
Skip Account Check – for devices (see previous row for hosts)	Selected or unselected	<p>Devices: Controls sharing of devices across accounts. By default, FlexNet Operations applies rules to limit the mapping of entitlements to devices based on the device owner account.</p> <p>Generally, enabling Skip Account Check permits entitlements that belong to accounts other than the device owner and its sub-accounts to be mapped to a device. (See About Device Management for more information.)</p> <p>Unselected (Default)</p> <p>The FlexNet Embedded license generator executes the activation request when</p> <ul style="list-style-type: none"> the device is owned by the same account as activation ID the device is owned by the parent account and the activation ID is owned by one of its child accounts <p>The FlexNet Embedded license generator produces an error when the activation ID is owned by the parent account and the device is owned by one of its child accounts.</p> <p>Selected</p> <p>The FlexNet Embedded license generator executes the activation request without regard to the account that owns the device.</p>
Auto-provision error email recipient(s)	Valid email address	Comma-separated email IDs that receive any error emails related to auto-provisioning.
Device user option	Off (default) On with no validation On with validation	Select to offer the option to assign a user to a device, as well as whether the system checks the validity of the user.
Override license expiration date	Selected or unselected	If selected, allows user to shorten license expiration term.
Enable Producer User for CLS	Selected or unselected	If selected, allows a user to reset the Cloud Licensing Service producer user password for both existing and future Cloud License Server (CLS) instances. This producer password can be used to obtain Authorization tokens for all instances.

Table 21-9 • FlexNet Operations: Embedded Device Settings

Name	Possible Values	Description
Producer User's Password for CLS (Confirm)	Password fulfilling the requirements	<p>The Cloud Licensing Service password must fulfill the following requirements:</p> <ul style="list-style-type: none"> ● 8-30 characters ● 1 uppercase character ● 1 lowercase character ● 1 digit ● 1 of the following special characters: (^*\$-+?_&=!%{}/#) ● No spaces
Prepopulate quantity to add with available count in Map by Activation IDs page	Selected or unselected	<p>Select if the Qty to add field—located on the Map by Activation IDs page in the Producer Portal and End-User Portal—should show the maximum license count that is available to the end-user.</p> <p>When unselected, the Qty to add field is blank and requires the user to type in the desired license count.</p> <p>Default: Selected.</p>
Update entitlement last modified date	Selected or unselected	<p>When selected, an entitlement's last modified date is updated together with the line item's last modified date whenever the available license count changes for a device.</p> <p>When unselected, only the line item's last modified date changes when the available license count changes for a device.</p> <p>Default: Unselected.</p>
Allow feature override changes to be published to a License Server	Selected or unselected	<p>When selected, changes to feature overrides are reflected on the relevant license server instance of the FlexNet Cloud Licensing Service.</p> <p>The Client Uniqueness parameter is not used in FlexNet Embedded licensing, therefore any updates to this field do not impact the Cloud Licensing Service.</p> <div style="border: 1px solid black; width: 20px; height: 20px; display: flex; align-items: center; justify-content: center; margin: 10px 0;"> v </div> <p>Important - If you are changing the feature override parameter Counted from Yes to No, you also need to unmap and remap the add-on licenses for the existing Cloud Licensing Service instances.</p>

Table 21-9 • FlexNet Operations: Embedded Device Settings




Name	Possible Values	Description
Allow feature bundle changes to be published to a License Server	Selected or unselected	<p>When selected, changes made to feature bundles—either through the UI or via a SOAP request—are reflected on the relevant instance of the FlexNet Cloud Licensing Service.</p> <p>The following changes are fed through to the Cloud Licensing Service instance:</p> <ul style="list-style-type: none"> • A feature is added to the feature bundle • A feature is removed from the feature bundle • The quantity of one or more features in a bundle changes. <p>Default: Unselected.</p>
Enable feature count aggregation	Selected or unselected	<p>Shows or hides the Aggregation Type field on the Package Products Create a Feature page, which enables you to select an aggregation type for feature count aggregation.</p> <p>For more information, see Creating a Feature and Using Feature Count Aggregation.</p> <p>Default: Selected.</p> <hr/> <p> Note • When using the option Enable feature count aggregation, the option Consolidate Licenses (under System > Configure > Embedded Devices > Host Options) must be unselected.</p> <hr/> <p> Important • The configuration option Enable feature count aggregation merely shows or hides the Aggregation Type field. It does not enable or disable the feature count aggregation functionality itself.</p> <p>Therefore, if you specified aggregation types for certain features but then decide not to use the feature count aggregation functionality, you must set the Aggregation Type field to NONE for each feature. If the Aggregation Type field remains set to SUM or MAX, FlexNet Operations will continue to aggregate feature counts, even if Enable feature count aggregation is disabled.</p>

Table 21-9 • FlexNet Operations: Embedded Device Settings

Name	Possible Values	Description
Allow mapping of expired entitlements	Selected or unselected	<p>Select to allow expired activation IDs to pass the validation so that they can be sent to the License Fulfillment Service for mapping.</p>  <p>Important • This configuration option only works in conjunction with the option Allow expired line items to be mapped to devices or servers (under System > Configure > Embedded Devices > Host Options). To allow mapping of expired activation IDs to devices, both options must be selected.</p>
Allow an upgrade line item to be mapped to a device via the FlexNet Embedded client SDK	Selected or unselected	<p>If selected, mapping a parent activation ID via a FlexNet Embedded client SDK to a standalone device succeeds even if there are no line items remaining.</p> <p>This configuration is relevant in scenarios like the following:</p> <p>A producer creates a parent line item and activates it using a FlexNet Embedded client SDK. This action creates a device and maps the parent line item. When the producer then creates an upgrade line item and activates the line item on the same device, the parent line item is removed, as expected. If the producer then attempts to map the same parent line item to another device, the mapping succeeds (if option is selected) or is rejected (if option is unselected).</p> <p>Default: Selected.</p>

Renewals

These settings correspond to the **Renewals** section of the **FlexNet Operations** configuration page in **System > Configure**. For producers who use FlexNet Operations with the FlexNet Customer Growth module, these settings determine how FlexNet Operations behaves when the Expiring Entitlements job or Expired Entitlements job runs. These settings are required for producers who use FlexNet Operations with the FlexNet Customer Growth module; otherwise, they are not used.



Note ▪ For more information about using the Expiring Entitlements and Expired Entitlements jobs, see [Administering Alerts](#).

Table 21-10 ▪ FlexNet Operations: Renewal Configurations

Name	Possible Values	Description
Renewal Look Ahead	200 or specify. Default: 200 days.	<p>The number of days in the future, including the day the Expiring Entitlements job runs, to search for entitlements to include in the Renewal Reminder email message.</p> <p>This value is also used as the upper limit for line items that appear on the Expiring Entitlements page in the End-User Portal. Those entitlements with expiration dates further out than the Renewal Look Ahead are excluded from the list.</p>



Note ▪ This setting is also used to limit the number of **expired** entitlements shown on pages that list expired entitlements. Entitlements that are more than 200 days (using the default setting) past their expiration date are not shown.



Tip ▪ The Renewal Look Ahead value must be greater than the Expiring Window value.



Note ▪ You must provide a value.

Table 21-10 • FlexNet Operations: Renewal Configurations




Name	Possible Values	Description
<p>Expiring Window</p>	<p>90 or specify. Default: 90 days.</p>	<p>The number of days in the future, including the day the Expiring Entitlements job runs, to search for entitlements that are soon to expire.</p> <p>Together with the Expiring Email Frequency, Expiring Window determines whether or not FlexNet Operations sends a Renewal Reminder email message. See More About the Expiring Entitlements Job for details.</p> <p>This value and the Renewal Critical value determine the way line items are highlighted on the Expiring Entitlements page in the End-User Portal. Line items that expire in the span between the Renewal Critical setting and the Expiring Window setting are highlighted in yellow.</p> <hr/> <p> Tip • The Expiring Window value must be smaller than the Renewal Look Ahead value.</p> <hr/> <p> Note • You must provide a value.</p>
<p>Expiring Email Frequency</p>	<p>30 or specify. Default: 30 days.</p>	<p>The minimum number of days to wait before sending out the next Renewal Reminder email message to a particular account.</p> <p>For example, using the default system configuration settings, FlexNet Operations limits the number of renewal reminders sent to an account to one every 30 days.</p> <p>Together with the Expiring Window, Expiring Email Frequency determines whether or not FlexNet Operations sends a Renewal Reminder email message. (Renewal Reminder email messages are based on the Renewal Reminder email template.)</p> <p>See More About the Expiring Entitlements Job for details.</p> <hr/> <p> Note • You must provide a value.</p>

Table 21-10 • FlexNet Operations: Renewal Configurations




Name	Possible Values	Description
Expired Email Frequency	30 or specify. Default: 30 days.	<p>The minimum number of days to wait before sending out the next expired entitlements message to a particular account.</p> <p>If FlexNet Operations has sent an expired entitlements message to an account within the number of days specified, no new email messages are sent, even if newly expired entitlements are discovered when the Expired Entitlements job runs. (Expired entitlements messages are based on the Renewal Reminder for Expired Entitlements email template.)</p> <p>See More About the Expired Entitlements Job for details.</p> 
Note		<p>Note • You must provide a value.</p>
Renewal Critical	30 or specify. Default: 30 days.	<p>Number of days from an entitlement’s expiration date to mark the entitlement as critical.</p> <p>This value and the Expiring Window value determine the way line items are highlighted on the Expiring Entitlements page in the End-User Portal. Line items that expire within the number of days specified in the Renewal Critical setting are highlighted in red.</p> 
Note		<p>Note • You must provide a value.</p>
Request Renewal Notification Email	Valid email address	<p>An email address, managed by the producer, to which an end user’s intent-to-renew messages are sent.</p> <p>In the End-User Portal, the Expiring Entitlements page includes a Request button. When an end user selects expiring entitlements and clicks Request, the End-User Portal sends an intent-to-renew message (based on the Renewal Intent for End Customer email template) to the email address you specify here.</p> <p>Request Renewal Notification Email is optional.</p> <p>The Renewal Callout and the Request Renewal Notification Email are not mutually exclusive. If both are present, FlexNet Operations runs the callout code and sends an email to the address indicated by Request Renewal Notification Email. If neither setting has a value, the Request button is suppressed in the End-User Portal.</p>

Table 21-10 ▪ FlexNet Operations: Renewal Configurations

Name	Possible Values	Description
Renewal Failed Notification Email	Valid email address	An email address to which FlexNet Operations sends renewal notifications when an account with expiring or expired entitlements has no end users who have subscribed to receive renewal reminders. Producers can use this address to receive the renewal reminders on behalf of their customer accounts.
Renewal Callout	Classname or URL	Optionally identify a callout to use when an end user clicks the Request button on the End-User Portal's Expiring Entitlements page. Specify a callout as an external SOAP endpoint that implements the RenewalService interface. (Click the Test Connection button to verify connectivity between FlexNet Operations and your endpoint.)
		 <p>Version ▪ <i>The Renewal Callout and the Request Renewal Notification Email are not mutually exclusive. If both are present, FlexNet Operations runs the callout code and sends an email to the address indicated by Request Renewal Notification Email. If neither setting has a value, the Request button is suppressed in the End-User Portal.</i></p>

Customer Growth

These settings correspond to the **Customer Growth** section of the **FlexNet Operations** configuration page in **System > Configure**.

Table 21-11 ▪ FlexNet Operations: Customer Growth Configurations

Name	Possible Values	Description
Consumption Thresholds (Low,High)	0-100,0-100 Default: 30,70	The low and high markers for service consumption levels. Consumption is considered unhealthy if below the low threshold and very healthy if at or above the high threshold.
Renewal Health Thresholds (Low,High)	0-100,0-100 Default: 30,70	The low and high markers for a customer's renewal health. A low renewal health score is indicative of a risky renewal. A renewal health at or above the high mark translates to a high probability of the renewal.
Account Health Thresholds (Low,High)	0-100,0-100 Default: 30,70	The low and high markers for an account's overall health. The account is considered unhealthy if below the low threshold and very healthy if at or above the high threshold.
Alert Period	0-30 Default: 5	The period in days to wait before generating another alert for the same account and score type.

Table 21-11 ▪ FlexNet Operations: Customer Growth Configurations

Name	Possible Values	Description
Enable running health aggregation job on demand	Selected or unselected	Enables the health aggregation job to be run for this specific tenant on demand.

Updates

These settings correspond to the **Updates** section of the **FlexNet Operations** configuration page in **System > Configure**.

Table 21-12 ▪ FlexNet Operations: Updates Configurations

Name	Possible Values	Description
Platforms		Comma separated list of custom platforms which are available for an Update when defining the Release To packages.

See Also

[Performing System Configuration](#)
[Configuring End-User Portal Settings](#)
[Exporting a Configuration](#)
[Importing a Configuration](#)

Configuring Trusted Activation Settings

A user must be assigned a role with the **View and Manage Configurations** permission to modify configuration settings for Trusted Activation settings through the Producer Portal.



Note ▪ Before changing any configuration settings in a working FlexNet Operations instance, it is advisable to [export the working configuration settings](#). If there is a problem with the new settings, you have a backup of working settings to restore.



Task **To configure trusted activation settings**

1. Click **System > Configure**.
2. Click **Trusted Storage** to open the configuration page for trusted activation.
3. View or change the values of the settings below.
4. Click **Save Configs**.

The Producer Portal saves your configuration settings. Required fields are indicated with an asterisk.

Table 21-13 - Trusted Storage Configurations


Name	Possible Values	Description
Do not delete Generated Trusted Configurations, ASRs, and Key Files	Selected or unselected	Select to prevent the deletion of generated files stored in <User Data Directory as configured in the configurator> store. These files are generated when the first activation is requested using a new transaction key.
Load Web Register Keys as Part of Trusted Type Bulk Entitlements Activation	Selected or unselected	Select to prevent pre-loading of web register keys for bulk entitlements using a trusted license model. Web register keys are loaded dynamically at the time of activation. This setting does not affect bulk entitlements using a certificate-based license models. Those web register keys are always pre-loaded.
Enable Bulk Entitlement Linking while Creating Short Code	Selected or unselected	Select to link a bulk entitlement when creating a short code ASR. This only allows keyboard (short code) activation with bulk entitlement.
Unwrap License Lines for Trusted Activations	Selected or unselected	In some network transport scenarios, new line between INCREMENT lines in trusted storage response XML file is stripped during transport, causing license to be invalid. In these cases, license is not applied to trusted storage. Select to remove new lines from license and sign response to prevent this problem.
Enable Internet Address Binding	Selected or unselected	Determines whether or not to use internet address as one of the binding elements for every transaction key created.
		 <p>Caution - Use caution when changing this configuration option. Changing the binding elements may change trusted configurations and fulfillment records on your end users' machines. Such changes can result in otherwise unnecessary repair requests.</p> <p>Default: Unselected.</p>
Send Host Address and Port Number in the Activation Response	Selected or unselected	Determines whether or not activation responses include a host address and port number.
		Default: Selected.

Table 21-13 • Trusted Storage Configurations

Name	Possible Values	Description
Force Default Transaction Key for all FNP versions	Selected or unselected	<p>Forces the use of a default transaction key rather than a virtualization-aware transaction key for all trusted activations.</p> <p>Select to use default transaction keys from both physical and virtual machines. When selected, FlexNet Operations does not require virtualization-aware transaction keys for activations originating from virtual machines.</p> <p>Leave unselected to allow trusted activations from earlier, supported FlexNet Publisher versions to use virtualization-aware transaction keys when the activation originated from a virtual machine (and a VMID is present).</p> <p>Default: Unselected</p>
Server Chain Host Name	URI or blank	<p>Enter a URI in the format <code>protocol://hostname:port/...</code> which is sent in activation responses. If blank, the URI sent in the activation responses is the actual server name.</p> <p>Default: Blank.</p>
Add Version in Product ID	Selected or unselected	<p>Select to add version information as part of product ID in <code>NAME=PRODUCT;VERSION=PROD_VERSION</code> format.</p> <p>Default: Selected</p>
Enable short code for license server	Selected or unselected	<p>Select to create short code for a license server.</p> <p>Default: Unselected</p>

Configuring Public Services Settings

A user must be assigned a role with the **View and Manage Configurations** permission to modify configuration settings for Public Services settings through the Producer Portal.



Note • Before changing any configuration settings in a working FlexNet Operations instance, it is advisable to [export the working configuration settings](#). If there is a problem with the new settings, you have a backup of working settings to restore.



Task To configure public services settings

1. Click **System > Configure**.
2. Click **Public Services** to open the configuration page for public services settings.
3. View or change the values of the settings below.

4. Click **Save Configs**.

The Producer Portal saves your configuration changes.

Table 21-14 ▪ Public Service Configurations

Name	Possible Values	Description
Publish LineItemDetails Public Service	Selected or unselected	Select to enable an activation application to query for line item information based on activation ID.
Publish EntitlementDetails Public Service	Selected or unselected	Select to enable activation application to query for entitlement information based on entitlement ID.

See Also

- [Performing System Configuration](#)
- [Exporting a Configuration](#)
- [Importing a Configuration](#)

Configuring End-User Portal Settings

A user must be assigned a role with the **View and Manage Configurations** permission to modify configuration settings for the End-User Portal through the Producer Portal.



Note ▪ Before changing any configuration settings in a working FlexNet Operations instance, it is advisable to [export the working configuration settings](#). If there is a problem with the new settings, you have a backup of working settings to restore.

This section includes the following sub-sections with instructions for changing End-User Portal settings and descriptions of different End-User Portal setting groups:

- [Changing End-User Portal Settings](#)
- [General Options](#)
- [Login Page](#)
- [Portal Navigation](#)
- [End-User Portal Home Page](#)
- [Entitlements Page](#)
- [Bulk Entitlements Page](#)
- [License Support Page](#)
- [Devices Page](#)
- [Downloads Page](#)
- [Recent Releases](#)
- [Recent Files Page](#)

- [Download Order Page](#)
- [Download Packages Page](#)
- [Manage Accounts & Users](#)
- [Custom Branding](#)

Changing End-User Portal Settings

Follow the instructions, below, to change the settings that govern the appearance and behavior of your End-User Portal.



Task

To configure the End-User Portal

1. Click **System > Configure**.
2. Click **End-User Portal Setup** to open the configuration page for the End-User Portal.
3. Make any setting changes that suit your configuration needs. Consult the tables, below, for additional information about the settings in each section.
4. Click **Save Configs** to save changes.

The Producer Portal saves your configuration changes.



General Options

These settings correspond to the **General Options** section of the **End-User Portal Setup** page in **System > Configure**.

Table 21-15 ▪ End-User Portal: General Options Configurations

Name	Possible Values	Description
Transferred Items Set to <i>On Hold</i>	Selected or unselected	Set the state of items transferred in the End-User Portal to On Hold and send an email to the FlexNet Operations administrator to approve the transfer by releasing the hold.
Enable Auto Login	Selected or unselected	Select to enable an end user to log in to the portal by passing an activation ID or entitlement ID in the login URL.
Hide Header	Selected or unselected	Hides the header in all pages of portal. Select to enable when End-User Portal is embedded into an external portal.
Skip Home Page	Selected or unselected	Skips the Home page after a user logs in and proceeds directly to the List Entitlements page.




Table 21-15 ▪ End-User Portal: General Options Configurations

Name	Possible Values	Description
Resource Bundle Time-to-Live	30 or specify	<p>Reload the resource bundle cache at this time interval (minutes). Specify the number of minutes between resource bundle cache reloads.</p>  <hr/> <p>Note ▪ You must provide a value.</p>
Enable Self-Registration for an existing Account	Selected or unselected	<p>Select to enable an end user to be associated with an existing Self-Registered account when they self-register in the End-User Portal with an entitlement ID or activation ID.</p>
Enable terms and conditions panel	Selected or unselected	<p>Show or hide the Privacy Terms and Conditions link on the Register for Account page for self-registering users. If enabled, users are reminded to read the privacy terms and conditions when they click Complete on the Register for Account page. When a user clicks the link, the Privacy Terms and Conditions are opened in a new tab. Customers are not required to acknowledge that they have read the Privacy Terms and Conditions.</p>
Terms and conditions URL	Specify	<p>If you selected Enable terms and conditions panel, enter the URL to the Privacy Terms and Conditions that a self-registering user should read before registering.</p>
Show Download Button	Selected or unselected	<p>Show or hide the Download button on the Downloads tab on the device's default view. If selected, the Download button enables a user to download entire download packages or individual files contained in a download package.</p> <p>Requires that the configuration setting Hide Download Manager (in the Downloads Page section) be unselected and Show Downloads Tab (in the Devices Page section) be selected.</p> <p>Default: Unselected.</p>  <hr/> <p>Version ▪ This setting is only available for producers who use the Software Delivery module.</p>

Login Page

These settings correspond to the **Login Page** section of the **End-User Portal Setup** page in **System > Configure**.

Table 21-16 ▪ End-User: Portal Login Page Configurations

Name	Possible Values	Description
Hide Register Link	Selected or unselected	Hides the Register link for self-service registration near Log In .
Hide Log in With Entitlement ID Option	Selected or unselected	Hides With Entitlement ID link in the login page.  Important ▪ Hiding any two login methods removes the option box from the login form.
Hide Log in With Activation ID Option	Selected or unselected	Hides With Activation ID link in the login page.  Important ▪ Hiding any two login methods removes the option box from the login form.
Hide Log in With User Name Option	Selected or unselected	Hides With User Name link in the login page.  Important ▪ Hiding any two login methods removes the option box from the login form.

Portal Navigation

The settings correspond to the **Portal Navigation** section of the **End-User Portal Setup** page in **System > Configure**.

Table 21-17 ▪ End-User Portal: Navigation Configurations

Name	Possible Values	Description
Hide Top-level Navigation	Selected or unselected	Hides the top-level navigation/menu in all pages of portal. Select to hide navigation/menu when End-User Portal is embedded into an external portal.
Hide System Help	Selected or unselected	Hides the system help links in the top-level navigation.
Hide Home Button	Selected or unselected	Hides Home in the top-level navigation.
Hide Activation & Entitlements Menu	Selected or unselected	Hides the Activation & Entitlements menu in the top-level navigation.

Table 21-17 • End-User Portal: Navigation Configurations

Name	Possible Values	Description
Hide Claim Activation IDs Link	Selected or unselected	Hides the Claim Activation IDs link in the Activation & Entitlements menu.
Hide Devices Menu	Selected or unselected	Hides the Devices menu in the top-level navigation.
Hide Accounts & Users Menu	Selected or unselected	Hides the Accounts & Users menu in the top-level navigation.  Important • Selecting this option overrides the Show List All Administrators Link option.
Hide Host Transfer Jobs Link	Selected or unselected	For customer users, hides the Host/Device Transfer Jobs links in the License Support menu.
Hide Downloads Menu	Selected or unselected	Hides the Downloads menu in the top-level navigation.
Hide List Downloads Link	Selected or unselected	Hides the List Downloads link in the Downloads menu.
Hide Recent Files Added Link	Selected or unselected	Hides the Recent Files Added link in the Downloads menu.
Hide Recent Releases Link	Selected or unselected	Hides the Recent Releases link in the Downloads menu.
Hide Usage Menu	Selected or unselected	Hides the Usage menu in the top-level navigation.
Hide License Support Menu	Selected or unselected	Hides the License Support menu in the top-level navigation.
Show List All Administrators Link	Selected or unselected	If selected, shows the List all administrators link in the Accounts & Users menu. This enables the end-user to see the linked names of their account administrators in the End-User Portal and contact them by email. Requires that the Roles for Administrator configuration option (under Manage Accounts & Users) be populated and that Hide Accounts & Users Menu be unselected.  Note • The List all administrators link only appears for users with roles that include the End-User Portal permissions View Accounts or View Users .

End-User Portal Home Page

These settings correspond to the **Portal Home Page** section of the **End-User Portal Setup** page in **System > Configure**.

Table 21-18 ▪ End-User Portal: Home Page Configurations

Name	Possible Values	Description
Hide Recent Entitlements Widget	Selected or unselected	Hides the Recent Entitlements panel on the Home page.
Hide Recent Releases Widget	Selected or unselected	Hides the Recent Releases panel on the Home page.
Hide Recent Files Widget	Selected or unselected	Hides the Recent Files panel on the Home page.
Hide Downloads Widget	Selected or unselected	Hides the Downloads panel on the Home page.
Hide Announcements Widget	Selected or unselected	Hides the Announcements panel on the Home page. See Managing Custom Content for information about publishing announcements to the home page.
Hide Quick Links Widget	Selected or unselected	Hides the Quick Links panel on the Home page.

Entitlements Page

These settings correspond to the **Entitlements Page** section of the **End-User Portal Setup** page in **System > Configure**.

Table 21-19 ▪ End-User Portal: Entitlements Page Configurations

Name	Possible Values	Description
Hide Activate	Selected or unselected	Hides the Actions > Activate link on the Entitlements page.
Hide Trusted activate	Selected or unselected	Hides the Actions > Trusted activate link on the Entitlements page. For producers that support only trusted storage activation, hiding the Trusted Activate link prevents users from activating anything from the End-User Portal. However, the short code activation link is still shown and is usable.
Hide Transfer	Selected or unselected	Hides the Action > Transfer link on the Entitlements page.
Hide Split	Selected or unselected	Hides the Action > Split link on the Entitlements page.

Table 21-19 ▪ End-User Portal: Entitlements Page Configurations

Name	Possible Values	Description
Hide Short Code Activation	Selected or unselected	Hides the Action > Short Code Activation link on the Entitlements page.
Hide Print	Selected or unselected	Hides the View > Print link on the Entitlements page.
Hide View Certificate	Selected or unselected	Hides the View > View certificate link on the Entitlements page.
Hide Email	Selected or unselected	Hides the View > Email link on the Entitlements page.
Hide Claim Activation IDs	Selected or unselected	Hides the Action > Claim Activation IDs link on the Entitlements page.
Hide Export Button	Selected or unselected	Hides the Export button on the Entitlements page.
Show View Download Packages	Selected or unselected	If selected, shows the View > View Download Packages link on the Entitlements page. Default: Unselected.

Bulk Entitlements Page

These settings correspond to the **Bulk Entitlements Page** section of the **End-User Portal Setup** page in **System > Configure**.

Table 21-20 ▪ End-User Portal: Bulk Entitlements Page Configurations

Name	Possible Values	Description
Hide View Web Register Keys Button	Selected or unselected	Hides the View > View Web Register Keys link on the Bulk Entitlements page. Default: Unselected.

License Support Page

These settings correspond to the **License Support Page** section of the **End-User Portal Setup** page in **System > Configure**.

Table 21-21 ▪ End-User Portal: License Support Page Configurations

Name	Possible Values	Description
Hide Return	Selected or unselected	Hides the Action > Return link on the License Support page.
Hide Rehost	Selected or unselected	Hides the Action > Rehost link on the License Support page.
Hide Repair	Selected or unselected	Hides the Action > Repair link on the License Support page.

Table 21-21 • End-User Portal: License Support Page Configurations

Name	Possible Values	Description
Hide Upgrade	Selected or unselected	Hides the Action > Upgrade link on the License Support page.
Hide Upsell	Selected or unselected	Hides the Action > Upsell link on the License Support page.
Hide Renew	Selected or unselected	Hides the Action > Renew link on the License Support page.
Hide Manual Return	Selected or unselected	Hides the Action > Manual Return link on the License Support page.
Hide Manual Repair	Selected or unselected	Hides the Action > Manual Repair link on the License Support page.
Hide Save to File	Selected or unselected	Hides the View > Save to File on the License Support page.
Hide Email License	Selected or unselected	Hides the View > Email License link on the License Support page.
Hide Shipment Records	Selected or unselected	Hides the View > Shipment Records link on the License Support page.
Hide View Fulfillments Button	Selected or unselected	Hides the View > View Fulfillments button on the License Support/Consolidate Licenses page.
Hide Print	Selected or unselected	Hides the View > Print link.
Hide Export Menu	Selected or unselected	Hides the Export menu above lists of licenses.
Hide Consolidate Link	Selected or unselected	Hides the Action > Consolidate link on the License Support page.
Hide Verify	Selected or unselected	Hides the Action > Verify link (shown when user generates a license).
Hide Transfer Licenses	Selected or unselected	Hides the Action > Transfer Licenses link on the License Support and Manage Hosts pages.
Hide Product Version Details	Selected or unselected	Hides the Product Version details for activatable line items on all pages. Select the check box to prevent the product version from being rendered in the Product column after the product name.
Hide Batch Rehost	Selected or unselected	For customer users, hides the Action > Batch Rehost link.
Hide Short Code Return	Selected or unselected	Hides the Action > Short Code Return link on the License Support page.

Table 21-21 ▪ End-User Portal: License Support Page Configurations

Name	Possible Values	Description
Hide Short Code Repair	Selected or unselected	Hides the Action > Short Code Repair link on the License Support page.
Hide List Hosts Link	Selected or unselected	Hides the List Hosts link in the License Support menu.

Devices Page

These settings correspond to the **Devices Page** section of the **End-User Portal Setup** page in **System > Configure**.

Table 21-22 ▪ End-User Portal: Devices Page Configurations



Name	Possible Values	Description
Hide View History Button	Selected or unselected	Hides View History option on the device's default view.
Hide Download Capability Response Link	Selected or unselected	Hides the Download Capability Response link in the Action menu for the device's default view and View Server pages.
Allow Standalone Device Creation	Selected or unselected	Allows creation of standalone devices in the End-User Portal. If Allow Standalone Device Creation and Allow Server Device Creation are unselected, the Create Device menu item and button are hidden.
Allow Server Device Creation	Selected or unselected	Allows creation of server devices in the End-User Portal. If Allow Standalone Device Creation and Allow Server Device Creation are unselected, the Create Device menu item and button are hidden.
Hide Move Button	Selected or unselected	Hides the Move Device button in the Action menu on the device's default view.
Allow Device Name Editing	Selected or unselected	Allows editing of device name in the End-User Portal.
Display Site Name in Devices Page	Selected or unselected	Displays the Site Name attribute on the Devices page. 
		Note ▪ <i>You must provide a value.</i>
Enable Return Device/Server	Selected or unselected	Allows devices and servers to be returned via the End-User Portal.

Table 21-22 • End-User Portal: Devices Page Configurations

Name	Possible Values	Description
Allow Backup Server ID Editing	Selected or unselected	Allows End-User Portal users to add backup servers.
Display vendor dictionary information in Devices page	Selected or unselected	<p>Controls whether vendor dictionary information is visible on the device's default view in the End-User Portal.</p> <p>Default: Selected (vendor dictionary information is visible on the device's default view).</p>
Show Downloads Tab	Selected or unselected	<p>Controls whether the Downloads tab is visible on the device's default view. If selected, the Downloads tab shows all downloads that are available for a standalone device.</p> <p>Default: Unselected.</p>
		
		<p>Version • This setting is only available for producers who use the <i>Software Delivery</i> module.</p>
Enforce device management permissions across accounts	Selected or unselected	<p>Controls the capabilities available on the Device Details page. When selected, a user belonging to more than one account will have their permissions to view or manage devices enforced according to the account that owns the device.</p> <p>Default: Unselected.</p>
Show entitlements owned by the Device Owner Account	Selected or unselected	<p>Controls which entitlements are displayed on the Map Entitlements page for the logged-in user in scenarios where the user belongs to multiple accounts.</p> <p>Select if the Map Entitlements page should only list entitlements that belong to the owner of the device.</p> <p>If unselected, the Map Entitlements page lists all entitlements of the logged-in user.</p> <p>Default: Unselected.</p>


Downloads Page

These settings correspond to the **Downloads Page** section of the **End-User Portal Setup** page in **System > Configure**.

Table 21-23 ▪ End-User Portal: Downloads Page Configurations

Name	Possible Values	Description
Show File Count	Selected or unselected	Show or hide the download file count on the Download page. Select the check box to have the End-User Portal show how many times each file has been downloaded.
Hide Download Log Tab	Selected or unselected	Show or hide the Download Log tab on the Downloads page. Select the check box to hide the Download Log tab.
Hide Notification Log Tab	Selected or unselected	Show or hide the Notification Log tab on the Downloads page. Select the check box to hide the Notification Log tab.
Hide Date Added	Selected or unselected	Show or hide the Date Added column in the Files list. Select the check box to hide the Date Added column.
Hide Extended File Description	Selected or unselected	Show or hide the extended file description in the expanded file details. Select the check box to hide the extended file description.
Hide Custom Attributes	Selected or unselected	Show or hide custom file attributes in the expanded file details. Select the check box to hide custom attributes.
Hide File Checksums	Selected or unselected	Show or hide the checksum values in the expanded file details. Select the check box to hide the checksums attribute.
Show Download Package Version	Selected or unselected	Show or hide the version number for each download package next to the download package name above the file list on the Download List page. Note that download packages are not required to have a version. If no download package version is available, no download package version appears in the End-User Portal. Select the check box to show the download package version numbers.
Hide File Details	Selected or unselected	Show or hide all additional file details in the expanded file details. Select the check box to hide all such details.
Show Order Media	Selected or unselected	Show or hide Order Media on the Downloads page. Order Media enables End-User Portal users to request copies of the files to which they are entitled on physical media.

Table 21-23 ▪ End-User Portal: Downloads Page Configurations

Name	Possible Values	Description
Order Media Request Recipient	Specify	The email destination for the Order Media request messages. Set the email address the End-User Portal uses when an end user wants to order physical media. 
Note ▪ You must provide a value.		
Hide Download Manager	Selected or unselected	Show or hide the Download Selected Files button on the Download List page.

Recent Releases

These settings correspond to the **Recent Releases** section of the **End-User Portal Setup** page in **System > Configure**.

Table 21-24 ▪ End-User Portal: Recent Releases Configurations

Name	Possible Values	Description
Default Days to Show	30 or specify	Set the default recency of the release for the recent files list. This setting determines the recency, in days, for download packages to be included in the recent releases list. Common settings are 30, 60, 90, and 120.

Recent Files Page

These settings correspond to the **Recent Files Page** section of the **End-User Portal Setup** page in **System > Configure**.

Table 21-25 ▪ End-User Portal: Recent Files Page Configurations

Name	Possible Values	Description
Default Days to Show	30 or specify	Set the default recency for the recent files list. This setting determines the recency, in days, for files to be included in the recent files list. Common settings are 30, 60, 90, and 120.

Download Order Page

These settings correspond to the **Download Order Page** section of the **End-User Portal Setup** page in **System > Configure**.

Table 21-26 ▪ End-User Portal: Download Order Page Configurations

Name	Possible Values	Description
Show Version	Selected or unselected	<p>Show or hide the Version column in the Download Package list of the Available Downloads page.</p> <p>The Available Downloads page lists the download packages associated with an entitlement. In the End-User Portal, the Available Downloads page appears when you click an entitlement’s Download Now link on the List Entitlements page.</p>
Show Custom Activation ID	Specify	<p>Replaces the default activation ID with the value of a custom activation ID attribute on the Download Order page.</p> <p>Exceptions</p> <ul style="list-style-type: none"> ● Any value other than “Not Applicable” and “Not Required”—The Download Order page displays the custom activation ID attribute with the value <value>. This replaces the Activation ID property and its value. ● “Not Required”—The Download Order page displays the custom activation ID attribute with the “Not Required” value. This replaces the Activation ID property and its value. ● “Not Applicable”—The Download Order page displays the Activation ID property and its value. ● No value—The Download Order page displays the Activation ID property and its value.

Download Packages Page

These settings correspond to the **Download Packages Page** section of the **End-User Portal Setup** page in **System > Configure**.

Table 21-27 ▪ End-User Portal: Download Packages Page Configurations

Name	Possible Values	Description
Show Version	Selected or unselected	<p>Show or hide the Version column in the Download Package list on the Download Packages page.</p> <p>The Download Packages page lists the download packages for a product. In the End-User Portal, the Download Packages page appears when you click on a product name. For example, an end user might click on a product name that appears in Your Downloads on the Home page or in the list that appears after clicking Downloads > List Downloads.</p>

Manage Accounts & Users

These settings correspond to the **Manage Accounts & Users** section of the **End-User Portal Setup** page in **System > Configure**.



Note ▪ Display of the **Created By** column on the **Accounts** page in the End-User Portal is configurable (default: displayed). Contact Reverera Support if the **Created By** column should be hidden.

Table 21-28 ▪ End-User Portal: Manage Accounts & Users Configurations

Name	Possible Values	Description
Hide Create a Sub Account	Selected or unselected	Hides the Create a Sub Account link in the Actions menu on the Accounts page.
Hide Delete Account	Selected or unselected	Hides the Delete Account link in the Actions menu on the Accounts page.
Hide Delete Subtree	Selected or unselected	Hides the Delete Subtree link in the Actions menu on the Accounts page.
Hide Create a User	Selected or unselected	Hides the Create a User link in the Actions menu on the Accounts and Users pages.
Hide Delete a User	Selected or unselected	Hides the Delete User link in the Actions menu on the Accounts and Users pages.
Prevent editing Account ID and Account Name	Selected or unselected	Prevents customer users and partner users from editing their account ID and account name.

Table 21-28 ▪ End-User Portal: Manage Accounts & Users Configurations

Name	Possible Values	Description
Hide Create an Account	Selected or unselected	Hides the Create partner account and Create customer account links in the Actions menu on the Accounts page.
Roles for Administrators	Specify	<p>Defines the role that a user must have to be considered an administrator. To specify multiple roles, separate the roles using a comma. If more than one role is specified, it is sufficient for a user to have one of the roles to be considered an administrator.</p> <p>This field must be populated if Show List All Administrators Link is selected. If Show List All Administrators Link is selected but no roles are specified, the Account Administrators list in the End-User Portal will be empty.</p>
Prevent editing geographic information	Selected or unselected	If selected, end users and partner users are unable to edit the geographic information (Country field) in the Edit User Profile and Edit Account pages in the End-User Portal.

Custom Branding

These settings correspond to the **Branding** section of the **End-User Portal Setup** page in **System > Configure**.

Table 21-29 ▪ End-User Portal: Custom Branding Configurations

Name	Possible Values	Description
Upload Company Logo	Specify	<p>Choose an image file (PNG or JPG format) to serve as your account’s logo in the End-User Portal and upload it. Use the controls to choose a file from your local machine to upload.</p> <p>After an image file is uploaded, a reset button is available to enable you to clear the uploaded image.</p> <p>Maximum file size: 40KB</p> <p>Recommended image height: 30 pixels</p>

Table 21-29 • End-User Portal: Custom Branding Configurations


Name	Possible Values	Description
Upload CSS	Specify	<p>Choose a CSS file to replace the style settings used by default for the End-User Portal. Uploading a customized CSS file allows for a broader range of style changes consolidated into a single place. For smaller changes, it may be simpler to use one of the override settings instead.</p> <p>Use the controls to choose a CSS file from your local machine to upload. (When no custom CSS file is present, the End-User Portal uses its default CSS.)</p> <p>Viewing Previously Uploaded Files</p> <ul style="list-style-type: none"> • If a custom CSS file has previously been uploaded, a Last Update date will be listed. To view the contents of this file, enter the following URL: <code>https://<siteID>.flexnetoperations.com/flexnet/staticfiles/operationsportal/custom.css</code> • If a custom header file has previously been uploaded, a Last Update date will be listed. To view the contents of this file, enter the following URL: <code>https://<siteID>.flexnetoperations.com/flexnet/staticfiles/operationsportal/header.html</code> • If a custom footer file has previously been uploaded, a Last Update date will be listed. To view the contents of this file, enter the following URL: <code>https://<siteID>.flexnetoperations.com/flexnet/staticfiles/operationsportal/footer.html</code> <p> Note • When you upload a CSS file to the Upload CSS field, it will overwrite any existing custom CSS file that was previously uploaded. Also, when you upload a custom CSS file, it will always be renamed to <code>custom.css</code>, even if that was not its original name. The same goes for a custom header (will always be named <code>header.html</code>) and a custom footer (will always be named <code>footer.html</code>).</p>
Upload Header	Specify	<p>Choose an HTML file to replace the default header content for the End-User Portal. Use the controls to choose a file from your local machine to upload. (When no custom header HTML is present, the End-User Portal uses its default header content.)</p>

Table 21-29 • End-User Portal: Custom Branding Configurations

Name	Possible Values	Description
Upload Footer	Specify	Choose an HTML file to replace the default footer content for the End-User Portal. Use the controls to choose a file from your local machine to upload. (When no custom footer HTML is present, the End-User Portal uses its default footer content.)
Primary Navigation Position	Top, Left, or Right	Specify where to show the high-level navigation menu for the End-User Portal. Default: Top.
Configure Portal Colors		<p>Click Open Configurator to show the Color Configurator panel. The Color Configurator allows you to set the colors to use in your End-User Portal pages for the following content:</p> <ul style="list-style-type: none"> ● Default button label color – sets the color of the label on default buttons in the End-User Portal. ● Default button color – sets the color of the default buttons in the End-User Portal. ● Background color – sets the background page color for all End-User Portal pages. ● Title color – sets the text color of the page titles in the End-User Portal. ● Link color – sets the color of the link text and lightweight button text on End-User Portal pages. ● Primary navigation – sets the background color for the primary navigation menu. ● Primary navigation open – sets the background color for open (active) primary navigation menu items. ● Primary navigation text – sets the color for all text in the primary navigation menu. <p>Specify all colors using hexadecimal format. For example, #000000 for black, #ffffff for white, or #228B22 for forest green.</p> <p>Click Preview to show a sample of your color settings within the Color Configurator.</p> <p>Click Undo to revert any changes that have not yet been saved.</p> <p>Click Use Defaults to restore color settings to the FlexNet Operations default colors.</p> <p>Click Save to store your changes to these color settings.</p>

See Also

[Performing System Configuration](#)
[Managing Devices](#)

Activating and Licensing FlexNet Operations

Reverera Support activates your license to use FlexNet Operations on the **Licensing** configuration page (**System > Configure > Licensing**). Note that the **Licensing** configuration page does not display any configuration options.

The Producer Portal shows the **Licensing** page when the first user from a producer's account logs in. Until a valid FlexNet Embedded endpoint URL is in place, the Producer Portal remains in its unactivated state, and no other pages are accessible to the producer's accounts' users.

Importing a Configuration

The configuration import utility uses the JAR file created by the configuration export utility to restore all FlexNet configuration settings. A user must be assigned a role with the **View and Manage Configurations** permission to import configuration settings.



Note - Before importing configuration settings into a working FlexNet Operations instance, [export the working configuration settings](#) (without writing over the JAR file you plan to import). If there is a problem with the imported settings, you have a backup of working settings to restore.



Task **To import configuration settings through the FlexNet Operations Producer Portal**

1. Click **System > Configure**.
2. Click **Import** to open the **Import** page.
3. Specify the JAR file that contains the configuration settings to restore.
4. Click **Import**.

The Producer Portal imports the settings contained in the imported file.

See Also

[Configuring the FlexNet Platform Server](#)
[Exporting a Configuration](#)

Exporting a Configuration

The configuration export utility exports all of the FlexNet configuration settings at once. Configurations are exported to a JAR file that contains database, FlexNet Platform Server, Producer Portal, and application-specific settings in separate XML files. The configuration import utility uses the JAR file to restore all configuration settings. A user must be assigned a role with the **View and Manage Configurations** permission to export configurations to a file.



Task **To export configuration settings through the FlexNet Operations Producer Portal**

1. Click **System > Configure**.
2. Click **Export** to open the **Export** page.
3. Click **Export**.
4. In the File to download dialog, click **Open, Save, or Cancel**.

Specify the location and file name for the JAR file. By default, the configuration settings are saved to a file called `flexnet_configurations.jar`. It is recommended to save the file to a safe location.

See Also

[Configuring the FlexNet Platform Server](#)
[Importing a Configuration](#)

Configuring Embedded Devices Settings

A user must be assigned a role with the **View and Manage Configurations** permission to modify configuration settings for Embedded Devices through the Producer Portal.



Note - Before changing any configuration settings in a working FlexNet Operations instance, it is advisable to [export the working configuration settings](#). If there is a problem with the new settings, you have a backup of working settings to restore.



Task **To configure embedded devices settings**

1. Click **System > Configure**.
2. Click **Embedded Devices** to open the configuration page.
3. View or change the values of the settings below.
4. Click **Save Configs**.

The Producer Portal saves your configuration changes.

Settings appear in the following groups:

- [Host Options](#)
- [Capability Request Handling](#)
- [License Generation](#)
- [History Logging](#)

Host Options

These settings correspond to the **Host Options** section of the **License Fulfillment Service Configuration Settings** page in **System > Configure**.

Table 21-30 • Embedded Devices: Host Option Configurations

Name	Possible Values	Description
Default Client Host Type	FLX_CLIENT or specify	The default host type FlexNet Operations uses when creating an unknown client device from a request, if the request does not specify a host type. This value is also used when claiming a client device from the End-User Portal, if not supplied by the request, the portal UI, or a call-out. Default: FLX_CLIENT.
Default Server Host Type	FLX_SERVER or specify	The default host type FlexNet Operations uses when creating an unknown server device from a request, if the request does not specify a host type. This value is also used when claiming a server device from the End-User Portal, if not supplied by the request, the portal UI, or a call-out. Default: FLX_SERVER.
Excluded Client Host ID Types	Specify	Use this option to select which of the normally supported host ID types should be excluded from the choices presented when editing the allowed ID types for a host type that supports clients.
Excluded Server Host ID Types	Specify	Use this option to select which of the normally supported host ID types should be excluded from the choices presented when editing the allowed ID types for a host type that supports servers.
Entitlement Map Overlap	Value in days	Maximum elapsed time, in days, that an entitlement mapping can exceed the limits specified by any applicable host series definitions.
Allow Duration License Decrease	Selected or unselected	Select to allow licenses with duration based features to have their copies reduced. Normally, licenses using durations only allow increasing the number of copies.
Allow Duration License Decrease for Producer	Selected or unselected	Select to allow licenses with duration based features to have their copies reduced by a producer. Normally, licenses using durations only allow increasing the number of copies.
Consume Copies When Mapping	Selected or unselected	Immediately deduct the number of copies from the appropriate line item when a request to increase a host's license copies is processed. If this option is not selected, the additional copies are not deducted until the license is generated.
Clone Detection	Selected or unselected	Select to record the clone suspect events in the back office.

Table 21-30 • Embedded Devices: Host Option Configurations





Name	Possible Values	Description
Limit Binding Break Repairs for License Server	Selected or unselected	<p>Select to limit the number of times a local license server can repair a binding break. If selected, configure the number of allowed binding break repairs in Maximum Number of Binding Break Repairs Allowed for License Server. If unselected, unlimited binding break repairs are permitted.</p> <p>Default: Unselected.</p> 
Maximum Number of Binding Break Repairs Allowed for License Server	Specify	<p>Available if the option Limit Binding Break Repairs for License Server is selected. Sets the maximum number of times the local license server is allowed to repair a binding break. If set to 0, no binding break repairs are allowed. The local license server will cease to serve licenses if the number of binding break repairs exceeds the maximum number of allowed repairs, and no further repairs are allowed.</p> <p>Default: 3</p>
Use Activation start date without compensating time zone	Selected or unselected	<p>When a device is activated and the activation date is equal to the current date in Pacific Standard Time (PST), the start date calculation logic applies a -1 day rollback. This is to compensate for timezones that are ahead of the database server time in PST.</p> <p>Select this option if you do not want to apply a -1 day rollback to the start date.</p> <p>Default: Unselected.</p> 
<p>Important • Selecting this option affects the start date of a license. Consult Reverera support before selecting it. For example, without the -1 day rollback, a customer who activates a license on 27-Jan-2023 06:00pm PST, which is equivalent to 28-Jan-2023 2:00am GMT, can only start using the license the following day (27-Jan-2023 12:00am PST).</p>		

Table 21-30 • Embedded Devices: Host Option Configurations

Name	Possible Values	Description
Allow Removing or Reducing Metered Features From a License Server	Selected or unselected	<p>When selected, allows the removal or reduction of metered features from a license server instance in the FlexNet Cloud Licensing Service.</p> <p>Default: Unselected.</p>
Support Multiple License Servers	Selected or unselected	<p>Select to allow served clients to have multiple parent license server instances concurrently. If selected, the Producer Portal and the End-User Portal show the multiple parent servers of served clients.</p> <p>Default: Unselected.</p>
Consolidate Licenses	Selected or unselected	<p>When selected, FlexNet Operations consolidates the licenses that contain multiple line items for the same feature if the following entities are identical for all line items:</p> <ul style="list-style-type: none"> ● Feature Name ● Feature Version ● Vendor String ● Notice ● Serial Number ● Expiration Date ● Issuer ● Version Date <p>Selecting this option may help improve the local license server's performance.</p> <p>Default: Unselected.</p>

Note - When using the option **Consolidate Licenses**, the option **Enable feature count aggregation** (under **System > Configure > FlexNet Operations > Embedded Device Settings**) must be unselected.

Table 21-30 • Embedded Devices: Host Option Configurations

Name	Possible Values	Description
Retain Non-Printing Characters in Device ID and Alias	Selected or unselected	<p>When selected, FlexNet Operations does not remove non-printing characters (if used) from the “Device ID” and “Alias” fields in the capability request. As a side effect, the Devices page will not load as expected.</p> <p>When this option is unselected, invalid characters in the “Device ID” and “Alias” fields in the capability request (such as ASCII control characters) are replaced with an empty string (for example, the device name <code>Test^BName</code> is saved as <code>TestName</code>).</p> <p>The following control characters are invalid: ^B, ^D, ^E, ^G, ^N, ^O, ^P, ^Q, ^R, ^S, ^T, ^U, ^W, ^X, ^Y, ^[, ^\, ^]</p> <p></p> <p>Important - When an invalid character is used in the “Device ID” or “Alias” field and subsequently removed by FlexNet Operations, the license will not be processed by the FlexNet Embedded toolkit.</p> <p>Default: Unselected.</p>
Allow expired line items to be mapped to devices or servers	Selected or unselected	<p>Select to allow expired activation IDs to be mapped to devices in the License Fulfillment Service.</p> <p></p> <p>Important - This configuration option only works in conjunction with the option Allow mapping of expired entitlements (under System > Configure > FlexNet Operations > Embedded Device Settings). To allow mapping of expired activation IDs to devices, both options must be selected.</p>

Capability Request Handling

These settings correspond to the **Capability Request Handling** section of the **License Fulfillment Service Configuration** page in **System > Configure**.

Table 21-31 • Embedded Devices: Capability Request Handling Configurations

Name	Possible Values	Description
Device Response Lifetime	Time value in seconds, minutes, hours, days, or weeks	Lifetime for device responses generated when a device request is received. You can specify the value to explicitly identify the time unit as seconds, minutes, hours, days, or weeks with a suffix of s, m, h, d, or w. If no suffix is used, the value is assumed to be in seconds. If the value is zero (0), the responses never expire.

Table 21-31 ▪ Embedded Devices: Capability Request Handling Configurations

Name	Possible Values	Description
Allow Adding Unknown Hosts	Selected or unselected	Select to allow an unknown host to be added as a result of processing a capability request. An unknown server is added only if the capability request contains a valid activation ID. (To add a server when the request contains no activation ID, select Allow Server Without Activation IDs .)
Allow Server Without Activation IDs	Selected or unselected	Select to allow unknown servers to be added as a result of processing a capability request, even if the request does not contain any activation IDs.
Prohibit Virtual Hosts	Selected or unselected	Select to prohibit capability requests for hosts running on virtual machines. If this option is not selected (default), capability requests are served regardless of the machine type.
Capability Request Call-out	URL or classname	The base URL of a REST server or name of a class that implements the com.flexnet.lm.bot.service.CapabilityRequestCallOut interface. If specified, it is called to customize handling of capability requests and generated responses.
Capability Request Finalize Host Call-out	Selected or unselected	Select to invoke call-out just before creating an unknown host. Additional attributes can be defined before it is persisted. It can also be used to cancel creation of the new host instance.
Capability Request Access Check Call-out	Selected or unselected	Select to invoke call-out after (optionally) creating an unknown host, before proceeding with processing an off-line request. The return value can be used to deny access to the targeted host.
Capability Request Finalize Response Call-out	Selected or unselected	Select to invoke call-out after an incoming host request has been validated, but before the capability response has been generated.
Call-out Includes Host Details	Selected or unselected	Select to send details about the target host in the request body. Otherwise, just send the host id and id type, host class, host type, and alias.
Call-out Includes Add-on Details	Selected or unselected	Select to send add-on details in the request body. Otherwise, just send list of activation IDs.

License Generation

These settings correspond to the **License Generation** section of the **License Fulfillment Service Configuration** page in **System > Configure**.

Table 21-32 ▪ Embedded Devices: License Generation Configurations

Name	Possible Values	Description
Default Borrow Interval	Time value in seconds, minutes, hours, days, or weeks	The default borrow interval for features that do not specify an override. You can specify the value to explicitly identify the time unit as seconds, minutes, hours, days, or weeks with a suffix of s, m, h, d, or w. If no suffix is used, the value is assumed to be in seconds. If the value is zero (0), the interval is unlimited.
Default Renew Interval	Percentage of borrow interval	The default renew interval expressed as a percentage of the borrow interval, for features that do not specify an override. If set to zero (0), the renew interval is at the client discretion.
Include Issued Date	Selected or unselected	If selected, include the Issued Date attribute in generated licenses for devices. Default: Selected.
Include Start Date	Selected or unselected	If selected, include the Start Date attribute in generated licenses for devices. Default: Selected.
Default Metered Undo Interval	Time value in seconds, minutes, hours, days, or weeks	The default value of the undo interval for metered features that do not explicitly define an undo interval and are not reusable. You can specify the value to explicitly identify the time unit as seconds, minutes, hours, days, or weeks with a suffix of s, m, h, d, or w. If no suffix is used, the value is assumed to be in seconds.
Skip Confirmation	Selected or unselected	When selected, no confirmation capability request is required when reducing the number of copies of a license.
Skip Confirmation for Producer	Selected or unselected	When selected, no confirmation capability request is required for a producer when reducing the number of copies of a license.
Skip Confirmation for Product Line	Selected or unselected	When selected, no confirmation capability request is required for a producer when reducing the number of copies of a license for a specified product line. You specify the product lines for which licenses can be reduced without requiring a confirmation in the Skip Confirmation column on the Package Products Product Lines page (available under Products > Product Lines). Default: Unselected.

Table 21-32 • Embedded Devices: License Generation Configurations

Name	Possible Values	Description
Date-based Version Format	yyyy.MM or yyyy.MMdd	When a feature that uses a date-based version format is created, this format is used when converting the version date to a version representation. For a date of May 15, 2018, yyyy.MM is 2018.05 and yyyy.MMdd is 2018.0515.

History Logging

These settings correspond to the **History Logging** section of the **License Fulfillment Service Configuration** page in **System > Configure**.

Table 21-33 • Embedded Devices: History Logging Configurations

Name	Possible Values	Description
Successful Capability in Request History	Selected or unselected	When selected, successful capability requests and matching responses are recorded in the request history. By default, successes are recorded only in the host history.
Record Sync in Request History	Selected or unselected	When selected, sync messages and acknowledgments are recorded in the request history. By default, messages are recorded only in the host history, at debug log level.
Write License History Events	Selected or unselected	When selected, individual license host history events are included in the request history for backward compatibility. Recording such events has been deprecated and replaced by adding fulfillment details in other events.
Host History Log Level	Debug, Information, Error	Include events in host history that are at or above the specified log level. The lowest log level is Debug; the highest is Error.

See Also

[Performing System Configuration](#)

Secure Token Single Sign-On

The FlexNet Operations End-User Portal can be configured to interface with a separate application, such as a corporate portal or intranet. The single sign-on (SSO) application passes user credentials to the FlexNet Operations End-User Portal, enabling a user to have a single set of credentials for both. The user signs on to the SSO application, and gains access to both the SSO application and FlexNet Operations End-User Portal for the duration of the browser session. This section describes how to configure single sign-on applications.

The secure token single sign-on process includes the following steps:

Table 21-34 - Secure Token Single Sign-On Process Steps

#	Step	Description
1	SSO application requests secure token	The SSO application requests a secure token from the FlexNet Operations server. The FlexNet Operations server sends the secure token back to the SSO application.
2	SSO application receives secure token and constructs URL	The SSO application receives the secure token and constructs a URL, which includes parameters that control the display and behavior of the End-User Portal.
3	SSO application sends URL to FlexNet Operations server	The SSO application sends the URL and the secure token to the FlexNet Operations server.
4	Upon login, credentials are passed to server and user is authenticated	When the user logs into the SSO application, credentials are passed to the FlexNet Operations server, and the user is authenticated. The FlexNet Operations server displays the End-User Portal landing page.

Configuring Secure Token Single Sign-On

Secure token single sign-on uses FlexNet Operations Web services.

- [Synchronizing SSO Application User Data](#)
- [Generating a Token](#)
- [Constructing a URL](#)



Note - For more information about Web services, including the SSO Web service, consult the *FlexNet Operations Web Services Integration Guide* and *FlexNet Operations SOAP Web Services Guide*.

Synchronizing SSO Application User Data

Before configuring secure token single sign-on, you must synchronize SSO application user data from the SSO application with your FlexNet Operations database, as shown here.

Table 21-35 - Data Synchronization for Secure Token SSO Applications

Data	Required or Optional?
User first name	Required
User last name	Required
User email ID	Required
User role	Required

Table 21-35 • Data Synchronization for Secure Token SSO Applications

Data	Required or Optional?
User locale	Optional, defaults to system locale
User time zone	Optional, defaults to system time zone
User Account ID	Optional, ID of the account to which the user belongs
Account ID	Required for all accounts
Account display name	Required

Native Authentication

If the secure token SSO application performs authentication natively, then you must pre-load all user data from the SSO application into FlexNet Operations using the **UserAcctHierarchyService** Web service. In addition, the SSO application must synchronize all subsequent changes to user information with the FlexNet Operations database.

- For example, if the application allows online user registration, the **UserAcctHierarchyService** Web service must be used to create the same user in FlexNet Operations.
- Because FlexNet Operations does not allow deletion of user information, if a user is deleted from the SSO application, the user's status must be set to Inactive in FlexNet Operations.



Note • For complete reference information on the individual FlexNet Operations SOAP-based APIs, see the [FlexNet Operations SOAP Web Services Guide](#).

External Authentication

If the secure token SSO application is authenticating users with a directory service (such as LDAP), you must configure the directory service in FlexNet Operations as follows:



Task **To configure the directory service for external authentication:**

1. Add the directory service as a new domain in FlexNet Operations.
2. Import groups from the directory service into the FlexNet Operations database.
3. Map roles to the imported directory groups. (Typically, the groups are assigned the Portal User role.)

Subsequent changes to the directory service user database must be synchronized with FlexNet Operations using the **UserAcctHierarchyService** Web service.



Note • For more information on roles, users, and domains, see [Managing Accounts and Users](#).

Generating a Token

FlexNet Operations Web services are used in making, processing, and generating token requests.



Task **To generate a token:**

1. The SSO application must request a secure token from the FlexNet Operations server. This request is performed with a SOAP message using a **FlexnetAuthentication** Web service call. Create a FlexNet user for a Web service client, and pass the credentials in the request for authentication so that the **FlexnetAuthentication** service processes the request and serves the response with a valid, secure token. The request message has the form:

```
<secureTokenRequest>  
  <userId>sjoe</userId>  
</secureTokenRequest>
```

2. After the request is processed by the FlexNet Operations server, the response message is returned with the secure token. The response message has the form:

```
<secureTokenResponse>  
  <token>vZ1VakmEUiNmTsj5-dYE38qQvUW_OcxoLeDhtNmS53v04xPF__2GmfKwUE7D6hPoZcV9W0K1qhjET  
  _NjY1QvK0_j_dmNUEVhKxibIQz1A2g_wg</token>  
</secureTokenResponse>
```

The token is valid for 300 seconds after creation.

Constructing a URL

After the SSO application receives the secure token, it must launch a URL to display the End-User Portal. The URL has the form:

```
http://<host>:<port>/flexnet/operationsportal/sso.do?username=<username>&token=<token>  
&language=<language>&externallogouturl=<URL>&goToPage=<page>&hideheader=<value>
```




Important • Query string parameters must be URL encoded.

Parameters are described in the following table:

Table 21-36 • SSO URL Parameters

Parameter	Description
username	User's name. Must be in the FlexNet Operations database or the login fails.
token	Secure token value.
language	Optional. The user's preferred language, such as en_US.

Table 21-36 • SSO URL Parameters

Parameter	Description
externallogoffurl	<p>URL to display if the session times out.</p>  <p>Important • The externallogoffurl must be URL encoded.</p>
goToPage	<p>Optional. Indicates which page of the FlexNet Operations End-User Portal to display initially. Possible values are:</p> <ul style="list-style-type: none"> • <code>homePage</code> displays the End-User Portal landing page • <code>showEntitlements</code> displays the entitlements landing page • <code>showFulfillments</code> displays the fulfillments landing page • <code>activate</code> displays the item corresponding to the activation ID
activationID	<p>Optional. If specified, the user can access only the specified activation ID. Used in conjunction with the <code>goToPage</code> value "activate" to directly navigate to activation page.</p>
entitlementID	<p>Optional. If specified, the user can access only the specified entitlement ID. Used in conjunction with the <code>goToPage</code> value "activate" to directly navigate to activation page. Note that if the <code>goToPage</code> is set to activate, only non-child items can be activated from this page. Child line items are those which are derived by upgrading or renewing another line item.</p> <p>An example of a URL that would load the activation page for a given entitlement ID: http://opshost:8888/flexnet/operationsportal/sso.do?username=admin&goToPage=activate&hideheader=true&token%3Dv9vF941Xv18xvhAY&entitlementId=SSOEnt&externallogoffurl=http%3A%2F%2Flocalhost%3A9090externalportalstartpage.jsp%26language%3Den_US</p>
hideheader	<p>Optional. Controls the display of the End-User Portal header. Value is true or false.</p>

Viewing Transaction Histories

Producers can use the transaction history feature to view system state changes of entity transactions to troubleshoot issues by observing the transactions and/or comparing changes in the entity fields. There are several types of entities that can be viewed. These entities include:

- Account
- Product
- User
- Update
- Entitlement

You can view when the entities were created, updated, deleted, and who submitted the change.



Task

To search for a transaction

1. Click **System > Transaction History**.
2. Select or enter your search criteria. Options include:
 - a. Select the **Entity Type** you want to search for from the drop-down menu.
 - b. If you select a specific entity, you can enter a value for that type of entity.
 - c. Enter the ID of the user who performed the transaction.
 - d. Enter or select a start date.



Note - If the year that you want to set is not currently available from the calendar, select the year that is closest to the desired year. This automatically increases the list by 10 years from the year you selected.

- e. Enter or select an end date.



Note - If the year that you want to set is not currently available from the calendar, select the year that is closest to the desired year. This automatically increases the list by 10 years from the year you selected.

3. Click **Search**.

The Producer Portal searches for transactions that match your search criteria and shows a list of matching transactions in the search results. The results page lists the following:

- The timestamp of the transaction
- The event type (create, update or delete)
- The entity type
- The entity ID
- The user who performed the transaction.

Click on the **View details** of an entity to view the details of the transaction. On the **Transaction Details** page, you can view all the fields associated with an entity, including any changes from the **Show all fields** tab, or select the **Show only differences** tab to view just the fields that changed.



Note - Only transactions with an event type of **UPDATE** have the **Show all fields** and **Show only differences** tabs. There are no differences to display for **CREATE** events.

Click on the Entity ID of a transaction to be taken to the create/update page for that entity.

See Also

[Browsing Users](#)

Managing Custom Content

Producers can create custom text or HTML to be shown to their end-users in the End-User Portal. Custom content is used in the End-User Portal to customize page instructions on supported pages, add announcements to the home page, or create standalone pages.



Note - To create or edit custom content, a Producer Portal user must have the View and Manage Custom Content permission. See [Working with Roles and Permissions](#) for more information about users, roles, and permissions.

The topics below explain more about custom content and how to manage it.

Table 21-37 •

Topic	Description
About Custom Content	Discusses custom content concepts, attributes, and supported End-User Portal pages.
About Product Trial Registration Support	Describes how to use the TrialRegistration custom content template to support the registration for trial products by end users, including the optional use of a custom email message and a custom registration-success page.
Listing Custom Content	Shows how to use the System menu to list all custom content.
Creating Custom Content	Explains how to create custom content.
Editing Custom Content	Describes how to edit an existing custom content item.
Localizing Custom Content	Explains how to update page instructions for localized sites.

See Also

[Configuring End-User Portal Settings](#)

About Custom Content

Producers can modify the on-page instructions of End-User Portal pages—typically the content at the top of a page just below the page title—by creating custom content in the Producer Portal. One common use for custom content is to add announcements to the End-User Portal’s home page. Producers can also create custom, standalone HTML pages to be included in the End-User Portal using the Custom Content feature.

To use custom content to modify on-page instructions of regular End-User Portal pages, first identify the End-User Portal page you want to customize. Next, on that page, determine the custom content ID of the portion you plan to customize. Then use the controls on the **Custom Content** page, along with your custom text or HTML, to create the new content. The custom content you create replaces the standard content (corresponding to the custom content ID) on the End-User Portal page.

Use the pages listed in [Pages That Support Custom Content](#) to determine which custom content ID to use when you create content. For example, use NotificationLogContent to alter the instructions on the Downloads page that appears when a user clicks on a download package on the **Download Packages** page.



Tip - To add announcements to the End-User Portal's home page, edit the HTML for custom content ID: **epAnnouncements**. Announcements are rendered on the home page in the Announcements panel.

To use custom content to create custom, standalone pages, add content from the **Custom Content** page but be sure to use a unique, unused custom content ID.

Additional information about custom content attributes, status, supported pages, and so forth appears in the following sections:

- [Custom Content Attributes](#)
- [Custom Content Status](#)
- [Pages That Support Custom Content](#)
- [Localization and Custom Content](#)
- [Additional Notes and Tips for Content Customization](#)

For information about using custom content to support trial registrations, see [About Product Trial Registration Support](#).

Custom Content Attributes

The following attributes are relevant to Producer Portal users who are creating or editing custom content to be shown in their End-User Portals.

Table 21-38 - Custom Content Attributes

Attribute	Description
Custom Content ID	<p>A unique ID that can be used to identify custom content in FlexNet Operations.</p> <p>When custom content is to replace existing, standard content on an End-User Portal page, this ID must match the ID of the content it replaces.</p> <p>When custom content is intended to introduce a new page to the End-User Portal, this ID must be unique and otherwise unused in the End-User Portal.</p>
Description	<p>A longer, descriptive name for custom content.</p>
Hide from Portal?	<p>A switch that determines whether live custom content appears on the End-User Portal.</p> <ul style="list-style-type: none">● Selected—Hide the custom content from End-User Portal users even if the custom content is the live version.● Unselected—Show the custom content to End-User Portal users if it is the live version. <p>Default: Unselected.</p> <p>Hide from Portal is a control that appears on the Create Content and Edit Content pages.</p>

Table 21-38 • Custom Content Attributes

Attribute	Description
Template	<p>The template to use for the custom content.</p> <p>Currently, only one template is available: TrialRegistration. This template is purpose built to support free trial registrations in the End-User Portal. In all other cases, leave the Template setting blank.</p>
Status	<p>The status of the custom content version. For custom content, status can be Live, Draft, or Archived. (See Custom Content Status, below.)</p> <p>Status is a value that appears in the list of custom content items on the Custom Content page.</p>
Last Modified	<p>The date the custom content was last changed.</p> <p>Last Modified is a value that appears in the list of custom content items on the Custom Content page.</p>
Modified By	<p>The Producer Portal user who last changed the custom content.</p> <p>Modified By is a value that appears in the list of custom content items on the Custom Content page.</p>
Permalink	<p>The relative URL for custom content in the End-User Portal. For standalone pages built from custom content, this URL can be used for links that target the custom content page.</p> <p>Permalink is an attribute that appears on the Edit Content page.</p>
Content Version	<p>The version of the custom content for the current custom content ID. Content Version values show the status and version of custom content. For example: Draft / 1 or Live / 2.</p> <p>Content Version is a control that appears on the Edit Content page.</p>
Content	<p>The text or HTML to be used in the End-User Portal.</p>

Custom Content Status

Similar to email template status values, custom content items can have one of three status values:

- **Live**—The current version of the content that appears in your End-User Portal. Only one version of a custom content item can be live at any given time.
- **Draft**—A work-in-progress version of new custom content or an existing custom content item that is being revised. Custom content items in draft state are not shown in the End-User Portal. Only one version of a custom content item can be in draft status at any given time.
- **Archived**—Formerly live versions of a custom content item. Archived versions are preserved in the system and can be made live, again, if your account is required to roll back changes made to the live version.

A custom content item’s status is shown on the **Custom Content** page.

Pages That Support Custom Content

The following table lists End-User Portal pages that support custom content, the custom content IDs for the customizable items, and a description of how the content is used for each custom content ID.



Note - It is also possible to create custom, standalone pages for the End-User Portal using your own custom content ID. The **Trial Registration** page is a special standalone page that producers can implement using the `TrialRegistration` template.

Table 21-39 - Pages That Support Custom Content

End-User Portal Page	Content ID	Description
Home (End-User Portal Announcements)	epAnnouncements	The Announcements panel on the home page can display messages from your account to its end users. This content is rendered on the home page unless the End-User Portal system configuration setting: Hide Announcements Widget is selected. (It is unselected by default.)
Downloads	ManufacturersContent	<p>Displayed when the user is presented with a list of producers. If only one producer is available, the end user sees only the list of available product lines (no producer choice when files from only one producer are available).</p> <p>This is the page that appears when an end user chooses Downloads > List Downloads in the End-User Portal, for example.</p> <p>This content is rendered under the page title (Downloads) and above the list of producers and product lines.</p>
Download Packages (Download Package Versions)	NewDownloadPackagesInfo	<p>The Download Packages page is the page that appears when an end user chooses a product line on the Producers page (the page the End-User Portal shows when end users click Downloads > List Downloads).</p> <p>This content is displayed when the New Versions tab is rendered and there are previous (archived) versions available for the product line selected.</p>

Table 21-39 • Pages That Support Custom Content

End-User Portal Page	Content ID	Description
Download Packages (Download Package Versions)	ArchivedDownloadPackagesInfo	<p>The Download Packages page is the page that appears when an end user chooses a product line on the Producers page (the page the End-User Portal shows when end users click Downloads > List Downloads).</p> <p>This content is displayed when the Previous Versions tab is rendered and there are new (current) versions available for the product line selected.</p>
Download Packages (View Download Order)	NewDownloadOrderContent	<p>The Download Order page is the page that appears when an end user clicks Download Now on the Entitlements page (the page the End-User Portal shows when end users click Activation & Entitlements > List Entitlements).</p> <p>This content is displayed when the New Versions tab is selected.</p>
Download Packages (View Download Order)	ArchivedDownloadOrderContent	<p>The Download Order page is the page that appears when an end user clicks Download Now on the Entitlements page (the page the End-User Portal shows when end users click Activation & Entitlements > List Entitlements).</p> <p>This content is displayed when the Archived Versions tab is selected.</p>
Download Search	SearchContent	<p>This content is displayed on the Download Search page and rendered under the page title and above the search controls.</p>
Download Files	DownloadContent	<p>Displayed on the Downloads page. This is the page that appears when an end user clicks on a download package on the Downloads page. This content is present when the Files tab is active. It is rendered below the page title (Downloads) and above the download package name.</p> <p>Note that download package-specific content is still maintained via the download package Download Instructions attribute. (Download instructions appear below the download package name and just above the Files, Download Log, and Notification Log tabs.)</p>

Table 21-39 • Pages That Support Custom Content

End-User Portal Page	Content ID	Description
Download Log	DownloadLogContent	<p>Displayed on the Downloads page when the Download Log tab is active and the Download Log tab is showing its default Files Downloaded view. It is rendered below the page title (Downloads) and above the download package name.</p> <p>Note that the Download Log tab can show three different views: Files Downloaded, Download Transactions, and Download Details. Each view corresponds to a separate HTML content entry.</p>
Download Log Detail	DownloadDetailContent	<p>This content is displayed on the Downloads page for a download package when a user clicks a file name on the Download Log tab. (Clicking a file name shows the Download Log’s Download Transactions view for that file.) The custom content for DownloadDetailContent is rendered below the page title (Downloads) and above the download package name.</p> <p>Note that the Download Log tab can show three different views: Files Downloaded, Download Transactions, and Download Details. Each view corresponds to a separate custom content entry.</p>
Download Log Detail File	DownloadDetailFileContent	<p>This content is displayed on the Downloads page for a download package when a user clicks a date-time value on the transaction list on the tab’s Download Transactions view. (Clicking a time-date value shows the Download Log’s Download Details view.) The custom content for DownloadDetailFileContent is rendered below the page title (Downloads) and above the download package name.</p> <p>Note that the Download Log tab can show three different views: Files Downloaded, Download Transactions, and Download Details. Each view corresponds to a separate custom content entry.</p>
Notification Log	NotificationLogContent	<p>Displayed on the Notification Log accessible from the Download page. Custom content for NotificationLogContent is rendered below the page title (Downloads) and above the download package name.</p>

Table 21-39 • Pages That Support Custom Content

End-User Portal Page	Content ID	Description
DownloadOrder	DownloadOrderContent	<p>Displayed on the Available Downloads page. The Available Downloads page is shown when a user clicks the Download Now link for an entitlement on the List Entitlements page.</p> <p>The Available Downloads page shows download packages for the products in the entitlement that include downloads. Custom content for DownloadOrderContent is rendered below the page title (Available Downloads) and above the Activation ID.</p>
View Recent Files	ViewRecentFilesContent	Displayed on the View Recent Files page on the Home page for specific implementation.
View Recent Products	RecentProductReleasesContent	Displayed on the View Recent Products page.
LandingPage	NoDownloadContent	Displayed on the landing page when no downloads are available for the current user.
Files Not Downloaded	NoDownloadContent	Displayed on the Files Not Downloaded page when no downloads are available for the current user.
Claim and Activate	ClaimAndActivateContent	Displayed on the Claim and Activate page. Custom content for ClaimAndActivateContent is rendered below the page title (Claim and Activate) and above the form inputs on that page.
Map by Activation IDs	AddOnUserEntryContent	Displayed on the Map by Activation IDs page. Custom content for AddOnUserEntryContent is rendered below the page title (Map by Activation IDs) and above the Device ID and Activation IDs field.
Password Reset	ForgotOrResetPassword	Displayed when a user clicks the Forgot Password link on the sign-in page. On the Password Reset page, the user is asked for their user ID and then asked to correctly answer their security question.

Table 21-39 • Pages That Support Custom Content

End-User Portal Page	Content ID	Description
Expiring Entitlements	ExpiringEntitlementsContent	Displayed when, in the End-User Portal, a user clicks Activations & Entitlements > Expiring Entitlements. On the Expiring Entitlements page, the End-User Portal shows a list of entitlements in which the entitlements due to expire soonest are listed first. ExpiringEntitlementsContent is rendered below the page title and above the list of entitlements. (Default: blank.)

Localization and Custom Content

Producers can localize the following custom content IDs, used to display custom instructions and information on specific End-User Portal pages:

- **Download Files** (Content ID: DownloadContent)
- **Home (End-User Portal Announcements)** (Content ID: epAnnouncements)
- **Password Reset** (Content ID: ForgotOrResetPassword)

Custom content IDs are defined using the **System > Custom Content** page (see [Listing Custom Content](#)).

To localize the content associated with the IDs listed above, you must add the locale code as a suffix to the ID. For example, to localize the epAnnouncements content for France, add the “-fr_FR” suffix to the ID: epAnnouncements-fr_FR.

For step-by-step instructions, see [Localizing Custom Content](#).

Additional Notes and Tips for Content Customization

A short list of tips to keep in mind as you customize End-User Portal pages.

- Remember that custom content items replace the content in question rather than appending to it.
- To revert the content of an End-User Portal page back to the standard content, edit the page’s customized HTML content (Edit Custom Content Data) so that its Hide from Portal attribute is selected.
- A completely empty custom content file does not remove a page’s standard content. To remove standard page instructions, use an empty HTML comment in the page’s custom content. For example, <!-- -->.
- Troubleshooting: In the End-User Portal pages, customizable content has HTML comments before and after it to indicate its custom content ID. Therefore, when you view the page source, you can see where the custom content is placed and what its ID is. Custom content appears like the following in the page source:

```
<!--BEGIN HTML Content ID <Custom Content ID value> -->
<Custom Content>
<!--END HTML Content ID <Custom Content ID value> -->
```

See Also

[Managing Custom Content](#)
[About Product Trial Registration Support](#)
[Configuring End-User Portal Settings](#)

About Product Trial Registration Support

Producers who want to offer trial registrations in the End-User Portal can use the TrialRegistration template to create a landing page for the free trial software users.

The TrialRegistration template uses the AngularJS framework along with standard custom content functionality to render a list of trial products from which end users can select and form fields for them to enter an email address (required) as well as additional contact information.



Tip ▪ See [About Trial Products](#) to learn how to configure the products you want to make available for free trials.

Trial Registration Process

Upon successful submission of the trial registration form, FlexNet Operations generates a new account and a new user account for the trial user (based on the email address provided). FlexNet Operations also creates an entitlement for that user to the trial product the end-user selected. The End-User Portal sends an email based on the **Welcome Email for End Users** template to the new trial user, giving that user access to their trial entitlement on the End-User Portal.



Tip ▪ Producers can create a variation of the **Welcome Email for End Users** template to use specifically for trial registrations. This variation name is then used in the trial registration custom content. In the custom content for your Trial Registration page, locate the hidden input, emailTemplate, and replace default value `{{formData.emailTemplate}}` with the Welcome Email for End Users email template's variation name.

Sending End Users to a Trial Registration Page

With a custom content Trial Registration page, and all trial registration elements in place, producers can send trial users to their trial registration page using a URL based on their End-User Portal location domain plus the Permalink path for the trial registration custom content page. For example, if your End-User Portal is hosted at `mycompany.flexnetoperations.com/flexnet/operationsportal` and the content ID for your trial registration page is `TrialReg`, the URL for your trial registration page would be

<https://mycompany.flexnetoperations.com/flexnet/operationsportal/showTrialRegisterUserPage.do?contentId=TrialReg>

Showing a Custom Registration-Success Page (Optional)


When an end user successfully registers, the End-User Portal shows a simple registration-success page. However, a producer can create a custom registration-success page to show to end users who complete the trial registration form. To do so, a producer first creates a standalone custom content page to serve as the custom registration-success page. The content ID of this new standalone page can then be used as the value for the hidden `landingContentId` input on the Trial Registration page.

See Also

[About Trial Products](#)
[Creating Custom Content](#)
[Managing Email Templates](#)
[Customizing Trial Registration Content](#)

Customizing Trial Registration Content

You can customize the trial registration template that is available on the **Custom Content** page. To access the trial registration template, in section [Creating Custom Content](#), follow [Step 1](#) through [Step 4](#). By default, the trial registration template contains predefined code that you can customize as required.

The Preview option  enables you to see how your code is rendered.

The following subsections explain the sections and individual fields that are included in the code, as well as how to customize the trial registration template code if custom attributes are used in FlexNet Operations.

“Trial Registration” Section

The only mandatory information that FlexNet Operations requires from a user to create an entitlement is a valid email address. Any other information is optional.

Table 21-40 • Trial Registration Fields

Field(s)	Description
<code>userEmail</code>	<p>Required. Prompts the user to enter their email address. The email address is the only user information required by FlexNet Operations to create an entitlement.</p> <p>By default, FlexNet Operations automatically generates the code snippet for the <code>userEmail</code> field with the label <code>Email</code>, and the field is displayed in the End-User Portal. This is the address that the trial details will be sent to.</p>

Table 21-40 • Trial Registration Fields

Field(s)	Description
userFirstName	Optional fields that can be used to collect additional customer information. By default, FlexNet Operations automatically generates the code snippet for these additional fields. You can edit the code according to your requirements.
userLastName	
companyphoneNumber	
streetAddress	
city	
state	
postalCode	

“Product Selection” Section

There are several ways to let your users select one or more part numbers, or you can specify a predefined part number in a hidden field:

- **Hidden input**—Does not let the user select a part number. You can include a predefined part number that cannot be seen or modified by users when the form is submitted.
- **Check boxes**—Enables the user to select one or more predefined part numbers. If you present the user with this option, the user should be required to select at least one check box.
- **Other selection/input mechanisms**—Listing all available selection or input mechanisms here would exceed the scope of this documentation. Offer the mechanism that suits your environment.

Table 21-41 • Product Selection Fields

Field(s)	Description
selectedPartNumbers	Use this field to specify the part number or selection of part numbers.

“Additional Information” Section

This section contains code snippets that illustrate how to customize the trial registration template code if custom attributes are used in FlexNet Operations. These custom attributes can be user attributes, account attributes, or license attributes. For information about custom attributes, see [Defining Custom Attributes](#).

See Also

[Defining Custom Attributes](#)

Defining Custom Attributes

It is important that you use the same structure for your code as demonstrated in the code snippets, otherwise errors may occur. You can include CSS styles, if required.

The following notes are applicable to all code snippets in this section and its subsections:

- Any class attribute must reference the style `"liExtProperty"`. This style can only be used on list item (``) tags.
- `class="required"` marks the custom attribute as mandatory (the output includes the red * symbol). Leave this out if the custom attribute is optional.
- The code snippets use the `ng-model` directive to bind the value of a user input field to a variable created in AngularJS. Permitted binding values are `formData.licenseCustomAttributes`, `formData.orgUnitCustomAttributes`, and `formData.userCustomAttributes`.

Defining Custom User Attributes

When you define custom user attributes in FlexNet Operations, the trial registration template will automatically contain relevant code for these attributes. You can customize this code to suit your needs.

Example

```
<li class="liExtProperty"><label >User_Identity:</label>
  <input type='text' ng-model="formData.userCustomAttributes['User_Identity']" />
</li>
<li class="liExtProperty"><label class="required">User_Identity_required:</label>
  <input type='text' ng-model="formData.userCustomAttributes['User_Identity_required']" />
</li>
```

Defining Custom Account Attributes

When you define customer account attributes in FlexNet Operations, the trial registration template will automatically contain relevant code for these attributes. You can customize this code to suit your needs.

Example

```
<li class="liExtProperty"><label >Account_Custom_Attribute:</label>
  <input type='text' ng-model="formData.orgUnitCustomAttributes['Account_Custom_Attribute']" />
</li>
<li class="liExtProperty"><label class="required">Account_Custom_Attribute_Required:</label>
  <input type='text' ng-model="formData.orgUnitCustomAttributes['Account_Custom_Attribute_Required']" />
</li>
```

Defining Custom License Attributes

When you define custom license attributes using FlexNet Operations for FlexNet Licensing, the trial registration template will automatically generate code for these attributes. However, the auto-generated code is not visible to the user until you remove the code `style="display: none"`, which is included by default. For more information on the effect of `style="display: none"`, see [Customization with Toggle Switch for Custom License Attributes](#).

Producer Portal users need to ensure these custom license attributes match existing part numbers. For custom license technology (other than FlexNet Licensing), the producer user has to define custom license attributes manually. The code snippets in this section help you with this task.

Customizing Custom Content Code for a Single Part Number

The following code snippet demonstrates how to create a trial activation for only one part number. The snippet shows custom content code for data type “number”. For snippets using different data types, see [Custom License Attribute Code Samples for Different Data Types](#).

```
<fieldset>
  <ol>
    <div id="Flexnet_Part1" class="WideColumnBlock left" >
      <li class="liExtProperty"><label class="required">CustLMA1:</label>
        <input type='text' ng-model="formData.licenseCustomAttributes['CustLMA1'][0]" />
      </li>
    </div>
  </ol>
</fieldset>
```

Notes

- **Flexnet_Part1** is the part number that was created and mapped to the product for trial activation.
- **CustLMA1** is the name of the custom license model attribute.
- In the trial registration template, this code snippet can be placed after the "Please answer the following questions" paragraph tag which is already included in the sample code.

Customizing Custom Content Code for Multiple Part Numbers with Different Custom License Attributes

If the trial registration allows the user to select between multiple part numbers, you can customize the content code so that either:

- only custom license attributes are displayed that apply to the part number that the user has selected. See [Customization with Toggle Switch for Custom License Attributes](#).
- all configured custom license attributes are displayed in the End-User Portal, irrespective of the part number selection. See [Customization Without Toggle Switch for Custom License Attributes](#).

The following subsections explain how to customize the code and possible use cases for both scenarios.

Customization with Toggle Switch for Custom License Attributes

When you customize the code to include a toggle switch, the End-User Portal initially does not display any custom license attributes. When the user selects a part number, only those custom license attributes are displayed that apply to the selected part number. When the user clears the part number selection, the custom license attributes are hidden.

Use the code `style="display: none"` to hide custom license attributes, as shown in the following snippet.

```
<fieldset>
  <ol>
    <div id="Flexnet_Part1" class="WideColumnBlock left" style="display: none" >
      <li class="liExtProperty"><label class="required">CUSTLMA_4_Flexnet_Part1:</label>
        <input type='text' ng-model="formData.licenseCustomAttributes['CUSTLMA_4_Flexnet_Part1']
          [0]" />
      </li>
    </div>
  </ol>
</fieldset>
```

```
<div id="Flexnet_Part2" class="WideColumnBlock left" style="display: none" >
  <li class="liExtProperty"><label class="required">CustLMA1:</label>
    <input type='text' ng-model="formData.licenseCustomAttributes['CustLMA1']" />
  </li>
  <li class="liExtProperty"><label >CustLMA2:</label>
    <input type='text' ng-model="formData.licenseCustomAttributes['CustLMA2']" />
  </li>
</div>
</ol>
</fieldset>
```

Notes

- The code `style="display: none"` hides the license attributes for all unselected part numbers. If you want the preview to show the license attributes for all part numbers (regardless of whether they are selected), remove the code `style="display: none"` and then generate a preview. Make sure that after the preview you add this code back to the custom content to enable the toggle functionality in the End-User Portal.
- `Flexnet_Part1` and `Flexnet_Part2` are the part numbers created and mapped to products for trial activation.
- `CUSTLMA_4_Flexnet_Part1`, `CustLMA1` and `CustLMA2` are the names of the custom license model attributes.
- License attributes `CUSTLMA_4_Flexnet_Part1` and `CustLMA1` are required attributes, as indicated by `<label class="required">`, whereas license attribute `CustLMA2` is optional.

Customization Without Toggle Switch for Custom License Attributes

When you do not include a toggle switch, all configured custom license attributes related to available trial part numbers are displayed in the End-User Portal, irrespective of the part number selection.



Note • If you have multiple products defined that use different license models, it is possible that each license model has different custom license attributes defined. For trial activation, all custom license attributes that are associated with the product are displayed, irrespective of the selected part number. In this case, it might be advisable to include a toggle switch, as described in [Customization with Toggle Switch for Custom License Attributes](#).

Sample code

```
<fieldset>
  <ol>
    <div id="Flexnet_Part1" class="WideColumnBlock left" >
      <li class="liExtProperty"><label class="required">CUSTLMA_4_Flexnet_Part1:</label>
        <input type='text' ng-model="formData.licenseCustomAttributes['CUSTLMA_4_Flexnet_Part1']" />
      </li>
    </div>
    <div id="Flexnet_Part2" class="WideColumnBlock left" >
      <li class="liExtProperty"><label class="required">CustLMA1:</label>
        <input type='text' ng-model="formData.licenseCustomAttributes['CustLMA1']" />
      </li>
      <li class="liExtProperty"><label >CustLMA2:</label>
        <input type='text' ng-model="formData.licenseCustomAttributes['CustLMA2']" />
      </li>
    </div>
  </ol>
</fieldset>
```

```

    </ol>
</fieldset>

```

Notes

- **Flexnet_Part1** and **Flexnet_Part2** are the part numbers created and mapped to products for trial activation.
- **CUSTLMA_4_Flexnet_Part1**, **CustLMA1** and **CustLMA2** are the names of the custom license model attributes.
- License attributes **CUSTLMA_4_Flexnet_Part1** and **CustLMA1** are required attributes, as indicated by `<label class="required">`, whereas license attribute **CustLMA2** is optional.

Custom License Attribute Code Samples for Different Data Types

The code snippets in this section demonstrate how to customize the custom license attributes for different data types.

Type "Number"

```

<li class="liExtProperty"><label >CUSTLMA_4_Flexnet_Part1:</label>
  <input type='text' ng-model="formData.licenseCustomAttributes['CUSTLMA_4_Flexnet_Part1'][0]" />
</li>

```

Type "Boolean"

```

<li class="liExtProperty"><label >CLM_BOOLEAN:</label>
  <input type='text' ng-model="formData.licenseCustomAttributes['CLM_BOOLEAN'][0]" />
</li>

```

Note that currently the Boolean data type accepts only true or false as whole words, not T or F as on the Trial Registration page.

Type "Date"

```

<li class="liExtProperty"><label >CLM_DATE:</label>
  <input type='text' ng-model="formData.licenseCustomAttributes['CLM_DATE'][0]" />
</li>

```

Note that currently the Date data type accepts only the date format "MM/DD/YYYY" (for example, 10/24/2018) on the Trial Registration page.

Type "Long Text" and Subtype "Text Area"

```

<li class="liExtProperty"><label >CLM_LONG_TXT_TXT_AREA:</label>
  <input type='text' ng-model="formData.licenseCustomAttributes['CLM_LONG_TXT_TXT_AREA'][0]" />
</li>

```

Type "Long Text" and Subtype "Text Field"

```

<li class="liExtProperty"><label >CLM_LONG_TXT_TXT_FLD:</label>
  <input type='text' ng-model="formData.licenseCustomAttributes['CLM_LONG_TXT_TXT_FLD'][0]" />
</li>

```

Type "Text" and Text Type "Single Select"

You can choose between a dropdown menu or radio buttons.

```

<li class="liExtProperty"><label >CLM_TEXT_FREFORM_SINGLE_SELECT:</label>

```

- Code snippet for dropdown menu:

```
<select ng-model="formData.licenseCustomAttributes['CLM_TEXT_FREFORM_SINGLE_SELECT'][0]"
ng-options="v as v for v in selectedLicenseCustomAttributes['CLM_TEXT_FREFORM_SINGLE_SELECT'].
  values"/>
```

- Code snippet for radio buttons:

```
<table cellpadding="0" cellspacing="0" border="0">
<tbody><tr ng-repeat="value in selectedLicenseCustomAttributes['CLM_TEXT_FREFORM_SINGLE_SELECT'].
  values">
  <td valign="top" nowrap="true">
    <input class="form" type='radio' ng-
      model="formData.licenseCustomAttributes['CLM_TEXT_FREFORM_SINGLE_SELECT']
        [0]"
      name="formData.licenseCustomAttributes['CLM_TEXT_FREFORM_SINGLE_SELECT'][0]" ng-
        value="value" /><label style="text-align:left" >{{value}}</label>
  </td>
</tr>
</tbody>
</table>
```

Type "Text", Text Type "Free Form" and Display Type "Text Area"

```
<li class="liExtProperty"><label >CLM_TEXT_FREFORM_TXTAREA:</label>
  <input type='text' ng-model="formData.licenseCustomAttributes['CLM_TEXT_FREFORM_TXTAREA'][0]" />
</li>
```

Type "Text", Text Type "Free Form" and Display Type "Text Field"

```
<li class="liExtProperty"><label >CLM_TEXT_FREFORM_TXTFIELD:</label>
  <input type='text' ng-model="formData.licenseCustomAttributes['CLM_TEXT_FREFORM_TXTFIELD'][0]" />
</li>
```

Type "Text" and Text Type "Multi-Valued Text"

```
<li class="liExtProperty"><label >CLM_TEXT_MULTI_VALUED_TXT:</label>
  <table cellpadding="0" cellspacing="0" border="0">
    <tbody><tr ng-repeat="value in selectedLicenseCustomAttributes['CLM_TEXT_MULTI_VALUED_TXT'].values">
      <td valign="top" nowrap="true">
        <input class="form" type='checkbox' ng-model="value.checked" />
        <label style="text-align:left" >{{value.val}}</label>
      </td>
    </tr>
  </tbody>
</table>
</li>
```

See Also

[Creating Custom Content](#)
[Managing Email Templates](#)

Listing Custom Content

Use the System menu to show a list of all existing custom content items.

**Task** *To list custom content*

Click **System** > **Custom Content**.

The Producer Portal shows the **Custom Content** page. This page shows the ID, description, and status of each custom content item, plus its last modified date and the Producer Portal user who made the modification. Click the ID of a custom content item to see its **Edit Content** page.

See Also

[Editing Custom Content](#)

[Creating Custom Content](#)

[About Custom Content](#)

[Localizing Custom Content](#)

Creating Custom Content

You can create custom content items from the **Custom Content** page. A new custom content item can replace the default content (if any) on a supported End-User Portal page or create a new standalone page.

**Task** *To create custom content*

1. On the **Custom Content** page, click **Create Content**. The Producer Portal opens the **Create Content** page.
2. On the **Create Content** page, set content details and enter the custom content in the field provided. See Custom Content Attributes in [About Custom Content](#) for more information.



Important - To change the content for a supported End-User Portal page, you must use the custom content ID for that page. To instead create a custom, standalone page, you must use a unique, unused custom content ID value. See Pages that Support Custom Content in [About Custom Content](#) for details.

3. Choose whether the custom content is available to viewers in the End-User Portal:
 - Select the **Hide from Portal?** check box to prevent this content from appearing in the End-User Portal.
 - Leave the **Hide from Portal?** check box clear to allow this content to appear in the End-User Portal (when its status is Live).
4. Choose a template.
 - For producers who want to create a landing page for free product trial registrations, click **Template** > **TrialRegistration**. See [About Product Trial Registration Support](#) for more information, in particular [Sending End Users to a Trial Registration Page](#), which includes the URL for your trial registration page.
 - For all other custom content pages, leave **Template** blank.
5. Click the **Preview** icon. The Producer Portal shows the Preview Content in a pop-up window where you can see the custom content rendered.
6. Choose whether to save the custom content as a draft or to save and publish it:

- Click **Save Draft** to save the content in its current state in Draft status. The Producer Portal saves the custom content with a status of Draft.
- Click **Publish** to save the content in its current state in Live status. The Producer Portal saves the custom content with a status of Live. Custom content with Live status is available to End-User Portal users unless its **Hide from Portal?** check box is selected.

You can edit the custom content later by clicking its ID on the **Custom Content** page.

See Also

[Editing Custom Content](#)
[Listing Custom Content](#)
[Managing Custom Content](#)
[Localizing Custom Content](#)

Editing Custom Content

When you edit custom content, you can alter its ID, description, the custom content, whether or not to show the content in the End-User Portal, and its version.



Tip - Notice that the custom content details on **Edit Content** page include a **Permalink** attribute. If the custom content is to be used as a stand-alone page, use the Permalink URI to link to your custom page.



Note - For more information about the use of content customizations, see [About Custom Content](#).



Task

To edit custom content

1. On the **Custom Content** page, click the ID of the item to edit. The Producer Portal opens the **Edit Content** page for the custom content.
2. If necessary, change the content ID or description for this custom content.
3. Choose whether the custom content is available to viewers in the End-User Portal:
 - Select the **Hide from Portal?** check box to prevent this content from appearing in the End-User Portal.
 - Leave the **Hide from Portal?** check box unselected to allow this content to appear in the End-User Portal (when its status is Live).
4. If necessary, change the version of the custom content with the **Content Version** control.
5. In **Content**, revise the text or HTML as needed.
6. Click the **Preview** icon. The Producer Portal shows the Preview Content in a pop-up window where you can see the custom content rendered.
7. Choose whether to save the custom content as a draft or to save and publish it:
 - Click **Save Draft** to save the content in its current state in Draft status. The Producer Portal saves the custom content with a status of Draft.

- Click **Publish** to save the content in its current state in Live status. The Producer Portal saves the custom content with a status of Live. Custom content with Live status is available to End-User Portal users unless its **Hide from Portal?** check box is selected.



Tip - Note that the **Permalink** attribute on the **Edit Content** page identifies the path to the custom content page where your End-User Portal is hosted. You can link directly to the custom content page by creating a URL that uses your End-User Portal domain plus the **Permalink** value.

See Also

[Creating Custom Content](#)
[Listing Custom Content](#)
[About Custom Content](#)
[Localizing Custom Content](#)

Localizing Custom Content

You can update page instructions for localized sites. When you localize custom content, you create new content by suffixing a custom content ID with a locale code. You can also decide whether or not to show the content in the End-User Portal.



Note - For information about the content that is localizable, see [Localization and Custom Content](#).



Task

To localize custom content

1. On the **Custom Content** page, click **Create Content**. The Producer Portal opens the **Create Content** page.
2. On the **Create Content** page, provide the following information:
 - a. **Content ID:** Enter the content ID of a supported End-User Portal page, followed by the locale code as a suffix to the ID. For example, to localize the epAnnouncements content for France, add the “-fr_FR” suffix to the ID: epAnnouncements-**fr_FR**.
 - b. **Description:** Enter a descriptive name for custom content. (This content will not be visible on the End-User Portal page.)
 - c. Choose whether the custom content is available to viewers in the End-User Portal:
 - Select the **Hide from Portal?** check box to prevent this content from appearing in the End-User Portal.
 - Leave the **Hide from Portal?** check box unselected to allow this content to appear in the End-User Portal (when its status is Live).
3. Leave **Template** blank.
4. In **Content**, enter the localized text or HTML to be displayed in the End-User Portal.
5. Click the **Preview** icon. The Producer Portal shows the Preview Content in a pop-up window where you can see the custom content rendered.

6. Choose whether to save the custom content as a draft or to save and publish it:
 - Click **Save Draft** to save the content in its current state in Draft status. The Producer Portal saves the custom content with a status of Draft.
 - Click **Publish** to save the content in its current state in Live status. The Producer Portal saves the custom content with a status of Live. Custom content with Live status is available to End-User Portal users unless its **Hide from Portal?** check box is selected.

See Also

[Creating Custom Content](#)

[Editing Custom Content](#)

[Listing Custom Content](#)

[About Custom Content](#)

22

Performing Administrative Tasks

Depending on the permissions you have been granted through FlexNet Operations roles, you can perform administration activities using the links in the **Administer** menu.

Table 22-1 •

Topic	Description
Using the Event Notification Service REST API	Use the Event Notification Service REST API to set up real-time event notifications which are triggered whenever an event related to entitlements and products occurs.
Administering Alerts	View and configure alerts using the Alerts links in the Administer menu.
Administering Custom Attributes	View and manage custom attributes, custom host attributes, and custom license attributes.
Importing and Exporting Entities	Migrate data between different FlexNet Operations instances by importing or exporting entities.
Administering License Technologies	Use the License Technologies and Custom Attributes links in the Administer menu to manage license technologies and license generator configurations, and custom license generator and license model attributes.
Administering License Models	View, add, and edit license models.
Working with Time Zones	Describes how to use the time zone functionality to bind license usage to a specified geographic location by identifying the time zone of that region. Only for producers who use certificate-based licenses.
Administering Device and License Server Setup	Covers the setup and administration of device series, device models, server host types, publishers, and publisher identities.

Table 22-1 •

Topic	Description
Working with Transaction Keys	Only for producers who use FlexNet licensing with trusted storage, this section explains how to use transaction keys and anchoring.
Working with Application Specification Records (ASRs)	Explains the use of Application Specification Records (ASRs) for local trials and short code activation.
View and Manage Trusted Activation Requests	Describes how to administer trusted activation requests.
Managing Email and Email Templates	Covers the administration of email messaging as well as email template management.

Using the Event Notification Service REST API



Version • This functionality is not yet available for customers who were recently migrated from the Revera-hosted Data Center to Amazon Web Services (AWS) instances of FlexNet Operations.

A software producer's ecosystem usually involves upstream and downstream systems, with FlexNet Operations being placed between those systems. It is vital that consistent information is shared between all of these systems. Event notifications help producers keep all related enterprise systems up to date. You can use the Event Notification Service API to trigger an event notification whenever a specific event related to products or entitlements occurs. Real-time data about the event is delivered to a specified webhook URL where the data can be consumed programmatically to update the producer's upstream or downstream systems.

Once a webhook has been created, anything can make use of this data. For example, you could use the data to feed an auditing system to keep track of changes made, when and by whom.

The Event Notification Service captures changes related to products or entitlements in the FlexNet Operations Transactional Database. The following diagram shows the data flow from the Transactional Database:

DATA FLOW FOR EVENT NOTIFICATIONS




Figure 22-1: Data flow for event notifications

Producers subscribe to and configure event notifications via the Event Notification Service REST API.

To receive event notifications, the producer must provide the webhook endpoint URLs. These URLs are the endpoints to which the event notifications payload (in JSON format) will be delivered.

The webhooks for entitlement and product events may be different. However, both webhooks must be accessed using the same credentials (that is, using the same user name and password for basic authentication).

This section details which events trigger an event notification and explains how to configure event notifications. It is grouped into the following subsections:

- [Events Triggering Event Notifications](#)
- [Accessing the Event Notification Service REST API](#)
- [Configuring Event Notifications](#)
- [Payload to Webhook Endpoints](#)
- [Monitoring the Event Notification Service Status](#)

Additional Documentation

In addition to this manual, you can consult the Swagger documentation, which provides more detailed information.

Depending on your AWS instance, use one of the following URLs to access the Event Notification Service REST API documentation on Swagger:

<https://<siteID>-uat.flexnetoperations.eu/notifications/swagger-ui.html>

<https://<siteID>-uat.flexnetoperations.com/notifications/swagger-ui.html>

where <siteID> is your organization's site ID which is supplied by Revenera. For production environments, omit "-uat". For more information on <siteID>, see [About Your Site ID](#).

Events Triggering Event Notifications



Version - This functionality is not yet available for customers who were recently migrated from the Revenera-hosted Data Center to Amazon Web Services (AWS) instances of FlexNet Operations.

Producers can subscribe to the following types of events:

- **Entitlement and line items events**—controlled by the entitlementSubscription parameter; set to yes or no.
- **Product events**—controlled by the productSubscription parameter; set to yes or no.

Both parameters, entitlementSubscription and productSubscription, are fields in the **/notificationService** endpoint. For more information, see [Configuration Parameters for Event Notifications](#).

The following table lists the properties which trigger an event notification whenever any of these is changed through the Producer Portal or Web services. A notification is also triggered when an entitlement or product is saved, even if no changes were made.

Table 22-2 - Properties Changes Triggering an Event Notification

Entitlement	Line Item	Product
Entitlement ID	Activation ID	Product Name
Description	Description	Version
Ship-to email	License Model	State
Ship-to Address	License Technology	Description
State	Parent Entitlement Owners	Usage Models
Account	State	Email template to use for product upgrade
Email Template variation	Order ID	Features
Allow Portal Login	Order Line Number	All Linked License Models
	Allowed Node-locked Host ID Types	All mapped Part numbers
	Allowed Server Host ID Types	

Table 22-2 • Properties Changes Triggering an Event Notification

Entitlement	Line Item	Product
	Product Information	Related Product List
	Number of Rehosts	License Technology
	Number of Repairs	License Generator
	Number of Returns	Can be used on a device?
	Expiration Date	Start Date
	Start Date	End Date
	Qty	
	Count	
	Maximum Overdraft	
	Overdraft Remaining	
	Overdraft Floor	
	Overdraft Ceiling	
	Qty Remaining	
	Permanent	
	Upgrade Order	
	Upsell Order	
	Renewal Order	
	Allow activation on Virtual Machines	
	Credit count back to entitlement on a return	

Accessing the Event Notification Service REST API



Version • This functionality is not yet available for customers who were recently migrated from the Revenera-hosted Data Center to Amazon Web Services (AWS) instances of FlexNet Operations.

This section provides details about the base URL and authentication required to access the Event Notification Service REST API.

This section covers the following topics:

- [Base URL](#)
- [Permissions](#)
- [Authentication](#)

Base URL



Version - This functionality is not yet available for customers who were recently migrated from the Reverera-hosted Data Center to Amazon Web Services (AWS) instances of FlexNet Operations.

Endpoints for the Event Notification Service REST API are available on your FlexNet Operations host. Choose the URL applicable to your AWS instance:

```
https://<siteID>-uat.flexnetoperations.eu/notifications/api/v1/notificationService
```

```
https://<siteID>-uat.flexnetoperations.com/notifications/api/v1/notificationService
```

where <siteID> is your organization's site ID which is supplied by Reverera. This is usually your organization's DNS name, but can also be the tenant ID that was assigned to your organization when FlexNet Operations was first implemented, and would have the format **flexNNNN**.

For production environments, omit "-uat".



Note - URLs in this document refer to v1 of the API. Further releases of the API may increment this version.

Permissions



Version - This functionality is not yet available for customers who were recently migrated from the Reverera-hosted Data Center to Amazon Web Services (AWS) instances of FlexNet Operations.

No specific permissions are required to call the **/authenticate** endpoint.

Authentication



Version - This functionality is not yet available for customers who were recently migrated from the Reverera-hosted Data Center to Amazon Web Services (AWS) instances of FlexNet Operations.

When calling the Event Notification Service REST API, an Event Notification Service REST API user must authenticate themselves, using the **/authenticate** endpoint. The Event Notification Service REST API user passes their credentials to the **/authenticate** endpoint, which creates a JSON Web Token (JWT) that can be used to authorize access to any endpoint of the Event Notification Service REST API. Credentials are a Base64-encoded combination of the Event Notification Service REST API user's user name and password separated by a colon (:).



Note - The **/authenticate** endpoint is not added to the base URL. Instead, depending on your AWS instance, use one of the following URLs for authentication:

```
https://<siteID>-uat.flexnetoperations.eu/notifications/api/v1/authenticate
```

```
https://<siteID>-uat.flexnetoperations.com/notifications/api/v1/authenticate
```


where <siteID> is your organization's site ID which is supplied by Reverera. For production environments, omit "-uat". For more information on <siteID>, see [About Your Site ID](#).

The following sections describe the main steps involved in authentication:

- [Step 1: Providing FlexNet Operations Credentials](#)
- [Step 2: Providing a JWT](#)

Step 1: Providing FlexNet Operations Credentials

The following procedures explain how to provide credentials, including an example for each step.



Task **To provide FlexNet Operations credentials**

1. Concatenate the user name and password with a single colon.

Example: If the user name is "serviceuser@reverera.com" and the password is "password", the resulting concatenated string would be serviceuser@reverera.com:password.

2. Base64 encode the concatenated user name and password.

Example: Base64 encode the string serviceuser@reverera.com:password to obtain "c2Vydm1jZXVzZXJAcmlV2ZW51cmEuY29tOnBhc3N3b3JkCg=="

3. Add either "Fno" or "Basic" before the Base64-encoded string.

Examples:

Fno c2Vydm1jZXVzZXJAcmlV2ZW51cmEuY29tOnBhc3N3b3JkCg==

Basic c2Vydm1jZXVzZXJAcmlV2ZW51cmEuY29tOnBhc3N3b3JkCg==

4. Make a POST call to the **/authenticate** endpoint, where you add the "Authorization" key to the header of the request, with the Base64-encoded result as the value.

Example: Add the value "Basic c2Vydm1jZXVzZXJAcmlV2ZW51cmEuY29tOnBhc3N3b3JkCg==" (or "Fno c2Vydm1jZXVzZXJAcmlV2ZW51cmEuY29tOnBhc3N3b3JkCg==") to the Authorization header.

The response will include a JWT, which Event Notification Service REST API users can use to authenticate themselves when calling any endpoint of the Event Notification Service REST API.

Step 2: Providing a JWT

When accessing any endpoint of the Event Notification Service REST API, users authenticate themselves by including the JWT (generated in [Step 1: Providing FlexNet Operations Credentials](#)) in the header of the request. The validity of the JWT is 60 minutes.



Task **To provide a JWT**

1. Call the desired endpoint.
2. Add the "Authorization" key to the header of the request, with the JWT as the value, so that it resembles this example:

Authorization: Bearer

```
eyJhbGciOiJSUzI1NiJ9.eyJleHAiOjE1NTcwOTEwOT19.PMMvCR10kTctS1pDIKzEHIVeJictvc5RrN2keQCU5AUp-  
tg1ekIX00tuaHKZJEfVfDmZqvDu1I47t5_vcB_VeFb12QQirvzkrng1YHbyZMLmc_jMSSsgAqvS1az83jOU71JvF_bZ1_xv503jb  
5MJDoD6v4Miuc-J46hJGe4UvEc
```

Configuring Event Notifications



Version - This functionality is not yet available for customers who were recently migrated from the Revenera-hosted Data Center to Amazon Web Services (AWS) instances of FlexNet Operations.

Configuring event notifications includes configuring the webhook URLs and subscribing to event notifications for the desired events (product or entitlement changes).

This section covers the following topics:

- [Using the Event Notification Service REST API Endpoints](#)
- [Configuration Parameters for Event Notifications](#)

Using the Event Notification Service REST API Endpoints



Version - This functionality is not yet available for customers who were recently migrated from the Revenera-hosted Data Center to Amazon Web Services (AWS) instances of FlexNet Operations.

The following endpoints are available for the Event Notification Service REST API. Prefix each with the appropriate base URL, as described in [Base URL](#).

To access any of the endpoints in the table below, a JWT must be passed in the header of the request. For more information, see [Authentication](#).

Table 22-3 - Overview of Event Notification Service REST endpoints

URI	Methods	Description
/notificationService	GET	Returns the configuration for the event notifications for your FlexNet Operations deployment. Note that using GET does not return the configuration until the service has been configured using POST. The values for the following properties are masked when calling /notificationService using GET: <ul style="list-style-type: none">● authToken● basicUserId● basicPassword● fnoServiceUser● fnoServiceUserPassword
/notificationService	POST	Used for the initial configuration of the event notifications.

Table 22-3 • Overview of Event Notification Service REST endpoints (cont.)

URI	Methods	Description
<code>/notificationService</code>	PATCH	Updates an existing configuration of the event notifications.

Configuration Parameters for Event Notifications



Version • This functionality is not yet available for customers who were recently migrated from the Reverena-hosted Data Center to Amazon Web Services (AWS) instances of FlexNet Operations.

When you call the `/notificationService` endpoint using POST or PATCH, you can pass the following configuration parameters in the request body to enable, configure, or update the event notifications:

Table 22-4 • Event Notifications Configuration Parameters



Property Name	Description
authToken	Authentication token of the webhook endpoints if <code>authType=bearer</code> . Leave empty if <code>authType=none</code> or <code>authType=basic</code> .
authType	Authentication type of the webhook endpoints. Valid values: <code>basic</code> , <code>bearer</code> , and <code>none</code>
basicUserId	User name for basic authentication for the webhook endpoints. The user name and password are passed as a base64-encoded string in the format <code>username:password</code> . Example: Username: <code>reverena_webhook_user</code> Password: <code>cmV2ZW51cmFfd2ViaG9va191c2Vy</code> 
	Important • <code>basicUserId</code> and <code>basicPassword</code> are used for authentication for the <code>entitlementWebhookUrl</code> and <code>productWebhookUrl</code> properties. The credentials must be the same for both webhook endpoints.
basicPassword	Password for basic authentication for the webhook endpoints. The user name and password are passed as a base64-encoded string in the format <code>username:password</code> . 
	Important • <code>basicUserId</code> and <code>basicPassword</code> are used for authentication for the <code>entitlementWebhookUrl</code> and <code>productWebhookUrl</code> properties. The credentials must be the same for both webhook endpoints.

Table 22-4 • Event Notifications Configuration Parameters

Property Name	Description
entitlementSubscription	<p>Set to true to subscribe to event notifications for entitlement and line item changes.</p> <p>Possible values: true or false</p>
entitlementWebhookUrl	<p>Webhook endpoint that receives the information about entitlement and line item events.</p> <p>Example:</p> <p><code>https://api.dev.central.mycompany.com/reverena-webhook/v1/notifications/entitlements</code></p>  <hr/> <p>Important • To access the entitlementWebhookUrl, pass authentication information using the properties basicUserId and basicPassword. The credentials must be the same as for productWebhookUrl.</p>
fnoServiceUrl	<p>The URL to your FlexNet Operations instance. Depending on your AWS instance, the URL has the following format:</p> <p><code>http://<siteID>-fno-uat.flexnetoperations.eu/flexnet/operations/</code> <code>http://<siteID>-fno-uat.flexnetoperations.com/flexnet/operations/</code></p> <p>where <siteID> is your organization's site ID which is supplied by Reverena. This is usually your organization's DNS name, but can also be the tenant ID that was assigned to your organization when FlexNet Operations was first implemented, and would have the format flexNNNN.</p> <p>For production environments, omit "-uat".</p>
fnoServiceUser	User name of the FlexNet Operations user with the system administrator role.
fnoServiceUserPassword	Password of the FlexNet Operations user with the system administrator role.
productSubscription	<p>Set to true to subscribe to event notifications for product and feature changes.</p> <p>Possible values: true or false</p>
productWebhookUrl	<p>Webhook endpoint that receives the information about product and feature events.</p> <p>Example:</p> <p><code>https://api.dev.central.mycompany.com/reverena-webhook/v1/notifications/products</code></p>  <hr/> <p>Important • To access the productWebhookUrl, pass authentication information using the properties basicUserId and basicPassword. The credentials must be the same as for entitlementWebhookUrl.</p>

Table 22-4 • Event Notifications Configuration Parameters

Property Name	Description
activateNotifications	<p>Activates or deactivates all event notifications. Set to true to receive event notifications.</p> <p>Possible values: true or false</p>
siteId	<p>Your site's ID in the UAT (or Production) environment, supplied by Revenera. The site ID is usually your organization's DNS name, but can also be the tenant ID that was assigned to your organization when FlexNet Operations was first implemented. It usually has the format flexNNNN. For the siteId parameter, omit the "flex" prefix.</p> <p>Example:</p> <p>12345</p>

Payload to Webhook Endpoints



Version • This functionality is not yet available for customers who were recently migrated from the Revenera-hosted Data Center to Amazon Web Services (AWS) instances of FlexNet Operations.

The following subsections show a sample payload that would be delivered to a webhook endpoint when a certain event occurs.

Entitlement Event Sample Payload

```
{
  "eventHeader": {
    "event": "ENT",
    "eventType": "UPDATE",
    "userId": "1000admin",
    "tenant": "1000",
    "timeStamp": "1683289809743"
  },
  "eventBody": {
    "entitlementId": "3395",
    "entitlementName": "NOTIF-TEST-3",
    "version": "1.0",
    "soldToAccount": "SAMPLE_ORG",
    "accounts": [
      "SAMPLE_ORG"
    ],
    "lineItems": []
  }
}
```

Line Item Event Sample Payload

```
{
```

```
"eventHeader" : {
  "event" : "ENT",
  "eventType" : "UPDATE",
  "userId" : "1000admin",
  "tenant" : "1000",
  "timeStamp" : "1682400267304"
},
"eventBody" : {
  "entitlementId" : "3394",
  "entitlementName" : "NOTIF-TESTS-1",
  "version" : "1.0",
  "soldToAccount" : "SAMPLE_ORG",
  "accounts" : [ "testAccount", "SAMPLE_ORG" ],
  "lineItems" : [ {
    "activationId" : "ACT-e0e0-7045-B6c2-781",
    "description" : "line desc",
    "licenseModel" : "Floating Counted",
    "orderId" : "addedordId",
    "copies" : "10",
    "exactAvailableCount" : "9",
    "startDate" : "1680048000000",
    "expirationDate" : null,
    "products" : [ {
      "name" : "prodtest1",
      "version" : "2.0"
    } ]
  } ]
} ]
}
```

Product Event Sample Payload

```
{
  "eventHeader": {
    "event": "PROD",
    "eventType": "UPDATE",
    "userId": "1000admin",
    "tenant": "1000",
    "timeStamp": "1665044575475"
  },
  "eventBody": {
    "productId": "1676",
    "productName": "demo-product-for-notifications",
    "version": "1.0",
    "features": [
      {
        "featureName": "2Dline",
        "version": "1",
        "count": "1"
      }
    ]
  }
}
```

Monitoring the Event Notification Service Status



Version - This functionality is not yet available for customers who were recently migrated from the Revenera-hosted Data Center to Amazon Web Services (AWS) instances of FlexNet Operations.

Call the **/health/status** endpoint using GET to monitor the status of the Event Notification Service.



Note - The **/health/status** endpoint is not added to the base URL. Instead, depending on your AWS instance, use one of the following URLs for authentication:

`https://<siteID>-uat.flexnetoperations.eu/notifications/health/status`

`https://<siteID>-uat.flexnetoperations.com/notifications/health/status`

where `<siteID>` is your organization's site ID which is supplied by Revenera. For production environments, omit `-uat`. For more information on `<siteID>`, see [About Your Site ID](#).

The response returns the status; possible responses are as follows:

- 200: OK. Includes the status as UP or DOWN.
- 503: Service Temporarily Unavailable. Returned if the service itself is offline or unreachable.

Sample Response

```
{
  "status": "UP"
}
```

Administering Alerts

Alerts, which by default are displayed in the Start Page, notify FlexNet Operations users of events that may require attention, such as expired or expiring entitlements, updated product definitions, or notifications for importing product part numbers or bulk entitlement Web register keys.

Alerts pages allow you to view a summary of alerts, view the types of alerts, and define alerts. Depending on the permissions you have been granted through roles, you can browse alert messages that have been triggered (and not dismissed) or configure how alerts behave and who is notified when they are triggered.

Table 22-5 -

Topic	Description
Browsing Alerts	Explains how to view alerts.
Dismissing (Removing) an Alert	Describes how to remove alerts from the Alerts page.

Table 22-5 •

Topic	Description
Configuring Alert Behavior	Shows how to configure alert behavior, including setting detection and notification interval, setting email notification properties, and limiting who can see an alert by their user role.
Setting Alert Subscriptions	Explains how to subscribe to an alert. Producers who subscribe to an alert receive an email when the job associated with that alert runs (depending on which alerts have been configured, the outcome of the job, and the subscription properties you set).
FlexNet Operations Alert Types	Provides more information about alert types.

See Also

[More About the Product Version Upgrade Job](#)

[More About the Expiring Entitlements Job](#)

[More About the Expired Entitlements Job](#)

Browsing Alerts

Recent alerts appear on the Producer Portal home page, but you can also browse alerts via the **Administer** menu.

Users assigned roles with the **View Alerts** or **View and Manage Alerts** permission can view a summary of alerts.



Task

To view a summary of alerts

- Click **Administer > Alerts**.

The Producer Portal shows the **Alerts** page.

In the **Alerts** page, you can view the

- **Date:** Date the alert message was sent
- **Message:** Text of the alert message

See Also

[FlexNet Operations Alert Types](#)

[Dismissing \(Removing\) an Alert](#)

[Configuring Alert Behavior](#)

Dismissing (Removing) an Alert

When an alert message is dismissed, its message is removed from the **Alerts** page. After an alert message is dismissed, the alert is displayed again if the alert condition is not corrected before the next time the alert condition is checked (based on the alert's detection and notification interval).

Users assigned a role with the **View and Manage Alerts** permission can dismiss an alert.

**Task** *To remove an alert*

On the **Alerts** page, select the alert and then click **Dismiss** to remove it from the list.

See Also

[Browsing Alerts](#)

[Configuring Alert Behavior](#)

[FlexNet Operations Alert Types](#)

Configuring Alert Behavior

There are alerts available in FlexNet Operations that can be used to notify specified users about different types of conditions or events. Alerts can be configured to display to the **Alerts** page or to send one or more email messages.

Users assigned a role with the **View and Manage Alert Configurations** permission can configure alert behavior.

**Task** *To configure the behavior of an alert*

1. Click **Administer > Configure Alerts/Jobs**.
2. For the alert type you want to configure, click **Configure**. The Producer Portal shows the **Configure Alert/Job Schedule** page.
3. On the **Configure Alert/Job Schedule** page, select a Status of **Active** or **Inactive**. When you select **Active**, the Schedule option appears. For all alerts, except **Purge Email History**, the default status is **Inactive**.
4. For the **Schedule** option you can:
 - Select the **Standard** option to set the number and time interval (default is 30 days).



Note - For **Purge Email History**, the default setting is to run once a day. It purges all sent emails older than 183 days or whatever is configured in **System > Configuration**.

- Select the **Advanced** option to set a cron expression for the time and frequency of the schedule. See [Creating a Customized Schedule](#) for more information.

An alert condition is first checked within a couple of minutes of the configuration being saved. Thereafter, the alert condition is checked according to the **Schedule**. For example, if an alert was configured with an interval of 15 minutes, the first check occurs a couple of minutes after the configuration is saved. The second check occurs 15 minutes after the first checking process finishes, the third check occurs 15 minutes after the second checking process finishes, etc. Therefore, the clock time that an alert condition is checked varies according to when the original alert configuration was saved and how long each checking process lasts.

5. Specify a **Subscription Restriction**. You can choose to allow only certain roles to subscribe to the alert.
 - Click **Add**.
 - Check the role(s) that you wish to allow to subscribe to that alert.

- Click **Select**, to save.

6. Click **Save**.

The Producer Portal saves your alert behavior changes.

See Also

- [FlexNet Operations Alert Types](#)
- [Browsing Alerts](#)
- [Dismissing \(Removing\) an Alert](#)
- [Creating a Customized Schedule](#)

Creating a Customized Schedule

For more advanced scheduling options, you can use a CronTrigger using a standard cron expression. A cron expression is a string consisting 6-7 fields (sub-expressions) that describe the details of the schedule. These fields are separated by a white space and are described in table [Allowed Fields and Values of Cron Expressions](#) in their expected order.

Table 22-6 ▪ Allowed Fields and Values of Cron Expressions

Field	Required	Allowed Values	Allowed Special Characters
Seconds	Yes	0-59	, - * /
Minutes	Yes	0-59	, - * /
Hours	Yes	0-23	, - * /
Day of Month	Yes	1-31	, - * / ? L W
Month	Yes	0-11 or JAN-DEC	, - * /
Day of Week	Yes	1-7 or SUN-SAT	, - * / ? L #
Year	No	empty or 1970-2099	, - * /

The purpose of the special characters is explained in the following table:

Table 22-7 ▪ Explanation of Special Characters

Character	Description
,	Used to specify a list of values not in a range. For example: “2,4,6” or “MON,WED,FRI” in the day-of-the-week field means “the days Monday, Wednesday and Friday”.
-	Used to indicate a range of values or an offset. For example “10-12” in the hour field means “the hours 10-12”.
*	Wildcard meaning every possible value of this field.

Table 22-7 • (cont.)Explanation of Special Characters




Character	Description
/	Used to specify increments to values. For example “0/15” in the minutes field means “every 15th minute of the hour, starting at minute zero”, i.e. 0, 15, 30, and 45. A “3/20” in the minutes field means “every 20 minutes starting at minute 3”, i.e. 3, 23 and 43. A “1/3” in the day-of-the-month field means “every three days starting on the first day of the month.” Omitting the initial number is equivalent to using 0, i.e. “/35” is the same as “0/35”.
?	Used for day-of-the-month and day-of-the-week fields to mean “no specific value”. This is useful when you must specify something in one of the two fields but not the other. For example if you want to schedule a job for the 10th day of the month, regardless of the day of the week, you would put a “10” in the day-of-the-month field and a “?” in the day-of-the-week field.
L	<p>Used for day-of-the-month and day-of-the-week fields and is used to specify “Last”, but it has different interpretations in each of those fields. An “L” in the day-of-the-month field means the “last day of the month, i.e. 31 for January or 28 for February on non-leap years and 29 on leap years.</p> <p>If used in the day-of-the-week field by itself, it means “7” or “SAT”, but if used in the day-of-the-week field after another value, it means the last X day of the month. For example, “6L” or “FRIL” both mean “the last Friday of the month.” You can also specify offsets such as “L-3” which means the third to the last day of the calendar month.</p> <p></p> <p>Note • When using the “L” option, it is important not to specify lists or ranges of values as you will get unexpected results.</p> <p>The “L” and “W” characters can be combined in the day-of-the-month field to yield “LW” which means “last weekday of the month”.</p>
W	<p>Used to specify the “Weekday” (Monday-Friday) nearest the given day. For example 15W as a day-of-the-month value means, “the nearest weekday to the 15th of the month.” However, if you specify “1W” as the value for the day-of-the-month and the 1st is on a Saturday, the job is scheduled for Monday, the 3rd because the previous Friday (which is closer to the 1st) is in a different month.</p> <p></p> <p>Note • When using the “W” option, it is important not to specify lists or ranges of values as you will get unexpected results.</p>

Table 22-7 ▪ (cont.)Explanation of Special Characters

Character	Description
#	Used for day-of-the-week fields to specify <i>n</i> th <i>x</i> day of the month. For example, the value “6#3” or “FRI#3” means “the third Friday of the month.”
	 <p>Note ▪ If you specify #5 and there are not 5 of the given day-of-the-week in the month, then no firing occurs that month.</p>

Cron Expression Examples

The following table gives a list of example cron expressions.

Table 22-8 ▪ Sample Cron Expressions

Expression	Meaning
0 0 12 * * ?	Fire at 12:00pm (noon) every day
0 15 10 ? * *	Fire at 10:15am every day
0 15 10 * * ?	Fire at 10:15am every day
0 15 10 * * ? *	Fire at 10:15am every day
0 15 10 * * ? 2017	Fire at 10:15am every day during the year 2017
0 10,44 14 ? 3 WED	Fire at 2:10pm and at 2:44pm every Wednesday in the month of March
0 15 10 ? * MON-FRI	Fire at 10:15am every Monday, Tuesday, Wednesday, Thursday, and Friday
0 15 10 15 * ?	Fire at 10:15am on the 15th day of every month
0 15 10 L * ?	Fire at 10:15am on the last day of every month
0 15 10 L-2 * ?	Fire at 10:15am on the 2nd-to-last day of every month
0 15 10 ? * 6L	Fire at 10:15am on the last Friday of every month
0 15 10 ? * 6L	Fire at 10:15am on the last Friday of every month
0 15 10 ? * 6L 2017-2020	Fire at 10:15am on every last Friday of every month during the years 2017, 2018, 2019, and 2020
0 15 10 ? * 6#3	Fire at 10:15am on the third Friday of every month
0 0 12 1/5 * ?	Fire at 12pm (noon) every 5 days every month, starting on the first day of the month
0 11 11 11 11 ?	Fire every November 11th at 11:11am



Note - Be mindful of setting times between the hours of the morning when the change to or from “daylight saving time” begins (for U.S. locales, this is between 1 am and 3 am) because the time shift can cause a skip or a repeat depending on whether the time moves back or jumps forward.

See Also

[FlexNet Operations Alert Types](#)
[Browsing Alerts](#)
[Configuring Alert Behavior](#)
[Dismissing \(Removing\) an Alert](#)

Setting Alert Subscriptions

After you have set the behavior of an alert type, you can set up to three email subscriptions for that alert type. Users assigned a role with the **View and Manage Alert Configurations** permission can set an alert subscription.



Task *To set an email subscription for an alert type*

1. In the user menu, click your name and then click **Alert Subscriptions**.
2. Click **Subscribe/Edit** for one of the alert types.
3. In the **Create/Edit Alert Subscription** page, set the following properties:
 - **Inbox Notification:** Choose whether or not to display the alert in the **Alerts** page. Once the alert has been displayed in the page, it is not displayed again unless the alert is dismissed and the alert condition remains uncorrected.
 - **Show Additional Email Notifications:** Select the box to configure more than one email subscription. One email notification per detected alert is sent for each email subscription that is specified for an alert. Consider setting up multiple email subscriptions with different trigger times to escalate alerts to different email recipients if an alert condition is not corrected.



Task *To configure email subscription properties*

1. Select the **Enabled** check box for the subscription.
2. Supply the following information for the alert subscription:
 - **Trigger time:** Minutes, hours, days after the alert date or days before the alert date. The alert date is the time the alert condition began, and the trigger time is the time offset from the alert date when the alert email is triggered, but not necessarily sent. Email with a trigger delay is sent when the alert condition is next checked after the trigger time has passed, if the triggering alert has not been dismissed.

Note that if an email subscription is set with a trigger time delay (for example, 1 hour) less than the detection interval (for example, 1 day), an email could be triggered by an alert condition on Monday, but not actually be sent until the alert is checked again on Tuesday (if the alert was not dismissed). Therefore, for clarity, set a trigger time to be a multiple of the **Detection and Notification Interval**.

We strongly recommend setting one subscription to trigger immediately upon detection of the event and setting trigger time delays only on additional subscriptions.

- **Send Email to:** Address for alert email. Multiple email address can be specified in a comma-separated list.

3. Click **Save**.

See Also

[Configuring Alert Behavior](#)

[FlexNet Operations Alert Types](#)

FlexNet Operations Alert Types

Alerts can be used to notify specified users about different types of conditions or events.

In new installations of FlexNet Operations, all alerts are set to Inactive. If you want an alert to run, you must set its status to active and define an interval at which it is to run. (Upgrades of FlexNet Operations from previous versions retain the previous alert status.)

Table 22-9 • FlexNet Operations Alerts

Alert Type	Possible Values	Description
User Deactivated	Detection and notification interval: <i>n</i> minutes, hours, days. The default is 30 seconds.	Generated when a user has been deactivated because the user has incorrectly logged in to FlexNet Operations too many times. The number of times that a user login can fail within a specified time period before being deactivated can be configured in the FlexNet Platform Server configuration . A FlexNet Operations administrator must reactivate a deactivated user before the user can log in to FlexNet Operations again.
Expired/Expiring Entitlements	Detection and notification interval: <i>n</i> minutes, hours, days. The default is 1 day.	Generated when any entitlement line items are expiring in the next 30 days. Lists all of the line items that are expiring in the next 30 days and all the line items that have already expired.
Updated Products	Detection and notification interval: <i>n</i> minutes, hours, days. The default is 1 day.	Generated when a Licensed Product is updated.

Table 22-9 • FlexNet Operations Alerts




Alert Type	Possible Values	Description
Importing Bulk Entitlement Web Register Keys	Detection and notification interval: <i>n</i> minutes, hours, days. The default is 1 day.	<p>Generated when bulk entitlement Web register keys are imported.</p> <p>This job is required for producers who want to load Web register keys via a user-supplied file, via auto-generation, or via Web service requests that are processed asynchronously.</p> <p></p> <p>Tip • If this job is not active, FlexNet Operations does not import Web register keys. See Loading Web Register Keys for more information.</p>
Export and Import Background Jobs	Detection and notification interval: <i>n</i> minutes, hours, days. The default is 1 day.	<p>Controls how frequently FlexNet Operations checks for new export or import background jobs.</p> <p>When scheduled and active, this job runs background import jobs based on both JAR file imports and data import template imports. Likewise, this alert runs any background export jobs (regardless of format) that are pending.</p>
Fulfillment Data Extract	Detection and notification interval: <i>n</i> minutes, hours, days. The default is 30 days.	<p>Controls how often FlexNet Operations runs a job to generate a snapshot of fulfillment events.</p> <p>This job takes a snapshot of fulfillments that have been created or updated. Designed to be run on a daily basis, this job's first run gathers data on events from the previous day—from 00:00:00 until 23:59:59. Subsequently, the job attempts to gather data on events starting from the end of the last successful run of the job until the current time.</p> <p></p> <p>Note • The date/time format of the data extract is controlled by the Use ISO 8601 time format in extracts configuration option. For more information, see Use ISO 8601 time format in extracts in <i>Configuring System Settings</i>.</p> <p></p> <p>Note • For more information on this extract, see the <i>FlexNet Operations Web Services Integration Guide</i>.</p>

Table 22-9 • FlexNet Operations Alerts





Alert Type	Possible Values	Description
Device Data Extract	Detection and notification interval: <i>n</i> minutes, hours, days. The default is 30 days.	<p>Controls how often FlexNet Operations runs a job to generate a snapshot of device and license server events.</p> <p>This job takes a snapshot of devices and license servers that have been created or updated (including the licenses mapped to them). Designed to be run on a daily basis, this job's first run gathers data on events from the previous day—from 00:00:00 until 23:59:59. Subsequently, the job attempts to gather data on events starting from the end of the last successful run of the job until the current time.</p> <hr/> <p> Version - Only producers who use FlexNet Embedded licensing gather device and license server events.</p>
Served Device Data Extract	Detection and notification interval: <i>n</i> minutes, hours, days. The default is 30 days.	<p>Controls how often FlexNet Operations runs a job to generate a snapshot of served device events.</p> <p>This job takes a snapshot of served devices that have been created or updated. Designed to be run on a daily basis, this job's first run gathers data on events from the previous day—from 00:00:00 until 23:59:59. Subsequently, the job attempts to gather data on events starting from the end of the last successful run of the job until the current time.</p> <hr/> <p> Note - The date/time format of the data extract is controlled by the Use ISO 8601 time format in extracts configuration option. For more information, see Use ISO 8601 time format in extracts in <i>Configuring System Settings</i>.</p> <hr/> <p> Note - For more information on this extract, see the <i>FlexNet Operations Web Services Integration Guide</i>.</p> <hr/> <p> Version - Only producers who use FlexNet Embedded licensing gather served device events.</p>

Table 22-9 • FlexNet Operations Alerts





Alert Type	Possible Values	Description
User Data Extract	Detection and notification interval: <i>n</i> minutes, hours, days. The default is 30 days.	<p>Controls how often FlexNet Operations runs a job to generate a snapshot of user events.</p> <p>This job takes a snapshot of user accounts that have been created or updated. Designed to be run on a daily basis, this job's first run gathers data on events from the previous day—from 00:00:00 until 23:59:59. Subsequently, the job attempts to gather data on events starting from the end of the last successful run of the job until the current time.</p> <hr/> <p> Note • The date/time format of the data extract is controlled by the Use ISO 8601 time format in extracts configuration option. For more information, see Use ISO 8601 time format in extracts in <i>Configuring System Settings</i>.</p> <hr/> <p> Note • For more information on this extract, see the <i>FlexNet Operations Web Services Integration Guide</i>.</p>
Account Data Extract	Detection and notification interval: <i>n</i> minutes, hours, days. The default is 30 days.	<p>Controls how often FlexNet Operations runs a job to generate a snapshot of account events.</p> <p>This job takes a snapshot of accounts that have been created or updated. Designed to be run on a daily basis, this job's first run gathers data on events from the previous day—from 00:00:00 until 23:59:59. Subsequently, the job attempts to gather data on events starting from the end of the last successful run of the job until the current time.</p> <hr/> <p> Note • The date/time format of the data extract is controlled by the Use ISO 8601 time format in extracts configuration option. For more information, see Use ISO 8601 time format in extracts in <i>Configuring System Settings</i>.</p> <hr/> <p> Note • For more information on this extract, see the <i>FlexNet Operations Web Services Integration Guide</i>.</p>

Table 22-9 • FlexNet Operations Alerts



Alert Type	Possible Values	Description
Usage Data Extract	Detection and notification interval: <i>n</i> minutes, hours, days. The default is 30 days.	<p>Controls how often FlexNet Operations runs a job to generate a snapshot of all usage events from the previous day.</p> <p>Designed to be run on a daily basis, this job's first run gathers data on events from the previous day—from 00:00:00 until 23:59:59. Subsequently, the job attempts to gather data on events starting from the end of the last successful run of the job until the current time.</p> <hr/> <p> Note - The date/time format of the data extract is controlled by the Use ISO 8601 time format in extracts configuration option. For more information, see Use ISO 8601 time format in extracts in <i>Configuring System Settings</i>.</p> <hr/> <p> Note - For more information on this extract, see the <i>FlexNet Operations Web Services Integration Guide</i>.</p>
Product Version Upgrade	Detection and notification interval: <i>n</i> minutes, hours, days. The default is 30 days.	<p>Controls how often FlexNet Operations runs a job to automatically add product upgrade line items to eligible entitlements. This job creates upgrade line items for qualifying products and line items.</p> <p>Note that logic the Product Version Upgrade job may create unwanted upgrade lines and related email messages for producers who are not properly prepared for its use.</p> <p>See More About the Product Version Upgrade Job for guidelines about using this job as well as product and line-item eligibility requirements.</p>
Expiring Entitlements	Detection and notification interval: <i>n</i> minutes, hours, days. The default is 30 days.	<p>Controls how often FlexNet Operations runs a job to identify entitlements scheduled to expire in the near future.</p> <p>When this job finds entitlements that are nearing their expiration date, FlexNet Operations generates a Renewal Reminder email message and sends it to end users in the account that owns the entitlement and have subscribed to receive renewal notifications (users that have the Expiring Entitlements Email check box selected).</p> <p>See More About the Expiring Entitlements Job for guidelines about using this job.</p>

Table 22-9 • FlexNet Operations Alerts





Alert Type	Possible Values	Description
Expired Entitlements	Detection and notification interval: <i>n</i> minutes, hours, days. The default is 30 days.	<p>Controls how often FlexNet Operations runs a job to identify entitlements that have expired.</p> <p>When this job finds entitlements that have expired, FlexNet Operations generates an Expired Entitlements email message and sends it to end users in the account that owns the entitlement and have subscribed to receive renewal notifications (users that have the Expiring Entitlements Email check box selected).</p> <p>See More About the Expired Entitlements Job for guidelines about using this job.</p>
Entitlement Data Extract	Detection and notification interval: <i>n</i> minutes, hours, days. The default is 1 day.	<p>Controls how often FlexNet Operations runs a job to generate a snapshot of all entitlement data from the previous day.</p> <p>Designed to be run on a daily basis, this job's first run gathers data on events from the previous day—from 00:00:00 until 23:59:59. Subsequently, the job attempts to gather data on events starting from the end of the last successful run of the job until the current time.</p> <p></p> <p>Note - For more information on this extract, see the <i>FlexNet Operations Web Services Integration Guide</i>.</p>
Device Updates Extract	Detection and notification interval: <i>n</i> minutes, hours, days. The default is 30 days.	<p>Controls how often FlexNet Operations runs a job to generate a snapshot of updates applied to standalone devices.</p> <p>Designed to be run on a daily basis, this job's first run gathers data on events from the previous day—from 00:00:00 until 23:59:59. Subsequently, the job attempts to gather data on events starting from the end of the last successful run of the job until the current time.</p> <p></p> <p>Note - For more information on this extract, see the <i>FlexNet Operations Web Services Integration Guide</i>.</p> <p></p> <p>Version - Only for producers who use Software Delivery.</p>

Table 22-9 • FlexNet Operations Alerts

Alert Type	Possible Values	Description
Updates Extract	Detection and notification interval: <i>n</i> minutes, hours, days. The default is 30 days.	<p>Controls how often FlexNet Operations runs a job to generate a snapshot of new updates that have been added to the system.</p> <p>Designed to be run on a daily basis, this job’s first run gathers data on events from the previous day—from 00:00:00 until 23:59:59. Subsequently, the job attempts to gather data on events starting from the end of the last successful run of the job until the current time.</p> <hr/> <p> Note - For more information on this extract, see the <i>FlexNet Operations Web Services Integration Guide</i></p> <hr/> <p> Version - This job is only available for producers who use the <i>Software Delivery</i> module.</p>
Line Item Auto Renewal	Detection and notification interval: <i>n</i> minutes, hours, days. The default is 1 day.	<p>Controls how often FlexNet Operations runs a job to automatically renew line items that are marked for auto-renewal (in the Configure Line Item Wizard in the Configure Product section).</p> <p>By default, the job is inactive.</p> <p>For more information, see also Automatic Renewal of Line Items.</p>

See Also

[Configuring Alert Behavior](#)
[Browsing Alerts](#)

More About the Product Version Upgrade Job

The Product Version Upgrade job automates the creation of upgrade line items. For eligible products and line items, it causes FlexNet Operations to create upgrade line items, to add them to existing entitlements, and to send an email message to end users to notify them about the upgrade.



Important - To avoid the creation of unexpected upgrade line items and unwanted email messages, be sure to review the guidance in [Product Version Upgrade Use Guidelines](#) and [Product and Line Item Eligibility Rules](#) before scheduling the Product Version Upgrade job.

Product Version Upgrade Use Guidelines

Due to the qualifications FlexNet Operations uses to determine which entitlements receive the automatic upgrade line items, the use of this feature is best suited for producers who structure their product upgrades in the following ways:

- Product upgrade relationships are relatively simple. Products upgrade in a direct line from one version to the next without branching into multiple upgrade paths.
- Permanent entitlements, if offered, are sold with maintenance items.
- All accounts are entitled to product upgrades. (No need to filter out specific accounts.)

Producers who follow different product upgrade models may not benefit from using the Product Version Upgrade Job.



Note - To support the Product Version Upgrade job, products include product-upgrade-specific attributes: **Start Date**, **End Date**, and **Email Template to Use for Product Upgrade**. The dates play a role in determining which products are eligible to upgrade. The email template attribute specifies which variation to use for the email messages sent to end users as a result of this new job. See [Creating a Product](#) for more information.

Product and Line Item Eligibility Rules

The Product Version Upgrade job determines which entitlements receive upgrade line items based on associated product and line item attributes.

- Upgrade relationships must exist between the products (with only one possible upgrade-to path).
- The license model to use for upgrade entitlements must be clearly determined due to some combination of the following conditions:
 - An upgrade product is linked to the same license model as the license model on the line item to be upgraded.
 - An upgrade product is linked to only one license model.
 - A default license model has been defined on an upgrade relationship. (See [Relating Products to Other Products](#) for instructions on setting the default license model in **Upgrade Default Model** for an upgrade relationship.)
- Product start and end dates are either valid or unspecified.
- Line items must be deployed.
- Line items cannot include multiple products.
- Permanent line items must be linked to a maintenance item that has not expired.
- Non-permanent line items must not be expired (past a known end date). They are not required to be linked to a maintenance item. However, when a non-permanent line item is linked to a maintenance item, the maintenance item must not be expired.
- If a line item is linked to a maintenance line item, the following conditions must be met:
 - Maintenance products must have Allow Upgrades set to Yes.

- The upgrade-to product must be related to all the maintenance products to which the upgrade-from product is related. The Product Version Upgrade job does not create upgrade lines for a product if the upgrade-from product has relationships that the upgrade-to product does not have.
- Line items must not already have been otherwise upgraded, upsold, or renewed.

Entitlements that do not meet these qualifications are ignored by the upgrade job.

Avoiding the Creation of Upgrade Line Items with Incompatible License Models

Some license technology and license model conflicts can prevent the successful activation of upgrade line items. (FlexNet Operations does not prevent the creation of these upgrade line items, but the resulting line items cannot be successfully activated.) The following upgrade paths result in upgrade line items that cannot be activated:

Table 22-10 •

Upgrading From	Upgrading To	Notes
Custom licensing	FlexNet Publisher Trusted Licensing	Sharing counts between a license model from a custom license technology and retail activation license model is not supported.
FlexNet Publisher Certificate Licensing	FlexNet Publisher Trusted Licensing	Sharing counts between a floating, counted license model and a retail activation license model is not supported.
FlexNet Embedded Licensing	FlexNet Publisher Certificate Licensing	Sharing counts between an embedded counted license model and a node-locked, uncounted license model is not supported.
FlexNet Embedded Licensing	FlexNet Publisher Trusted Licensing	Sharing counts between an embedded, counted license model and a retail activation license model is not supported.

Information Copied During the Upgrade

During the upgrade job, the following information is copied from the line item to be upgraded to the upgrade line:

- License model (if possible)
- Start date and license term settings
- Number of copies
- Custom line item attribute values
- Entitlement-time license model attribute values. (This copying happens even if the license technologies are different as long as the license model attributes have the same name and data type.)



Tip • To learn about how predefined and custom attribute values can be substituted into license strings, see [Employing a Predefined Substitution Variable](#).

Running the Job

Producers can schedule the Product Version Upgrade job to run activating the Product Version Upgrade alert on its **Configure Alert Definition** page. By default, this alert is inactive and the Product Version Upgrade job does not run. (See [Configuring Alert Behavior](#) for instructions.)

When the Product Version Upgrade job is completed, customers can use the End-User Portal to view the new upgrade line items in their entitlements, then download and activate them.

See Also

[FlexNet Operations Alert Types](#)
[Creating a Product](#)
[Configuring Alert Behavior](#)

More About the Expiring Entitlements Job

The Expiring Entitlements job finds entitlements that are nearing their expiration date and generates email messages to end user accounts with expiring entitlements.

Like other jobs, producers can schedule the Expiring Entitlements job and subscribe to its alerts in the Producer Portal. However, when the Expiring Entitlements job finds entitlements that are soon to expire for an account, FlexNet Operations generates an email message about that account's expiring entitlements and attempts to send the message to the account's users. End users who elect to receive renewal notifications will receive an email message when their account's entitlements are nearing their expiration date.

The FlexNet Customer Growth module also adds an End-User Portal page to list expiring entitlements and to highlight those entitlements that are closest to their expiration date. From this **Expiring Entitlements** page, end users can click the **Request** button to send the producer an email message that indicates their intent to renew.

For producers, a number of system configuration settings determine when email messages are triggered, which entitlements are included in the Renewal Reminder message, whether or not an email is to be sent, and how frequently an account can receive such email messages. Producers can also customize the email template FlexNet Operations uses when it sends these renewal notifications.



Tip ▪ In determining when to send a Renewal Reminder email message, FlexNet Operations uses the system configuration settings **Renewal Look Ahead** (default: 200 days), **Expiring Window** (default: 90 days), and **Expiring Email Frequency** (default: 30 days). These values are set in the Renewals settings on the FlexNet Operations system configuration page at **System > Configure > FlexNet Operations**. For details about these system configuration settings, see [Configuring System Settings](#).

Understanding When FlexNet Operations Generates a Renewal Reminder Email Message

When the Expiring Entitlements job runs, it scans all of your end user accounts' entitlements to see if any are approaching their expiration date. For a given account, FlexNet Operations first looks to see if any of the entitlements have line items or maintenance lines expiration dates that fall within the Expiring Window. If so, FlexNet Operations then checks when that account last received a Renewal Reminder email message.

- If FlexNet Operations has recently sent a Renewal Reminder email message to the account, no new email messages are sent, even if newly expiring entitlements (per the Expiring Window setting) are discovered when the Expiring Entitlements job runs.

- If FlexNet Operations has not sent an email to the account within the number of days specified in the system configuration setting, Expiring Email Frequency, it generates a new Renewal Reminder email message for that account.

Using the default system configuration settings, when an account has expiring entitlements, FlexNet Operations limits the frequency of its renewal reminders to once every 30 days per account. Producers can customize this frequency (**Expiring Email Frequency**) to best suit the needs of their end users.



Note ▪ The decision of whether or not to generate an email is made at the account level. The choice to receive renewal notifications happens at the user level. End users who belong to multiple accounts may receive multiple Renewal Reminder messages (one for each account that qualifies for an Renewal Reminder email message).

Anticipating the Content of the Renewal Reminder Email Message

The content of the Renewal Reminder email message that FlexNet Operations generates depends mainly on two factors:

- The **Renewal Reminder** email template content. Producers can customize the content of the email template FlexNet Operations uses to send Renewal Reminder email messages. (See [Managing Email Templates](#) for instructions on editing an email template.)
- The account's entitlement line items and maintenance lines that expire within the number of days specified in the system configuration setting, **Renewal Look Ahead**.

For the Renewal Reminder email message, FlexNet Operations compiles a list of all the account's entitlements with line items or maintenance lines that expire within the Renewal Look Ahead range. All the account's line items and maintenance lines that expire within that range are all included in the Renewal Reminder email message that FlexNet Operations generates.



Tip ▪ The Renewal Look Ahead is a separate system configuration from the Expiring Window setting. The Expiring Window determines whether or not to generate an Renewal Reminder message. The Renewal Look Ahead determines which line items or maintenance lines are included in the message itself.

Understanding Who Receives Renewal Reminders

After generating a Renewal Reminder message for an account, FlexNet Operations sends the message to that account's End-User Portal users who have opted to receive expiring entitlement email. If none of the account's end users is subscribed to receive renewal reminders, FlexNet Operations instead sends the Renewal Reminder message to the address you specify for the system configuration setting, Renewal Failed Notification Email (optional). If there are no end users who have subscribed to receive renewal reminders and no valid email address specified for Renewal Failed Notification Email, then FlexNet Operations does not send any renewal reminders for that account, even if the Expiring Entitlements job finds qualifying, expiring entitlements.



Tip ▪ To receive renewal reminders, end users must select the **Expiring Entitlements Email** check box in their user profiles.



Important • End users must have the **View Expiring Entitlements** permission to subscribe to see the **Expiring Entitlements Email** check box, receive renewal reminders, or see the **Expiring Entitlements** page in the End-User Portal. (End users with the Portal Administrator User role have the View Expiring Entitlements permission by default.)

See Also

[Configuring System Settings](#)
[Administering Alerts](#)
[About Email Templates](#)

More About the Expired Entitlements Job

The Expired Entitlements job finds entitlements that have expired since the last time the job was run and generates email messages to end-user accounts with expired entitlements.

Like other jobs, producers can schedule the Expired Entitlements job and subscribe to its alerts in the Producer Portal. However, when the Expired Entitlements job finds entitlements that are expired for an account, FlexNet Operations generates an email message about that account's expired entitlements and attempts to send the message to the account's users. End users who elect to receive renewal notifications will receive an email message when their account's entitlements have expired.

The FlexNet Customer Growth module also adds an End-User Portal page to list expiring entitlements and to highlight those entitlements that are closest to their expiration date. (Expired entitlements are not shown by default. End users can use on-page filters in the End-User Portal to include expired entitlements in the list.) From the **Expiring Entitlements** page, end users can click the **Request** button to send the producer an email message that indicates their intent to renew.

For producers, system configuration settings help determine how frequently an account can receive such email messages, as well as which expired entitlements appear in the End-User Portal's **Expiring Entitlements** page. Producers can also customize the email template FlexNet Operations uses when it sends these renewal reminders.



Tip • In determining when to send an Expired Entitlements email message, FlexNet Operations uses the system configuration setting, **Expired Email Frequency** (default: 30 days). This value is set in the Renewals settings on the FlexNet Operations system configuration page at **System > Configure > FlexNet Operations**. For details about these system configuration settings, see [Configuring System Settings](#).

Understanding When FlexNet Operations Generates an Expired Entitlements Email Message

When the Expired Entitlements job runs, it scans all of your end user accounts' entitlements to see if any have expired line items or maintenance lines. If so, FlexNet Operations then checks when that account last received an email message about expired entitlements (based on the Renewal Reminder for Expired Entitlements email template).

- If FlexNet Operations has recently sent an email message about expired entitlements to the account, no new email messages are sent, even if newly expired entitlements are discovered when the Expired Entitlements job runs.

- If FlexNet Operations has not sent an expired entitlements message to the account within the number of days specified in the system configuration setting, Expired Email Frequency, it generates a new renewal reminder email message for that account.

Using the default system configuration settings, when an account has expired entitlements, FlexNet Operations limits the frequency of its expired entitlements message to once every 30 days per account. Producers can customize this frequency (**Expired Email Frequency**) to best suit the needs of their end users.



Note ▪ The decision of whether or not to generate an email is made at the account level. The choice to receive renewal notifications happens at the user level. End users who belong to multiple accounts may receive multiple Renewal Reminder for Expired Entitlements messages (one for each account that qualifies for an expired entitlements message).

Anticipating the Content of the Expired Entitlements Email Message

The content of the Expired Entitlements email message that FlexNet Operations generates depends mainly on two factors:

- The **Renewal Reminder for Expired Entitlements** email template content. Producers can customize the content of the email template FlexNet Operations uses to send Expired Entitlements email messages. (See [Managing Email Templates](#) for instructions on editing an email template.)
- The account's entitlement line items and maintenance lines that have expired since the last time the expired entitlements message was sent to subscribed users in that account.

FlexNet Operations uses the Renewal Reminder for Expired Entitlements email template to create expired entitlements messages. For this email message, FlexNet Operations compiles a list of all the account's line items and maintenance lines that expired since the Expired Entitlements job was last run and includes that list in the message.



Tip ▪ The frequency with which the Expired Entitlements job runs is set on its **Configure Alert/Job Schedule** page, but the frequency with which FlexNet Operations sends expired entitlements messages is also restricted by the system configuration setting, **Expired Entitlements Frequency**. Even if the job runs and finds new expired entitlements, no email messages about expired entitlements are sent for a particular account until the specified number of days has passed since the account was last messaged about expired entitlements.

Understanding Who Receives Renewal Reminders

After generating a Renewal Reminder message for an account, FlexNet Operations sends the message to that account's End-User Portal users who have opted to receive expiring entitlement email. If none of the account's end users is subscribed to receive renewal reminders, FlexNet Operations instead sends the expired entitlements message to the address you specify for the system configuration setting, Renewal Failed Notification Email (optional). If there are no end users who have subscribed to receive renewal reminders and no valid email address specified for Renewal Failed Notification Email, then FlexNet Operations does not send any renewal reminders for that account, even if the Expired Entitlements job finds qualifying, expired entitlements.



Tip ▪ To receive renewal reminders, end users must select the **Expiring Entitlements Email** check box in their user profiles.



Important - End users must have the **View Expiring Entitlements** permission to subscribe to see the **Expiring Entitlements Email** check box in their user profiles, receive expired entitlements messages, or see the **Expiring Entitlements** page in the End-User Portal. (End users with the Portal Administrator User role have the View Expiring Entitlements permission by default.)

See Also

- [Configuring System Settings](#)
- [Administering Alerts](#)
- [About Email Templates](#)

Administering Custom Attributes

Producers can use the commands in the **Administer** menu to view and manage custom attributes, custom host attributes, and custom license attributes.

Table 22-11 -

Topic	Description
About Custom Attributes	Discusses the custom attributes FlexNet Operations supports, how they operate in FlexNet Operations, and some rules particular to their use, including custom attribute data types, required versus optional attributes, and attribute status, and the use of the Copy to Data Warehouse setting.
Managing Custom Attributes	Covers the management of the standard set of custom attributes for entities such as users, accounts, products, entitlements, entitlement lines, download packages, and download files. Topics include <ul style="list-style-type: none"> ● Custom Attribute Settings ● Adding Custom Attributes ● Listing Custom Attributes ● Editing Custom Attributes ● Deleting Custom Attributes
Managing Custom Host Attributes	Covers the management of custom host attributes on custom license technologies. Topics include <ul style="list-style-type: none"> ● Custom Host Attribute Settings ● Adding Custom Host Attributes ● Listing Custom Host Attributes ● Deleting Custom Host Attributes

Table 22-11 •

Topic	Description
Managing Custom License Attributes	<p>Covers the management of custom license attributes defined on a particular technology. Topics describe how to list, create, edit, and delete custom license generator attributes and custom license model attributes. Topics include</p> <ul style="list-style-type: none"> • Custom License Generator Attribute Settings • Custom License Model Attribute Settings • Adding Custom License Attributes • Listing Custom License Attributes • Editing Custom License Attributes • Deleting Custom License Attributes

About Custom Attributes

In the Producer Portal, custom attributes occur in three different groups, and each group is managed from a different page:

Table 22-12 • Custom Attribute Types



Type	Description
Custom attributes or entity-specific custom attributes	<p>Custom attributes that apply to entities like users, accounts, products, and so forth are referred to simply as <i>custom attributes</i>, or <i>entity-specific custom attributes</i> when necessary to distinguish them from the other two groups.</p> <p>Entity-specific custom attributes allow producers to capture extra information and associate it with a user, account, product, entitlement, entitlement line, download package, or file.</p> <p>Producers manage these attributes from the Custom Attributes page.</p>  <p>Note • See Managing Custom Attributes for details.</p>
Custom host attributes	<p>Custom attributes that apply only to host types of custom license technologies are called <i>custom host attributes</i>.</p> <p>Custom host attributes provide a way for producers to capture information that can be used to generate host IDs for custom license technology fulfillments.</p> <p>Producers manage these attributes from the Custom Host Attributes page.</p>  <p>Note • See Managing Custom Host Attributes for details.</p>

Table 22-12 • Custom Attribute Types

Type	Description
Custom license attributes	<p>Custom attributes that apply to license generators or license models of a particular license technology are called <i>custom license attributes</i>. These include custom license generator attributes and custom license model attributes.</p> <ul style="list-style-type: none"> ● License generator attributes provide a way to capture information that can be sent to a custom license generator. ● License model attributes provide a way to capture licensing-related information that might be useful in the entitlement lifecycle or even expressed in license text. <p>Producers manage these attributes from the Custom License Attributes page.</p>



Note • See [Managing Custom License Attributes](#) for details.

Required Attributes and Optional Attributes

When you create a custom attribute, you can define it as required or optional. Generally, you must supply a value for each required custom attribute when creating or editing the entity to which it is associated; the value for optional custom attributes can be left blank.

When considering whether to make a product-specific custom attribute required, for example, be aware that the custom attribute is also required on any existing product the next time that product is edited.

The Required setting can be toggled on and off for entity-specific custom attributes; however, the Required setting is permanent for custom host attributes and custom license attributes after they are created.

For custom license model attributes, when a custom attribute is required, it means that the value of the custom attribute must be set at the specified time in the entitlement lifecycle (license model creation time, entitlement time, or activation time). However, the value of an inactive custom attribute is not asked for at the specified time.



Tip • License model attributes can be defined as optional when they are created, but later can be defined as required when they are enabled on individual license models.

Custom Attribute Status

Entity-specific custom attributes can have a status of either active or inactive. All active custom attributes defined for a particular entity are automatically displayed on Producer Portal and End-User Portal pages on which those entities are created or edited.



Note • Entity-specific custom attributes have a Status setting. Custom host attributes and custom license attributes do not.

Only entity-specific custom attributes can be made inactive. Custom host attributes and license generator attributes can only be active.

Likewise, custom license model attributes can only be active but, unlike other groups of custom attributes, active custom license model attributes are not automatically displayed. When you create a custom license model attribute, you can specify the possible times the attribute’s value can be set (license model creation time, entitlement time, or fulfillment time). A custom license model attribute is not displayed on a license model unless at least one setting is enabled for **When to Request this Attribute Value**.

Inactive custom attributes are hidden in the End-User Portal and Producer Portal pages; however, they remain visible in the Producer Portal under **Administer > Custom Attributes** so that they can be managed. (Click the **Show All** link to view both inactive and active custom attributes.)

A custom attribute is not required to be inactive to be deleted. However, after a custom attribute is in use, with values recorded on related entitlements, users, or other entities, it cannot be deleted from the system.

Custom Attribute Data Types

When you create a custom attribute, you choose the data type for that attribute. (A custom attribute’s data type cannot be changed after it is set.)

Table 22-13 - Custom Attribute Data Types

Data Type	Description
Number	A numeral, for example, 33452. (The value must be an integer.)
Text	<p>An alphanumeric string. If you choose this option, the Producer Portal reveals additional controls for Max. Length and Text Type.</p> <ul style="list-style-type: none"> ● Max Length: Maximum number of characters the text field accepts. The maximum value allowed is 4000 characters. ● Text Type: (Required) Choose from Free Form, Single Select, Multi Valued Text, or Hex. (This choice cannot be changed once set.) <p>Free Form: If you select this option, your custom attribute takes a typed-in alphanumeric string. When the Text Type is Free Form, also choose a Display Type to determine how the text attribute is displayed: Text Field or Text Area.</p> <p>Single Select: If you select this option, your custom attribute takes the value of an item from a drop-down list. When the Text Type is Single Select, also specify Valid Values with the Add Value button. Valid Values determine the list of values a user can choose for this attribute.</p> <p>Multi Valued Text: If you select this option, your custom attribute takes the value of several selected boxes next to items in a specified list. When the Text Type is Multi Valued Text, also specify Valid Values with the Add Value button. Valid Values determine the list of values a user can choose for this attribute.</p> <p>Hex: If you select this option, your custom attribute must meet the following requirements:</p> <ul style="list-style-type: none"> ● Minimum length: 8 characters ● Allowed characters: letters A-F (uppercase and lower case are allowed), numbers 0-9, and the special characters minus (-) and colon (:) ● Maximum length: 4000 characters <p>This is an example for a custom host attribute of type “Hex”: AB-CD-f3-61-73-62.</p>

Table 22-13 • Custom Attribute Data Types

Data Type	Description
Long Text	An alphanumeric string that can be up to 16384 characters. The value can be typed or pasted into the text box. When the attribute's Type is Long Text, also choose a Display Type to determine how the text attribute is displayed: Text Field or Text Area .
Boolean	A pair of options for mutually exclusive choices, such as Yes or No .
Date	A calendar date.

Copying to the Data Warehouse

Most but not all custom attributes can be copied to the data warehouse. The Copy to Data Warehouse setting flags attributes to be included in the reporting transformation process. Those attributes that are copied to the data warehouse are subsequently available for reporting.

Entity-specific custom attributes for Download Packages and Download Files are not transformed to the reporting data warehouse. Also, custom host attributes and custom license generator attributes cannot be copied to the data warehouse. In addition, some custom attributes are also unavailable for reporting due to the data type used for the attribute. For example, custom license model attributes that use a Long Text data type are not allowed to be copied to the data warehouse.

Specifically, the following conditions apply:

- Download Package and File-specific custom attributes cannot be transformed.
- Attributes of all data types except **Long Text** are available for reporting.
- There is a limit of 30 attributes for a single entity and single tenant.
- In Reporter, the maximum length for custom attribute labels and values is 256 characters. Custom attribute labels or values longer than 256 characters will be truncated in the Reporter interface.
- If there are more than 30 attributes, or if the attribute type is set to **Long Text**, the **Copy to Data Warehouse** check box is not visible.
- After it is selected and saved, the option cannot be reverted (the **Copy to Data Warehouse** check box is disabled) nor can the attribute modified. (However, the attribute can be deleted if it has not yet been used, and then re-created as a new attribute.)
- **Multi Valued Text** type is supported, but only allows 255 characters, with all the values separated by a vertical bar (a | pipe character) as a delimiter. For example, if the values are **Address,Email,Phone**, then the value in the data warehouse is transformed into **Address | Email | Phone** format.

See Also

[Managing Custom Attributes](#)

[Managing Custom Host Attributes](#)

[Managing Custom License Attributes](#)

Managing Custom Attributes

Entity-specific custom attributes allow producers to capture extra information and associate it with a user, account, product, entitlement, entitlement line, download package, or file. Producers can define these custom attributes for the following entity types:

- Users
- Accounts
- Products
- Entitlements
- Entitlement Lines
- Download Packages
- Download Files



Note - For information about managing custom host attributes or custom license attributes, see [Managing Custom Host Attributes](#) or [Managing Custom License Attributes](#), respectively.

Table 22-14 -

Topic	Description
Custom Attribute Settings	Provides details about the settings associated with custom attributes.
Adding Custom Attributes	Explains how to add entity-specific custom attributes for users, accounts, products, entitlements, entitlement lines, download packages, and download files.
Listing Custom Attributes	Describes how to show a list of custom attributes.
Editing Custom Attributes	Explains how to edit an existing custom attribute.
Deleting Custom Attributes	Shows how to remove custom attributes.

See Also

[About Custom Attributes](#)

Custom Attribute Settings



Note - Custom host attributes and custom license attributes are managed separately. For details, see [Managing Custom Host Attributes](#) or [Managing Custom License Attributes](#).

Custom attributes have the following settings:

Table 22-15 -

Setting	Description
Name	Type a name to uniquely identify this custom attribute. This name must be unique for the entity type you select next. Custom attribute names can contain upper and lower case alphabet characters, numbers, and underscores.
Entity Type	<p>For Entity Type, choose entity to which you want this attribute added. Choose from</p> <ul style="list-style-type: none"> ● Account ● User ● Product ● Entitlement ● Entitlement Line ● Download Package ● File <p>After the attribute is saved, you cannot change its Entity Type.</p> <p>Note that custom attributes for Download Packages and Files cannot be copied to the data warehouse and, as a result, cannot be made available for reporting. For details, see Copying to the Data Warehouse in About Custom Attributes.</p>
Required?	<p>Choose Yes or No to specify whether this custom attribute is required or optional. If required, a value for this attribute must be set when the entity is created.</p> <p>For more information about required and optional custom attributes, see Required Attributes and Optional Attributes in About Custom Attributes.</p>
Status	Sets the custom attribute to active or inactive status.
Type	<p>The data type of the values the custom attribute accepts. Type cannot be changed once set.</p> <p>Choose from the following:</p> <ul style="list-style-type: none"> ● Number ● Text (requires Max. Length and Text Type settings) ● Long Text (requires Display Type setting) ● Boolean ● Date <p>For details about these data types, see Custom Attribute Data Types in About Custom Attributes.</p>

Table 22-15 •

Setting	Description
Copy to Data Warehouse	If selected, this attribute is included in the data transformation for reporting. Otherwise, the custom attribute is not available for reporting. Note that some data types cannot be copied to the data warehouse and, as a result, cannot be made available for reporting. For details, see Copying to the Data Warehouse in About Custom Attributes .

See Also

[Adding Custom Attributes](#)
[Editing Custom Attributes](#)
[About Custom Attributes](#)

Adding Custom Attributes

Producers can add custom attributes for users, accounts, products, entitlements, entitlement lines, download packages, and download files from the **Custom Attributes** page.



Note • To add custom host attributes or custom license attributes (license model attributes or license generator configuration attributes), see [Adding Custom Host Attributes](#) or [Adding Custom License Attributes](#).



Task

To add a custom attribute

1. In the Producer Portal, click **Administer > Custom Attributes**. This link shows the **Custom Attributes** page.
2. On the **Custom Attributes** page, click **Add Attribute**.
3. On the **Create Custom Attribute** page, specify custom attribute settings.

See [Custom Attribute Settings](#) for more information about attribute properties.
4. Click **Save**.

The Producer Portal adds the custom attribute using the settings you provided, and returns to the **Custom Attributes** page.

See Also

[Editing Custom Attributes](#)
[Managing Custom Attributes](#)

Listing Custom Attributes

The Producer Portal shows previously defined custom attributes on the **Custom Attributes** page.



Note - Custom host attributes and custom license attributes are managed separately. For details, see [Managing Custom Host Attributes](#) or [Managing Custom License Attributes](#).



Task *To list existing custom attributes*

- Click **Administer > Custom Attributes**.

The Producer Portal shows the **Custom Attributes** page. This page lists attributes with the following information:

Table 22-16 - Custom Attributes Information

Field	Description
Name	Name of the custom attribute
Data Type	Type of value the custom attribute accepts: Boolean, Date, Text (free form or single select), Multi-valued text, Long Text, or Date.
Required	Shows whether or not the attribute is required. <ul style="list-style-type: none"> ● true for required attributes ● false for optional attributes See Custom Attribute Settings for more information about required versus optional attributes.
Status	Shows whether the attribute is active or inactive.



Tip - By default, only active custom attributes are shown. To display both active and inactive attributes, click **Show All**.

Click an attribute name to view its details.

Click **Add Attribute** to add a custom attribute.

See Also

- [Adding Custom Attributes](#)
- [Editing Custom Attributes](#)
- [Managing Custom Attributes](#)

Editing Custom Attributes

You can edit existing custom attributes from the **Custom Attributes** page.



Note - Custom host attributes and custom license attributes are managed separately. For details, see [Managing Custom Host Attributes](#) or [Managing Custom License Attributes](#).



Task **To edit a custom attribute**

1. In the Producer Portal, click **Administer > Custom Attributes**. This link shows the **Custom Attributes** page.
2. On the **Custom Attributes** page, click the name of the attribute you want to change.
3. On the **Create Custom Attribute** page, specify custom attribute settings.

Some attribute settings cannot be edited. The ability to edit a setting depends, in part, on its status, whether or not it has been in use, and whether it is required or optional. See [Custom Attribute Settings](#) for more information about attribute properties.

4. Click **Save**.

The Producer Portal saves your changes to the attribute settings.

Adding or Deleting Custom Attribute Values

If the custom attribute that you are editing is of type **Text**, with a text type **Single select** or **Multi-valued text**, you can add or remove values.



Task **To add or remove values from a custom attribute of type Text**

1. Perform steps 1 through 3 as described in the previous procedure, [To edit a custom attribute](#).
2. To add a value:
 - a. Click **Add Value**. This adds a new field to the list of valid values.
 - b. Type the desired value into the new field.
 - c. Click **Save**.
3. To delete a value:
 - a. To remove the last value in the **Valid Values** list, click **Remove Value**.
 - b. To remove any other value, click the field with the value that you want to remove and delete it so that the field is blank.
 - c. Click **Save**.

See Also

[Adding Custom Attributes](#)
[Managing Custom Attributes](#)

Deleting Custom Attributes

Except for download package custom attributes and file custom attributes, most unused custom attributes can be deleted from the **Create Custom Attribute** page.

Download package-specific and file-specific custom attributes cannot be deleted. Attributes defined on users, accounts, products, entitlements, and line items can be deleted only if they have never been assigned a value on any entity.



Note - Custom host attributes and custom license attributes are managed separately. For details, see [Managing Custom Host Attributes](#) or [Managing Custom License Attributes](#).



Task

To delete a custom attribute

1. In the Producer Portal, click **Administer** > **Custom Attributes** to show a list of custom attributes.
2. On the **Custom Attributes** page, click the name of the custom attribute you want to delete. The Producer Portal shows the attribute's **Create Custom Attribute** page.
3. On the **Create Custom Attribute** page, click **Delete**. The Producer Portal prompts you to confirm the deletion.
4. Click **OK** to confirm the deletion of the selected custom attributes.

The Producer Portal deletes the selected attributes and refreshes the custom attributes list.

See Also

[Editing Custom Attributes](#)
[About Custom Attributes](#)
[Managing Custom Attributes](#)

Managing Custom Host Attributes

You can manage your custom host attributes from the Custom Host Attributes page.

Custom host attributes apply only to host types of custom license technologies and provide a way for producers to capture information that can be used to generate host IDs for custom license technology fulfillments.

Licenses are usually bound to either a node or a host. Defining a host attribute allows you to create a host ID for a host and to use the host as the criteria for capabilities like batch rehosts, searching and sorting on hosts, and listing all fulfillments for a given host.

If custom host attributes are defined for a host type, FlexNet Operations displays them to users when they create a host of that type.

The topics below discuss how to add, list, and delete custom host attributes.



Note - For information about entity-specific custom attributes or custom license attributes, see [Managing Custom Attributes](#) or [Managing Custom License Attributes](#), respectively.

Table 22-17 -

Topic	Description
Custom Host Attribute Settings	Provides details about the settings associated with custom host attributes.
Adding Custom Host Attributes	Explains how to add a custom host attribute and specify its name, license technology, host type, and data type.
Listing Custom Host Attributes	Describes how to show a list of custom host attributes.
Deleting Custom Host Attributes	Shows how to remove custom host attributes.

See Also

[About Custom Attributes](#)

Custom Host Attribute Settings

Custom host attributes have the following settings:

Table 22-18 -

Setting	Description
Name	Type a name to identify this custom host attribute.
License Technology	The type of license technology with which the attribute is to be used.
Host Type	Select a host type from the list provided.
Required?	Choose Yes or No to specify whether this custom attribute is required or optional. If required, a value for this attribute must be set when the entity is created. For more information about required and optional custom attributes, see Required Attributes and Optional Attributes in About Custom Attributes .

Table 22-18 •

Setting	Description
Type	<p>The data type of the values the custom attribute accepts. Type cannot be changed once set.</p> <p>Choose from the following:</p> <ul style="list-style-type: none"> ● Number ● Text (requires Max. Length and Text Type settings) ● Long Text (requires Display Type setting) ● Boolean ● Date <p>For details about these data types, see Custom Attribute Data Types in About Custom Attributes.</p>

See Also

[Adding Custom Host Attributes](#)
[About Custom Attributes](#)

Adding Custom Host Attributes

Follow the instructions, below, to create a custom host attribute.



Task

To add a custom host attribute

1. In the Producer Portal, click **Administer > Custom Host Attributes**. The Producer Portal opens the Create Custom Host Attribute page.
2. On the Create Custom Host Attribute page, provide a name for the attribute and specify values for its other settings. See [Custom Host Attribute Settings](#) for setting details.
3. Complete the attribute creation process by clicking **Save** or **Add New**:
 - Click **Save** to save the attribute and remain on the current page.
 - Click **Add New** to save the current attribute and begin creating another custom host attribute.

The custom host attributes you create here are typically assigned values for a given host when that host is created.

See Also

[Deleting Custom Host Attributes](#)
[Managing Custom Host Attributes](#)

Listing Custom Host Attributes

The Producer Portal shows all previously defined custom host attributes on the Custom Host Attributes page.



Task **To list existing custom host attributes**

- Click **Administer > Custom Host Attributes**.

The Producer Portal shows the Custom Host Attributes page. This page lists attributes with the following information:

Table 22-19 • Custom Attributes Information

Field	Description
Name	Name of the custom attribute.
Type	Type of value the custom attribute accepts: Boolean, Date, Text (free form or single select), Multi-valued text, Long Text, or Date.
License Technology	Name of the license technology to which the attribute belongs.
Host Type	Type of host for the custom attribute.

Click an attribute name to view its details.

Click **Create** to add a custom host attribute.

Select the box next to an attribute and click **Delete** to delete it. Custom host attributes cannot be deleted if the associated license technology is in Deployed status.

See Also

- [Deleting Custom Host Attributes](#)
- [Managing Custom Host Attributes](#)

Deleting Custom Host Attributes

Custom host attributes can be deleted from the Custom Host Attributes page.

Custom attributes cannot be deleted if the associated license technology is deployed. When a custom attribute is deleted from a draft license technology, all references to this attribute are deleted from the corresponding generator configuration or license model.



Task **To delete custom host attributes**

1. On the Custom Host Attributes page, select the check box of the custom host attributes you want to delete and then click **Delete**. The Producer Portal prompts you to confirm the deletion.
2. Click **OK** to confirm the deletion of the selected custom attributes.

The Producer Portal deletes the selected attributes and refreshes the custom host attributes list.

See Also

- [Managing Custom Host Attributes](#)

Managing Custom License Attributes

You can manage your custom license generator attributes and custom license model attributes from the **Custom License Attributes** page.

Custom license attributes include custom license generator attributes and custom license model attributes. License generator attributes provide a way to capture information that can be sent to a custom license generator. License model attributes provide a way to capture licensing-related information that might be useful in the entitlement lifecycle or even expressed in license text.

The topics below discuss how to add, list, edit, and delete custom license generator attributes and custom license model attributes.



Note ▪ For information about entity-specific custom attributes or custom host attributes, see [Managing Custom Attributes](#) or [Managing Custom Host Attributes](#), respectively.

Table 22-20 ▪

Topic	Description
Custom License Generator Attribute Settings	Provides details about the settings associated with custom license generator attributes.
Custom License Model Attribute Settings	Provides details about the settings associated with custom license model attributes.
Adding Custom License Attributes	Explains how to add custom license model and license generator configuration attributes. <ul style="list-style-type: none"> For custom license generator configuration attributes, these instructions cover specifying a numeric, text, boolean, or date attribute for a license generator configuration associated with a license technology. For custom license model attributes, these instructions cover creating attributes for custom license models or creating custom attributes for FlexNet Publisher Licensing Toolkit models
Listing Custom License Attributes	Describes how to show a list of custom license attributes.
Editing Custom License Attributes	Explains how to edit existing custom license generator attributes and custom license model attributes.
Deleting Custom License Attributes	Shows how to remove custom license attributes.

See Also

- [About Custom Attributes](#)
- [Administering Custom Attributes](#)
- [Administering License Technologies](#)
- [Administering License Models](#)

Custom License Generator Attribute Settings

Custom license generator attributes have the following settings:

Table 22-21 -

Setting	Description
Name	A name to uniquely identify this custom license generator attribute. This name must be unique within a given license technology.
License Technology	License technology of which the attribute is a part. Choose from the drop-down list.
Required?	Is this a required or optional attribute for license generation? If required, this attribute can only be created for a license technology in the draft state.
Type	<p>The data type of the values the custom attribute accepts. Type cannot be changed after it is set.</p> <p>Choose from the following:</p> <ul style="list-style-type: none">● Number● Text (requires Max. Length and Text Type settings)● Long Text (requires Display Type setting)● Boolean● Date <p>For details about these data types, see Custom Attribute Data Types in About Custom Attributes.</p>

See Also

- [Adding Custom License Attributes](#)
- [Editing Custom License Attributes](#)
- [About Custom Attributes](#)

Custom License Model Attribute Settings

Custom license model attributes have the following settings:

Table 22-22 -

Setting	Description
Name	A name to uniquely identify this custom license model attribute. This name must be unique within a given license technology.
License Technology	License technology of which the attribute is a part. Choose from the drop-down list. If you choose FlexNet Licensing from this list, you are setting custom attributes on its license models.
When to Request this Attribute Value	<p>The events during which it is possible for to specify the values of this attribute:</p> <ul style="list-style-type: none"> ● License Model Creation: when creating a license model that enables this attribute ● Entitlement: when creating entitlements with license models that enable this attribute ● Fulfillment: when activating licenses with license models that enable this attribute <p>The selected events, above, define the events when the values of this attribute may be specified on some license model of the selected license technology. When the current license model attribute is enabled on a particular license model, one event from the set of possible events must be selected. For more information, see Setting Up Custom License Model Attributes.</p>
Required?	Is this a required or optional attribute for license generation? If required, this attribute can only be created for a license technology in the draft state.
Type	<p>The data type of the values the custom attribute accepts. Type cannot be changed after it is set.</p> <p>Choose from the following:</p> <ul style="list-style-type: none"> ● Number ● Text (requires Max. Length and Text Type settings) ● Long Text (requires Display Type setting) ● Boolean ● Date <p>For details about these data types, see Custom Attribute Data Types in About Custom Attributes.</p>

Table 22-22 •

Setting	Description
Copy to Data Warehouse	If selected, this attribute is included in the data transformation for reporting. Otherwise, the custom attribute is not available for reporting. Note that some data types cannot be copied to the data warehouse and, as a result, cannot be made available for reporting. For details, see Copying to the Data Warehouse in About Custom Attributes .

See Also

- [Adding Custom License Attributes](#)
- [Editing Custom License Attributes](#)
- [About Custom Attributes](#)

Adding Custom License Attributes

Although you can create custom license generator configuration attributes and custom license model attributes as part of the license technology creation wizard, both types of custom attributes can also be created directly from the **Custom License Attributes** page.

This topic explains how to create custom license generator configuration attributes and custom license model attributes:

- For custom license generator configuration attributes, these instructions cover specifying a numeric, text, boolean, or date attribute for a license generator configuration associated with a license technology. See [Adding Custom License Generator Attributes](#), below.
- For custom license model attributes, these instructions cover creating attributes for custom license models or setting custom attributes for FlexNet Licensing models. See [Adding Custom License Model Attributes](#), below.

Adding Custom License Generator Attributes

Custom license generator attributes can be created as part of the license technology creation wizard or they can be created independently of that wizard. These instructions start from the **Create a License Generator Attribute** page.

In the license technology creation wizard, the **Create a License Generator Attribute** page is step 2. To open the **Create a License Generator Attribute** page independently of that wizard, click **Administer > Custom License Attributes**. Then, click **Add a License Generator Attribute**.



Note • When creating a license technology, if you implement your license generator class so that it references the license generator executable, you can skip this step.

You can create a license generator attribute for custom license technologies in the draft state. You cannot create a license generator attribute for FlexNet Licensing.

**Task** *To add a custom license generator attribute*

1. On the **Create a License Generator Attribute** page, provide a name for the attribute and specify values for its other settings. See [Custom License Generator Attribute Settings](#) for setting details.
2. Complete the attribute creation process by clicking **Save**, **Add New**, **Reset**, or **Next**:
 - Click **Save** to save the attribute and remain on the current page.
 - Click **Add New** to save the current attribute and begin creating another custom license generator attribute.
 - Click **Reset** to clear the current form and start again.
 - Click **Next** to save the license technology and move to the Create License Generator Configuration page.

The custom license generator attributes you create here are typically configured for a given license generator when that license generator is created. These license generator configurations are set up in the Create a License Technology wizard. See [Creating a License Generator Configuration](#) for more information.

Adding Custom License Model Attributes

Custom license model attributes can be created as part of the license technology creation wizard or they can be created independently of that wizard. These instructions start from the **Create a License Model Attribute** page.

In the license technology creation wizard, the **Create a License Model Attribute** page is step 4. To open the **Create a License Model Attribute** page independently of that wizard, click **Administer > Custom License Attributes**. Then, click **Add a License Model Attribute**.

**Task** *To add a custom license model attribute*

1. On the **Create a License Model Attribute** page, provide a name for the attribute and specify values for its other settings. See [Custom License Model Attribute Settings](#) for setting details.
2. Complete the attribute creation process by clicking **Save**, **Add New**, or **Complete**:
 - Click **Save** to save the attribute and remain on the current page.
 - Click **Add New** to save the current attribute and begin creating another custom license model attribute.
 - Click **Complete** to save the license technology and return to the **License Technologies** page.

The custom license model attributes you create here are typically configured for a given license model when the license model is created. The license model creation wizard includes a step in which you can set up how the available custom license model attributes are to be used (or not) for the current license model. See [Setting Up Custom License Model Attributes](#) for instructions.



Note ▪ If you create an attribute for a custom technology called “SERIAL_NUMBER,” its label, by default, is displayed as “Serial Number.” This is because SERIAL_NUMBER is a FlexNet Licensing attribute for which resources are already defined. If you change the label for the custom SERIAL_NUMBER attribute, its FlexNet Licensing display label also changes.

See Also

- [Managing Custom License Attributes](#)
- [Administering License Technologies](#)
- [Administering License Models](#)

Listing Custom License Attributes

The Producer Portal shows all previously defined custom license generator attributes and custom license model attributes on the **Custom License Attributes** page.



Task *To list existing custom license attributes*

- Click **Administer** > **Custom License Attributes**.

The Producer Portal shows the **Custom License Attributes** page. This page lists attributes with the following information:

Table 22-23 - Custom Attributes Information

Field	Description
Name	Name of the custom attribute.
Type	Type of value the custom attribute accepts: Boolean, Date, Text (free form or single select), Multi-valued text, or Long Text.
Belongs To	Whether the attribute is associated with license models or license generator configurations.
License Technology	Name of the license technology to which the attribute belongs.

From this page, you can add a license generator attribute or a license model attribute, edit an existing attribute, or delete existing attributes. Producers can also export the attributes the license attributes that appear in the list.

Click an attribute name to view its details.

- Click **Add a License Model Attribute** to create a custom license model attribute.
- Click **Add a License Generator Attribute** to create a license generator configuration attribute.

See [Adding Custom License Attributes](#) for instructions.



Tip - If you have many custom license attributes, note that the list of attributes is paginated. Use the page controls to view more attributes. Use the search features on the **Custom License Attributes** page to narrow the list.

See Also

- [Editing Custom License Attributes](#)
- [Deleting Custom License Attributes](#)
- [Managing Custom License Attributes](#)

Editing Custom License Attributes

Both custom license generator attributes and custom license model attributes can be edited from the **Custom License Attributes** page. (Not all settings for these custom license attributes are editable.)



Task

To edit a custom license attribute

1. On the **Custom License Attributes** page, click the name of the custom attribute you want to edit. The Producer Portal opens the **Create a License Generator Attribute** or the **Create a License Model Attribute** page, depending on the type of attribute you choose.
2. Edit the settings for the current attribute. For details about these settings, see [Custom License Generator Attribute Settings](#) or [Custom License Model Attribute Settings](#).
3. Click **Save**.

The Producer Portal saves your changes to the attribute settings.

See Also

[Adding Custom License Attributes](#)
[Deleting Custom License Attributes](#)
[Managing Custom License Attributes](#)

Deleting Custom License Attributes

Both custom license generator attributes and custom license model attributes can be deleted from the **Custom License Attributes** page.

Custom license attributes cannot be deleted if the associated license technology is deployed. When a custom license attribute is deleted from a draft license technology, all references to this attribute are deleted from the corresponding generator configuration or license model.



Task

To delete custom license attributes

1. On the **Custom License Attributes** page, select the check box of the custom attributes you want to delete and then click **Delete**. The Producer Portal prompts you to confirm the deletion.
2. Click **OK** to confirm the deletion of the selected custom attributes.

The Producer Portal deletes the selected attributes and refreshes the custom license attributes list.

See Also

[Editing Custom License Attributes](#)
[Managing Custom License Attributes](#)

Importing and Exporting Entities

You can import and export entities from the FlexNet Operations database into other Operations databases. This enables you to migrate data between different FlexNet Operations installations. In addition, data export can be helpful when troubleshooting issues. For example, problematic entities can be exported to a file and then sent to tech support for review.

Imports can be either contained in packages or Unicode text. Packages are .jar files that contain an XML metafile to describe the contents of the package and the order in which the content files should be loaded, and content XML files for the entities. Unicode .txt files are saved from Data Import Templates in .xlt format. Blank Data Import Templates can be downloaded from the Data Import Templates tab, as described in [Using Data Import Templates](#).

Exports can be in either .jar or Data Import Template (.xlt) format. With a Data Import Template, modification of the data is simplified with tools designed to ensure compatibility with the FlexNet Operations database. See [Using Data Import Templates](#) for more information.

Information about importing and exporting entities is described in the following sections:

- [Import/Export Package Structure](#)
- [Importing and Exporting Entities Overview](#)
- [System Configuration](#)
- [Exporting Entities](#)
- [Importing Entities](#)
- [Using Data Import Templates](#)
- [Import/Export Job Status](#)

Import/Export Package Structure

During the import/export process, FlexNet Operations works with an export-import package, which is a .jar file containing the following:

- An XML metafile to describe the contents of the package and the order in which the files should be loaded.



Note - For more information, see [XML Metafile Structure](#).

- A set of content XML files for the entities that are exported. Each file contains entities of one type only. For example, products are in one XML file, and license models are in another XML file.



Important - FlexNet Operations does not support the importing or exporting of test entities, such as test entitlements.

See Also

[XML Metafile Structure](#)
[Importing and Exporting Entities Overview](#)
[System Configuration](#)
[Exporting Entities](#)
[Importing Entities](#)
[Using Data Import Templates](#)
[Import/Export Job Status](#)

XML Metafile Structure

If a package is built by hand, this metafile must be constructed and packaged into a .jar file with the content XML files.

The type tag in XML specifies the type of entity being imported.

A sample metadata file is shown here:

```

<fileMetaInfo version="8.3">
  <statusInfo> <!--This tag is optional and it is not used during import-->
    <message>Exported from FNO 8.3 installed on host blind</message>
    <timestamp>03/16/2007 14:30:35</timestamp>
  </statusInfo>
  <fileInfo>
    <file order="1" type="LIC_TECH">1</file>
    <file order="2" type="MODEL">1</file>
    <file order="3" type="FEATURE">1</file>
    <file order="4" type="PRODUCT">1</file>
    <file order="5" type="ENTITLEMENT">5</file>
  </fileInfo>
  <fileDetails><!-- This tag lists the location of each file and the order it should be loaded -->
  <fileSet type="LICTECH">
    <fileName order="1">lictech_1.xml</fileName>
  </fileSet>
  <fileSet type="MODEL">
    <fileName order="1">licmodel_1.xml</fileName>
  </fileSet>
  <fileSet type="FEATURE">
    <fileName order="1">feature_1.xml</fileName>
  </fileSet>
  <fileSet type="PRODUCT">
    <fileName order="1">product_1.xml</fileName>
  </fileSet>
  <fileSet type="ENTITLEMENT">
    <fileName order="1">entitlement_1.xml</fileName>
    <fileName order="2">entitlement_2.xml</fileName>
    <fileName order="3">entitlement_3.xml</fileName>
    <fileName order="4">entitlement_4.xml</fileName>
    <fileName order="5">entitlement_5.xml</fileName>
  </fileSet>
  </fileDetails>
</fileMetaInfo>

```

File Order

The order in which entities are loaded is important. Before an entity is loaded, all of its dependencies must exist in the system. There are two points to consider while determining the file order in the metafile:

- Different entity types: For example, before an entitlement is loaded, the product and license model the entitlement refers to must exist in the system. So, the product XML files must be loaded before loading the entitlement XML files.
- Same entity types: If there is a parent-child relationship between the same entity types, the parent must be loaded before the child is loaded. For example, if an entitlement line item is defined as an upgrade of another line item. The parent line item must be loaded before the upgraded line item is loaded.

Each content XML file must be of a reasonable size to ensure that the I/O processes proceed smoothly.

Content XML Files

In general, all constants in the content XML files are enumerated types which are defined in the corresponding .xsd file.

In general, if the user wants to update even one attribute, such as state, the entire XML file must be submitted along with all the collections and references.

For example, if the user wants to import a product, then the entire product definition along with the features, bundles, license models, parts, and associated parameters, has to be provided in the XML file. If the product already exists in the system, the user is given a choice to either update the record or report an error during the import process. If the user selects to update the record, then the entire product definition is replaced by the details in the XML imported. This means that the existing features, bundles, license models, parts in the product are replaced by the new collections mentioned in the imported XML.

Common specifications for each content XML include:

- Date values must be entered in yyyy-mm-dd format.
- Time Zone must be entered in a format like -7:00, which indicates GMT -7 hours.
- Locales must be entered as en or en_US. A locale's language is specified by the ISO 639 standard and the locale's country code is specified by the ISO 3166 standard. If the locale entered does not conform to these standards, then a default value of en is stored.

See Also

[Import/Export Package Structure](#)

Importing and Exporting Entities Overview

When importing or exporting, you can select a single entity, specific entities, or all entities of a certain type. For example, you can export a single product, selected products, or all products. If you export an entity, you can also choose to export its dependent entities (dependencies). For example, if you export an entitlement, and you select its dependencies, FlexNet Operations can also export the entitlement's dependent product, features and other associated entities.

Permission to view an entity also includes permission to export it.



Important - Only the .jar package mechanism supports importing and exporting of feature bundles.

Importable and exportable entities include:

- License Technologies, License Models and License Generator Configurations
- Publishers and publisher identities
- Custom Attributes
- Features and feature bundles
- Part Numbers
- Transaction Keys
- Products and Suites
- Product relationships to license models, features, feature bundles, license models, part numbers and other products
- Simple entitlements and line items
- Bulk entitlements and Web register keys.
- Fulfillments, including fulfillment vendor names. (Import limitations apply. See [Fulfillment Import Limitations](#).)
- Consolidated licenses
- All business objects in FlexNet Operations (including account units, license technologies, products, suites, features, feature bundles, license models, entitlements, and fulfillment records).



Important - You cannot import or export test entities, such as test entitlements.



Note - Administrative entities like roles, and records like history and audit trails cannot be exported or imported.

See Also

[System Configuration](#)
[Exporting Entities](#)
[Importing Entities](#)
[Using Data Import Templates](#)
[Import/Export Job Status](#)

System Configuration

Imports and exports are processed as background jobs. Before importing or exporting, configure an alert for the background queue.



Task **To configure alerts for background queue processing**

1. Click **Administer > Configure Alerts**.
2. Under Export and Import Background Jobs, click **Configure**.
3. On the Set Alert Handlers page, set your alert handlers.
4. If desired, set a value for the interval at which FlexNet Operations checks for background jobs. The default is 5 seconds.
5. Click **Save**.
6. Subscribe to the alert as usual.

See Also

[Importing and Exporting Entities Overview](#)
[Exporting Entities](#)
[Importing Entities](#)
[Using Data Import Templates](#)
[Import/Export Job Status](#)

Exporting Entities

The following tasks explain how to export entities.

- [Exporting an Entity or Set of Entities as a JAR File](#)
- [Exporting the Entire FlexNet Operations Database](#)
- [Exporting a Set of Entities as a Data Import Template File](#)

Exporting an Entity or Set of Entities as a JAR File

To export an entity or a set of entities from FlexNet Operations as a JAR file, perform the following steps.



Task **To export an entity or set of entities from FlexNet Operations as JAR file**

1. On the landing page for the entity, do one of the following:
 - a. To export selected entities, select one or more entities, then click **Export > Selected Items** or **Selected Items With Their Dependencies**.
 - b. To export all entities in the list, click **Export > All Items** or **All Items With Their Dependencies**.
2. The selected entities are exported to a jar file. If you chose to include dependencies, the dependencies are included.

Exporting the Entire FlexNet Operations Database

To export the entire FlexNet Operations database, perform the following steps.



Task **To export the entire FlexNet Operations database**

1. Click **Administer > Export Data Objects**.
2. On the Export Business Objects page, click **Export**.
3. Click **Yes** to confirm export.
4. All exportable business objects in FlexNet Operations are exported to a .jar file. Your job is assigned a request number, and an alert is sent when processing is completed. You can check the job status on the Status page. See [Import/Export Job Status](#) for more information.

Exporting a Set of Entities as a Data Import Template File

To export the a set of entities as a Data Import Template file, perform the following steps.



Task **To export a set of entities from FlexNet Operations as Data Import Template file**

1. On the landing page for the entity, click **Export > Data Import Template**.



Note - For Users and Accounts, click **Export > Data Import Template** from any tab. All user or all account data is exported into the template file. For Download Packages and Files, go to the **Products > Search Download Packages** or **Search Files** page and click the **Search** button to access the Search Results page, then click **Export > Data Import Template**. All Download Packages or all Files are downloaded into the template file, regardless of the filtering on the search page.

2. A message similar to the following appears:

Request 3137 to export all Products as data import template successfully submitted. An alert will be sent after the request is processed.
3. Go to **Administer > Import/Export Status**.
4. When the request has completed, select the check box next to its **Job ID** and click the **Download exported file** button. The selected entities are exported to a Data Import Template (.xlt) file. Data for all the tabs in the template are included in the downloaded file.



Note - The Products download does not include the Create/Update Product line tab data available in the blank Data Import Template. Save each tab of the downloaded .xlt file as a separate Unicode text file for uploading to another instance of FlexNet Operations. The Create-Update Features data is included as a separate tab in the PackageProducts.xlt export as well as a standalone tab in the FeatureExport.xlt export.

See Also

[Importing and Exporting Entities Overview](#)
[System Configuration](#)
[Importing Entities](#)
[Using Data Import Templates](#)
[Import/Export Job Status](#)

Importing Entities

To import a set of entities into FlexNet Operations, perform the following steps.



Task

To import a set of entities into FlexNet Operations

1. Click **Administer > Import Data Objects**.
2. In the **Import Settings** tab, under **Upload Type**, select either **Unicode of Data Import Template** or **Jar file**. If you select **Unicode of Data Import Template**, skip to [Step 6](#), otherwise go to [Step 3](#).
3. If you are importing a JAR file larger than 2 MB in size, select the **Run job in background?** check box.
 - If **Run job in background?** is selected (default setting), FlexNet Operations processes the import job asynchronously. FlexNet Operations submits the job for processing and assigns the job a record number. (You can check the status of the import job on the status page. See [Import/Export Job Status](#) for more information.)
 - If **Run job in background?** is not selected, FlexNet Operations processes the import immediately.See [Configuring Alert Behavior](#) for more information on configuring background jobs.
4. For Error handling, select one of the following options:
 - **Continue with errors**—The import process continues even if errors are encountered.
 - **Stop import job**—The import process stops upon encountering an error.
5. For Duplicate record handling, select one of the following options:
 - **Update record**—If the entity already exists in the database, the record is updated with the information in the import file.
 - **Skip and Generate Error**—If the entity already exists in the database, it is not updated and an error message is generated.
6. For File Name, click **Choose File**. Browse to the Unicode .txt or .jar file containing the data you want to import.



Note - When importing a large number of Web Register Keys, it is recommended that you limit each job to a maximum of 1,000 keys to optimize performance. If necessary, split the task into multiple jobs to stay within the recommended limit.

7. Click **Import**. The file is imported into FlexNet Operations.



Note - Only suites in Draft mode can be updated on import.

Import Order

If copying data from one instance of FlexNet Operations to another, dependencies such as Transaction Keys, License Technologies, and License Models must be imported first. Use the **Selected Items with their Dependencies** (if available) or **Selected items** to download JAR files from their respective entity pages and upload them before uploading a Product Packing or Entitlement Management Unicode text file.



Note ▪ See [Exporting an Entity or Set of Entities as a JAR File](#) and [Downloading a Data Import Template](#) for more information.

The following lists the order each type of entity should be uploaded.

Table 22-24 ▪ Upload Order of Entities

Entity Type	Upload Order
Dependencies	Dependencies must be uploaded in the following order: <ol style="list-style-type: none"> 1. License Generator 2. License Technology 3. License Model 4. Hosts 5. Accounts 6. Users 7. Product Lines 8. Custom Attributes 9. Custom Host Attributes 10. Custom License Attributes
Product Entities	Product entities must be uploaded in the following order: <ol style="list-style-type: none"> 1. Features 2. Products 3. Maintenance Products 4. Part Number or Product Relationship
Entitlement Entities	Entitlement entities must be uploaded in the following order: <ol style="list-style-type: none"> 1. Simple and Bulk Entitlements 2. Maintenance Line Item 3. Web Reg Keys



Note - *Not all entities have an export option. For any entity page that does not include an Export option, data must be manually entered into the new instance of FlexNet Operations*

Fulfillment Import Limitations

If updates on import are allowed, the following limitations apply:

- Existing *on-hold* fulfillments can be updated only to *active* by import.
- Existing *active* fulfillments can be updated only to *obsolete* by import.
- Existing *obsolete* fulfillments cannot be updated by import.

See Also

[Importing and Exporting Entities Overview](#)
[System Configuration](#)
[Exporting Entities](#)
[Using Data Import Templates](#)
[Import/Export Job Status](#)

Using Data Import Templates

Data Import Templates enable you to do a batch import of data into FlexNet Operations. You can add new entities or modify existing ones. This approach may be preferred if there is a lot of data to be added or modified.



Note - *Only suites in Draft mode can be updated on import.*

Templates for entitlements, accounts and users, and products can be downloaded and populated with data that can be imported into a FlexNet Operations database using the import function (see the task described under [Importing Entities](#)). Features of the templates include

- Color coded column headers based on transaction type, account, user, entitlement, line item, product and feature.
- Column headings of required fields for a transaction are in bold.
- Column heading comments containing information about the data expected for the column and any other column dependencies associated with this column.

Any Custom Attribute fields you have configured will be included in the templates. Unique Custom Attributes and License Model Attributes and Policies utilize the following heading name conventions:

- License Model Attribute: LM[<LicenseModelName>|<AttributeName>]
- License Model Policy Attribute: PO[<LicenseModelName>|<AttributeName>|<PolicyAbbreviation>]
- Custom Attributes: CA[<Entity>|<AttributeName>] where Entity = USER, PROD, ENT, or LINE

Downloading a Data Import Template

To download a Data Import Template, perform the following steps.



Task **To download a Data Import Template**

1. Click **Administer > Import Data Objects**.
2. Click the **Data Import Templates** tab.
3. Click the appropriate Download link for one of the following template types:
 - **Product Packaging Template**—Products, features, and other data associated with product packaging.
 - **Entitlement Management Template**—Entitlements, maintenance line items, bulk entitlements, web register keys and other data associated with entitlements.
 - **Download Packaging Template**—Download packages, files and other data associated with download packages.
 - **Account and User Template**—Accounts and users.
 - **Updates Template**—Updates.
4. Save the .xlt file

Editing and Saving a Data Import Template

To edit and save a Data Import Template, perform the following steps.



Task **Editing and saving a Data Import Template**

1. Open the .xlt file in Excel (or another compatible spreadsheet application).
2. Fill in the spreadsheet columns as appropriate.



Important - CreateUpdate transactions can blank existing data. If you upload a file containing transactions of these types, FlexNet Operations assumes any columns you include contain the desired value. If a column contains no values, then when FlexNet Operations updates the records, any existing data is lost. If you do not want to provide values in a column, then remove the column from the spreadsheet.

When working with spreadsheets, follow these guidelines:

- Do not change heading names. If they are changed, the transactions are processed but values in the columns whose names have been changed are not assigned to the corresponding fields in the database.
- Only columns with a heading in bold text are required.
- Hover over the heading to see comments on how to populate the field and to determine if there is a dependency requiring other columns to be completed. If there is more text in the comment that can be viewed by hovering over the heading, right click the heading and select **Edit Comment** to open the comment box and use the arrow keys to scroll up or down.
- For Users, see [Time Zone Settings](#) for correct construct of the time zone attribute.
- For Accounts, self-registered accounts cannot be imported into the Producer Portal. Also, the following restrictions apply to default accounts:

- MYORG: Only the account name can be changed. No other updates are permitted and this account cannot be deleted.
 - PORTAL_ORG_UNIT: This account cannot be updated or deleted.
 - UNKNOWN_ORG_UNIT: This account cannot be updated or deleted.
 - Products and Entitlements contain multi-valued attributes such as features and line items. To have multiple features and line items, they cannot be set in a single row but must be added on separate rows repeating any identifier fields for the product or entitlement. Data that is only needed once for the transaction type is taken from the first row and data that can have multiple values is aggregated from the succeeding rows, which is why you cannot change a field using multiple rows of data for the same product or entitlement in the same Data Import Template file.
 - If you want to change a field for products or entitlements, upload it in a separate Data Import Template file.
 - When importing a large number of Web Register Keys, it is recommended that you limit each job to a maximum of 1000 keys to optimize performance. If necessary, split the task into multiple jobs to stay within the recommended limit.
3. After all changes are made, save the file as a Unicode .txt file.

See Also

- [Time Zone Settings](#)
- [Importing and Exporting Entities Overview](#)
- [System Configuration](#)
- [Exporting Entities](#)
- [Using Data Import Templates](#)
- [Import/Export Job Status](#)

Time Zone Settings

One of the attributes that can be set for creating/updating users is a user’s time zone. Determine the correct time zone configuration from the following table.

Table 22-25 ▪ Time Zone Settings

Time Zone	Setting
Midway Island, Samoa	GMT-11.0DST0
Hawaii	GMT-10.0DST0
Hawaii-Aleutian Daylight Time	GMT-10.0DST60
Marquesas Time	GMT-9.5DST0
Gambier Time	GMT-9.0DST0
Alaska Daylight Time	GMT-9,0DST60
Pitcairn Standard Time	GMT-8.0DST0

Table 22-25 ▪ (cont.)Time Zone Settings (cont.)

Time Zone	Setting
Pacific Time	GMT-8.0DST60
Mountain Standard Time	GMT-7.0DST0
Mountain Daylight Time	GMT-7.0DST60
Central America	GMT-6.0DST0
Central Time	GMT-6.0DST60
Ecuador, Columbia, Peru Time	GMT-5.0DST0
Eastern Time	GMT-5.0DST60
Venezuela Time	GMT-4.5DST0
Guyana, Bolivia Time	GMT-4.0DST0
Atlantic Time (Canada)	GMT-4.0DST60
Newfoundland Daylight Time	GMT-3.5DST60
Argentine Time, French Guiana, Uruguay Time	GMT-3.0DST0
Brazil, Greenland Time	GMT-3.0DST60
Mid-Atlantic	GMT-2.0DST0
Cape Verde Time	GMT-1.0DST0
Azores Time	GMT-1.0DST60
Coordinated Universal Time	GMT0.0.DST0
British Time	GMT0.0DST60
Antarctica/Troll	GMT0.0DST120
Western Africa Time	GMT1.0DST0
Western European Time	GMT1.0DST60
Central African, South African Standard Time	GMT2.0DST0
Israel Daylight Time, Eastern European Time	GMT2.0DST60
Arabia Time	GMT3.0DST0

Table 22-25 ▪ (cont.)Time Zone Settings (cont.)

Time Zone	Setting
Iran Daylight Time	GMT3.5DST60
Mauritius, Seychelles Time	GMT4.0DST0
Georgia, Armenia, Azerbaijan Time	GMT4.0DST60
Afghanistan Time	GMT4.5DST0
Uzbekistan, Turkmenistan, Tajikistan, Pakistan, Maldives Time	GMT5.0DST0
India Standard Time	GMT5.5DST0
Nepal Time	GMT5.75DST0
Bangladesh, Sri Lanka, Bhutan Time	GMT6.0DST0
Myanmar Time, Cocos Island Time	GMT6.5DST0
Indochina, Christmas Island Time	GMT7.0DST0
Krasnoyarsk Time	GMT7.0DST60
China, Malaysia, Hong Kong, Singapore, Philippines, Western Australia Time	GMT8,0DST0
Irkutsk Summer Time	GMT8.0DST60
Pyongyang Time	GMT8.5DST0
Central Western Standard Time (Australia)	GMT8.75DST0
Japan, Korea Standard Time	GMT9.0DST0
Australia Northern Territory Time	GMT9.5DST0
South Australia Time	GMT9.5DST60
Papua New Guinea	GMT10.0DST0
Tasmania, Victoria, New South Wales Time	GMT10.0DST60
Load Howe Summer Time	GMT10.5DST30
New Caledonia, Vanuatu, Solomon Island Time	GMT11.0DST0
Fiji, Marshall Islands Time	GMT12.0DST0

Table 22-25 ▪ (cont.)Time Zone Settings (cont.)

Time Zone	Setting
New Zealand Time	GMT12.0DST60
Chatham Daylight Time	GMT12.75DST60
Phoenix Island Time, Tonga Time	GMT13.0DST0
Enderbury, Fakaofu, Tongatapu Island Time	GMT13.0DST60
Line Island Time	GMT14DST0

See Also

[Using Data Import Templates](#)

Import/Export Job Status

You can view the status of data import or export operations executed in the background on the **Import/Export Status** page.



Note ▪ You must first configure the Export and Import Background Jobs alert on the **Configure Alerts** page. The default setting for this alert is a Detection and Notification interval of 30 days with a status of inactive. See [To configure alerts for background queue processing](#) for more information.



Task *To check the status of an import or export job*

1. Click **Administer > Import/Export Status**.
2. The **Export & Import Job Status** page opens with a table that includes the following:

Column	Description
Job ID	Auto generated unique identifier.
Request type	Import or Export.
Export type	The type of business object being exported. If downloading all business objects, the value is FlexNet Operations.
Submitted by	The ID of the user making the import or export request.
Submitted on	Date and time of the import or export was submitted.
Input filename	Name of the file being imported or exported.

Column	Description
State	<p>Failed—All of the entities failed on import.</p> <p>Completed—At least one of the entities succeeded on import.</p>
Completed time	Date and time the import or export was completed.
Error	<p>If some or all of the entity transactions have failed, the following message appears: Some of the entities have failed. Please view the error log for details. Download Error Log</p> <p>A link to a zip file contains the download error log in XML format.</p> <p>If there were no failures, this column is blank.</p>

- To delete a job from the historical record, select the job and click **Delete**.
- To download a job log to a local file, select the job and click **Download Exported File**.

See Also

- [Import/Export Package Structure](#)
- [Importing and Exporting Entities Overview](#)
- [System Configuration](#)
- [Exporting Entities](#)
- [Using Data Import Templates](#)

Administering License Technologies

In addition to FlexNet Publisher Licensing Toolkit technology, FlexNet Operations supports the use of other license technologies with the core product packaging, entitlement generation, and license support capabilities.

FlexNet Publisher Licensing Toolkit is a feature-based license technology, wherein a software product’s binary code is rendered into licensable features. Variations of the product are achieved by combining different licensed features using FlexNet Operations product packaging rather than changing the binary code. You can view the components of the FlexNet Publisher Licensing Toolkit technology by navigating to **Administer > License Technologies**, and clicking **FlexNet Publisher Licensing Toolkit**.

License technology administration can be divided into the following activities.

Table 22-26 • License Technology Administration Activities

Topic	Description
Managing License Technologies	<p>Viewing, changing the state of, deleting, and specifying the class files for license technologies</p> <ul style="list-style-type: none"> ● Creating a License Technology

Table 22-26 • License Technology Administration Activities

Topic	Description
Using External Services with License Technologies	Explains how to use Revenera-provided interfaces to generate license keys by an external SOAP service. <ul style="list-style-type: none"> • External Service Operations • Creating an External Service
Managing License Generator Configurations	Viewing, deleting, and creating license generator configurations <ul style="list-style-type: none"> • Creating a License Generator Configuration • Creating a FlexNet Publisher Licensing Toolkit License Generator (VCG) Configuration
Managing License Model or License Generator Custom Attributes	Viewing, deleting and adding custom license generator configuration and license model attributes. <ul style="list-style-type: none"> • Creating a License Generator Configuration Custom Attribute • Creating a Custom License Model Custom Attribute
Managing Custom Host Attributes	Viewing, adding, deleting, and creating custom host attributes. <ul style="list-style-type: none"> • Creating a Custom Host Attribute

See Also

- [Managing Custom License Attributes](#)
- [Managing Custom Host Attributes](#)

Managing License Technologies

This page lists the license technologies registered with FlexNet Operations that can be used to create license generator configurations, linked with license models, and associated with products/suites.

Viewing the Details of a License Technology

To view the details of a license technology, perform the following steps.



Task *To view the details of a license technology*

Click its name from the technologies listed.

Changing the State of a License Technology

To change the state of a license technology, perform the following steps.



Task **To change the state of a license technology**

1. Select the box next to its name.
2. Click **Change State**.
3. Select a state (**Draft** or **Deploy** from the Change State drop-down box).



Note ▪ A license technology is created in draft state. After it has been deployed, you can continue to add license generator configurations. However, these generator configurations cannot be edited once they are used to create a (non-test) entitlement. (See [Creating an Entitlement](#).)

Deleting a License Technology

To delete a license technology, perform the following steps.



Task **To delete a license technology**

Select the box next to its name and click **Delete**. A license technology can only be deleted in draft state, and if there are no license generator configurations, products, suites, or license models (including those in draft state) linked to the technology.

Once a license technology is deleted, all custom attributes associated with it are also deleted. You *cannot* delete the FlexNet Publisher Licensing Toolkit technology.

See Also

[Creating a License Technology](#)

Creating a License Technology

To create a license technology, perform the following steps.



Task **To create a license technology**

1. Click **Administer > License Technologies**.
2. Click **Add a License Technology**.
3. Enter the following information in the **Create a License Technology** page:

Table 22-27 ▪ Creating a License Technology

Field	Description
Name	Name to uniquely identify this license technology. This is a required field and must be unique.

Table 22-27 • Creating a License Technology


Field	Description
Description	Describe the characteristics of this license technology that make it unique. The description can be changed at any time.
State	<p>A new license technology is always created in a draft state. Any attribute, except the name of the license technology, can be edited in this state.</p> <p>After a license technology is deployed, no attributes can be edited. Its state can be changed back to draft only if there are no products, suites, and licenses models (entities in draft state excluded) linked to the technology. A license technology can only be deleted in the draft state.</p>
Type	<p>Select a license technology type:</p> <ul style="list-style-type: none"> ● Manual: licenses are generated by a customer support representative manually using a third-party system. Since this license generator is not integrated into FlexNet Operations, when a user generates a license, the generated fulfillment is placed on hold and an email address is sent to the administrator at the address configured in System Configuration. The administrator logs in to the third-party system and generates the license, and then returns to FlexNet Operations to set the license on the on-hold fulfillment record. The user can then download the license. ● Hands-Free: licenses are generated programmatically using a third-party system. After generation, a fulfillment record is placed on hold. Web services are used to update the license text on the fulfillment record. Please refer to the <i>FlexNet Operations Web Services Guide</i> for more information. ● External SOAP Service: licenses are generated by FlexNet Operations, by implementing a web service interface. Please refer to the <i>FlexNet Operations Web Services Guide</i> for more information. <p>Refer to Getting Started with Non-FlexNet Licensing Technologies for additional information on these types.</p>
Generator Service End Point	<p>Enter the path for this licensing technology’s license generator service (required when the license technology type is External SOAP Service; otherwise, optional).</p> <p>Use {CUSTOM_TECH_HOST}/path, where path is the location provided to you by Revenera support.</p> <p></p> <p>Tip • The generator service you create can also be used to create customized filenames for license files and consolidated license files for FlexNet Licensing Technology.</p> <p>See Using External Services with License Technologies for more information.</p>

Table 22-27 • Creating a License Technology


Field	Description
Entitlement Certificate Template	<p>The variation name of the email template to use to generate an entitlement certificate for this license technology.</p> <p>When no path is specified, the default Entitlement Certificate template is used instead.</p>
Entitlement Certificate Email Template	<p>The variation name of the email template to use to create the body of the email for sending an entitlement certificate email attachment for this license technology.</p>  <p>Note - HTML content is always retrieved for this template.</p> <p>When no path is specified, the default Entitlement template is used instead.</p>
Multiple Consolidated Licenses Email Template	<p>The variation name of the email template to use to send a multiple consolidated license email attachment for this license technology.</p> <p>When no path is specified, the default Multiple Consolidated Licenses template is used instead.</p>
Consolidated License Email Template	<p>The variation name of the email template to use to send a consolidated license email attachment for this license technology.</p> <p>When no path is specified, the default Consolidated License template is used instead.</p>
Multiple License Files Email Template	<p>The variation name of the email template to use to send a multiple license files email attachment for this license technology.</p> <p>When no path is specified, the default Multiple Licenses template is used instead.</p>
License File Email Template	<p>The variation name of the email template to use to send a license email attachment for this license technology.</p> <p>When no path is specified, the default License template is used instead.</p>
Is Counted?	<p>Indicate whether or not the user is prompted to provide a fulfillment count when activating the license. A license technology that has counted license models belonging to it can also be defined as counted.</p> <p>For an uncounted license model, a license is generated for only 1 copy at a time.</p>

Table 22-27 • Creating a License Technology

Field	Description
Does this license technology generate replacement keys (i.e., regenerative licensing)	<p>Select whether or not the license technology generates replacement keys. Such a license technology is called regenerative.</p> <ul style="list-style-type: none"> ● Yes—With a regenerative (or replacement) license technology, the last license issued overwrites the previous one. Indicate whether or not the license technology is replacement or incremental. A master copy of the license is stored on the host. For all license lifecycle activities, such as returns or repairs, the master license is updated by FlexNet Operations. When a user downloads a license for a fulfillment record belonging to a replacement technology, the license on the corresponding host is given to the user. ● No—For an incremental license technology, each fulfillment record contains its own license.
Is Return Operation Allowed?	Indicate whether the technology allows license returns.
Is Repair Operation Allowed?	Indicate whether the technology allows license repairs.
Is Rehost Operation Allowed?	Indicate whether the technology allows license rehosts.
Is Stop Gap Operation Allowed?	Indicate whether the technology allows stop gap licenses.
Is Emergency Operation Allowed?	Indicate whether the technology allows emergency licensing.
Is Publisher Error Correction Operation Allowed?	Indicate whether the technology allows publisher correction operations.
Is Upgrade/Upsell/Renew of Fulfillments Allowed?	Indicate whether the technology allows upgrade, upsell, or renewal operations.

Table 22-27 • Creating a License Technology

Field	Description
File Definitions	<p>If the license technology uses multiple license files, you can define multiple file types for each fulfillment record. The end user can download multiple files from each fulfillment record, or receive multiple files of different types as email attachments.</p> <ol style="list-style-type: none">1. Click Add File Definition to add a license file type.2. In the Create File Definition window, enter a name for the file definition.3. Select whether the license file type is text or binary.4. Optionally, enter a description of the file type.5. If any custom host type attributes are defined for this type, enter values for these attributes. (See Managing Custom Host Attributes.)6. Click OK.
Host Type (non-FlexNet)	<p>Host type represents a class of device on which the license-enabled code is intended to run. When a license is generated for a product, FlexNet Operations prompts for the attributes that belong to the product's host type. The settings in the Create Host Type window differ for FlexNet and non-FlexNet licensing technologies.</p> <p>Host types can be included in a license technology either by adding a new host type or selecting an existing host type.</p> <p>To add a host type</p> <ol style="list-style-type: none">1. Click Add Host Type.2. In the Create Host Type window, enter a name for the host type.3. Optionally, enter a description of the host type.4. Click OK. <p>To select an existing host type</p> <ol style="list-style-type: none">1. Click Select Host Type.2. In the Select Host Type window, select the check box for a host type, and then click OK.
	<ol style="list-style-type: none">4. Click Save to save your changes, Reset to clear all fields, and Add New to save and specify a different license technology.5. Click Next to specify attributes for a license generator configuration.

See Also

[Managing License Technologies](#)
[Managing Email Templates](#)

Using External Services with License Technologies

Producers can use Revenera-provided interfaces to deploy external services that provide customized functionality within FlexNet Operations. License keys can be generated, for instance, by an external SOAP service that implements the **LicenseGeneratorService** Web Services Description Language (WSDL).

The server that implements this WSDL is hosted separately from the one that runs FlexNet Operations. It hosts the service externally and operates independently of FlexNet Operations, as shown in the figure below. The external service is accessed by FlexNet Operations at run time for operations such as product and license model validation and license generation.




Figure 22-2: External License Generator

For information on using external services with license technologies, see the following topics:

- [External Service Operations](#)
- [Creating an External Service](#)



Note - The availability of certain operations varies with your FlexNet Operations license technology type. Producers can implement a custom filename generator service for FlexNet Licensing Technology and connect FlexNet Operations to that service by specifying the end point in **Generator Service End Point** on the **Create A License Technology** page. (In this case, implement only the two filename generator methods; the other methods on the external generator service should return null.)

External Service Operations

An external service can be invoked from FlexNet Operations for the following operations:

- CustomGeneratorService
- CustomGeneratorValidator

- CustomLicenseConsolidator
- CustomFilenameGenerator
- CustomHostIdGeneration

External service operations and their descriptions are listed in the following table.

Table 22-28 - External Service Operations

External Service Operation	Description
generateLicense	Generates license
validateProduct	Validates product
validateLicenseModel	Validates license model
consolidateFulfillments	Consolidates licenses for multiple fulfillments
generateConsolidatedLicenseFileNames	Generates license file names for consolidated licenses
generateFulfillmentLicenseFileNames	Generates license file names for single fulfillments
generateCustomHostIdentifier	Generates custom host identifier
ping	Tests external service availability

Creating an External Service



Important - Examples and procedures in this section are based on Java. However, the external service can be created in any technology that supports SOAP, such as gSOAP, C#, or Java. You must make the necessary modifications and follow the procedures specific to the technology you choose.

Following are procedures for setting up a sample external service web application, creating the external service license technology, and testing the external service. You must have the extgenservice.zip FlexNet Operations build archive (download the extgenservice.zip archive from the Product and License Center at <https://flexerasoftware.flexnetoperations.com>), and the application server on which the custom service is to be deployed must be running.

Configuring the License Technology URL

On the FlexNet Operations **Create A License Technology** page, the license technology end point is called the **Generator Service End Point**. It is required when a license technology **Type** of **External SOAP Service** is selected, and optional for FlexNet Licensing Technology or when a **Manual** or **Hands-Free** technology is selected (manual and hands-free technologies rely on an external service for optional consolidators, file name generators, and host ID generators).

Create A License Technology

Create A License Technology

Name: * Custom_Tech_Name

Description:

State: Draft

Type? * Manual Hands-Free External SOAP Service

Generator Service End Point * {CUSTOM_TECH_HOST}/flexnet-licgen/services/LicenseGeneratorService

Figure 22-3: Create a License Technology Page

The external service host is referenced as CUSTOM_TECH_HOST in **Generator Service End Point** on the **Create A License Technology** page. (The CUSTOM_TECH_HOST is configured and maintained by the Revenera administrator and is linked to the custom generator when the license technology is created in FlexNet Operations.) To point to the service hosted by tenant ABCD, the **Generator Service End Point** value would be {CUSTOM_TECH_HOST}/ABCD/services/LicenseGeneratorService.

For existing custom license technology configurations, the old custom license technology URL in the system configuration is deleted from the database when the URL is updated.



Task *To set up the sample external service web application*

1. Create a directory on your local machine called C:\TenantTests\ExtLicenseService, for example.
2. Extract the extgenservice.zip archive, which contains these files:
 - lib – required .jar files
 - src – sample implementation Java files
 - schema – WSDL and XSD files
 - build.xml – ant build file
 - readme.txt – information file
3. Run the ant build tool to build the flexnet-licgen.war sample application.
4. Rename the .war file, if necessary, to use a different context path.
5. Deploy the .war file in the application server.
6. Start the application server, which deploys the application.



Task **To create the external service license technology**

1. Log in to FlexNet Operations.
2. Create the external license service technology. (Refer to the [Creating a License Technology](#) procedure).
 - a. For **Type**, select the license generator type **called External SOAP Service**.
 - b. For **Generator Service End Point**, type this path:
`{CUSTOM_Tech_HOST}/flexnet-licgen/services/LicenseGeneratorService`
3. Click to test the connection.
4. Deploy the external service license technology. (Refer to the [Managing License Technologies](#) procedure).
5. Create the external service license model. (Refer to the [Creating a License Model](#) procedure).
6. Deploy the external service license model. (Refer to the [Deploying a License Model](#) procedure).
7. Create a product using the external service license technology and license model, then deploy the product. (Refer to the [Creating a Product](#) and [Deploying a Product](#) procedures).
8. Create an entitlement for a few copies of the product, then deploy the entitlement. (Refer to the [Creating an Entitlement](#) and [Viewing Entitlements](#) procedures).
9. Ensure that the system configuration specifies the default URL for the external service (**System > Configure > FlexNet Operations**).



Task **To test the external service**

1. Activate a license for one copy of the product to send a request to the external service.
2. To perform a negative test, stop the application server. Try to activate a license for another copy of the product. You should receive an error message because the application server is not running.

Managing License Generator Configurations

A given license technology may have one, or many associated *license generator configurations*. For example, FlexNet Publisher Licensing Toolkit may have several license generator configurations to support different release versions. You may also want different license generator configurations to support different encryption levels for generated licenses.

A license generator configuration lets a publisher model any attributes that are specific to the license generation toolkit or executable. These are typically not business attributes. For example, with FlexNet technology, an example of an attribute could be the encryption strength used to generate a license.

The **License Generator Configurations** page displays the following information:

Table 22-29 ▪ License Generator Configuration Page

Field	Description
Name	Name of the license generator configuration.
License Technology	License technology to which the license generator configuration belongs.
Description	Description of the license generator configuration.

Viewing the Details of the License Generator Configuration

To view the details of the license generator configuration, perform the following steps.



Task *To view the details of the license generator configuration*

Click its name.

Deleting a Configuration

To delete a configuration, perform the following steps.



Task *To delete a configuration*

Select the box next to its name, and click **Delete**. A configuration cannot be deleted if its associated license technology is deployed, or if there are products and suites associated with the configuration.

Creating a New Configuration

To create a new configuration from a page, perform the following steps.



Task *To create a new configuration from this page*

Click **Add a License Generator Configuration**.

You can edit a license generator configuration as long as there are no (non-test) fulfillments against it.

Creating a License Generator Configuration



Note ▪ When creating a license technology, if you do not have any configuration for the license generator executable, you can skip this step.



Task **To create a license generator configuration for a draft or deployed license technology**

1. Navigate to the **Create a License Generator Configuration** page.
2. Enter the following fields:

Field	Description
Name	Name to uniquely identify this license generator configuration. This is a required field and must be unique for a given license technology.
Description	Describe the characteristics of this license generator configuration that make it unique. The description can be changed at any time.
License Technology	License technology for which this license generator configuration generates licenses. This field cannot be changed after it is saved.

3. If the license generator configuration has custom attributes defined, you must specify their values on this page.
4. Click **Save** to save your changes, **Reset** to clear all fields, and **Add New** to specify a different configuration.
5. Click **Next** to create a custom license model attribute.

To create a license generator configuration for FlexNet Publisher Licensing Toolkit, see [Creating a FlexNet Publisher Licensing Toolkit License Generator \(VCG\) Configuration](#).

See Also

- [Managing License Generator Configurations](#)
- [Managing Custom License Attributes](#)
- [Creating a License Technology](#)

Creating a FlexNet Publisher Licensing Toolkit License Generator (VCG) Configuration

A *Vendor Certificate Generator (VCG)* is an executable built by a publisher using the FlexNet Publisher Licensing Toolkit technology. A VCG contains unique encryption seeds used to digitally sign licenses. FlexNet Operations can be configured to use multiple VCGs. FlexNet Operations ships with a VCG for a vendor named “demo,” which you can use for testing purposes. This is equivalent to `1mcrpt` in the FlexNet Licensing toolkit.


FlexNet Publisher Licensing Toolkit license files are encoded using UTF-8.



Task **To configure FlexNet Operations with your own production VCG**

1. In the FlexNet Operations Producer Portal, click **Administer > License Generators**.
2. Click **Add a License Generator Configuration**.
3. From the **License Technology** drop-down list, select **FlexNet Publisher Licensing Toolkit**. (To create a license generator configuration for a different license technology, see [Creating a License Generator Configuration](#).)

4. View or change the values of the following settings. Required fields are indicated with an asterisk. If a default value exists, it is listed as the first choice.

Setting	Description
Name	Name to uniquely identify this license generator configuration in drop-down lists.
Description	Describe the characteristics of this license generator configuration that make it unique. The description can be changed at any time.
License Technology	License technology for which this VCG configuration generates licenses: Select FlexNet Publisher Licensing Toolkit .
Name of the VCG Executable	The name of the VCG executable. For example, the name of the demo VCG executable is "demo," "demo_vcg," (UNIX) or "demo_vcg.exe" (Windows only). Required.
Vendor Daemon Name	Name of the vendor daemon for which this VCG generates licenses. If not specified, this name is inferred from the name of the VCG executable .  Note - Vendor daemon name must match the vendor name in the publisher.xml file. The name is case-sensitive.
Index to VCG Generator Function Table (default is 0)	Integer index into the custom generator table inside the VCG.
Index to VCG Crypt Seed Table (default is 0)	Integer index into the key seed array inside the VCG.
License Signature Strength	The encryption strength of licenses generated by the VCG: The strength configured in the VCG can be overridden on this page.
License Signature Compatibility Level	Used to allow backward compatibility with version 8.0 CRO (TRL). The setting in the VCG can be overridden on this page.
Include License Key Strength for pre-TRL Compatibility	Used to add a 20-character license key along with a SIGN= signature. The setting in the VCG can be overridden on this page.
FlexNet Licensing Version for Compatibility with Client Application	The FlexNet Publisher Licensing Toolkit license file format to use to format the generated license: The setting in the VCG can be overridden on this page.

Setting	Description
Format String for Date-based Versions	<p>When a feature is created in FlexNet Operations, its version is specified to be either fixed or date-based. Using date-based versions is a product versioning strategy. In this scheme, the version number of the FlexNet Publisher Licensing Toolkit feature line is a representation of the calendar date when a customer's maintenance for the product expires. The version number that the application asks for when it checks out a license is a representation of the date it was built. Therefore, a customer has the right to use a version (the build date) of the application less than or equal to the date that the maintenance expires (the version in the license). The date-based version that the VCG puts in the license varies from license certificate to license certificate, whereas a fixed version is the same for all licenses generated for that product-version combination. If a feature is created that uses a date-based version format, the date that is expressed in that format is specified when an entitlement line item containing that product is configured.</p> <p>For a date of May 15, 2009, yyyy.MM gives 2009.05 and yyyy.MMdd gives 2009.0515.</p>
Suppress START Date Keyword in License Text	Used to suppress the START Date keyword identifying the license start date in a feature line.
Suppress ISSUED Date Keyword in License Text	Used to suppress the ISSUED Date keyword identifying the license issue date in a feature line.
Server host ID used for Trusted Activations	Fill in applicable data.
Default Server Port Number in License File	Fill in applicable data.
Version of VCG	<p>Version number of the VCG executable used to generate licenses. This setting is used to check whether FlexNet Publisher keywords and hostID types in a license are supported by the version of the VCG and also to deliver appropriate error messages when conflicts are discovered.</p> <p>If you are using VCG 11.5, for example, then set Version of VCG to 11.5.0. Default version: 6.2.1.</p> <p>Your current VCG version can be identified by executing the VCG with the version flag. For example: <code>demo_vcg.exe version</code>. So, if this command returns the VCG version (not the vendor version) 12.11.0.0, for instance, the Version of VCG value can be 12.11, 12.11.0, or 12.11.0.0.</p>

5. Click **Save** to save the configuration for this VCG.

Managing License Model or License Generator Custom Attributes

The **Custom Attributes** page lists custom attributes with the following information:

Table 22-30 • Custom Attributes Information

Field	Description
Name	Name of the custom attribute
Type	Type of value the custom attribute accepts: Boolean, Date, Text (free form or single select), Multi-valued text, or Long Text.
Belongs To	Whether the attribute is associated with a license model or a license generator configuration
License Technology	Name of the license technology to which the attribute belongs.

Click an attribute name to *view* its details.

- Click **Add a License Model Attribute** to create a custom license model attribute.
- Click **Add a License Generator Attribute** to create a license generator configuration attribute, as described in [Creating a License Generator Configuration Custom Attribute](#).

Select the box next to an attribute and click **Delete** to delete it.

- Custom attributes cannot be deleted if the associated license technology is deployed.
- When a custom attribute is deleted from a draft license technology, then all references to this attribute are deleted from the corresponding generator configuration or license model.

Creating a License Generator Configuration Custom Attribute



Note • When creating a license technology, if you implement your license generator class so that it references the license generator executable, you can skip this step. In the flow of the **Create a License Technology** wizard, this step precedes creating the license technology configuration itself.

You can create a license generator configuration attribute for custom license technologies in the draft state. You cannot create a license generator configuration attribute for FlexNet Publisher Licensing Toolkit.



Task To create a license generator configuration attribute:

1. Navigate to the **Create Custom Attribute** page.
2. Specify the following information for your custom generator attribute:

Field	Description
Name	Name to uniquely identify this custom license generator configuration attribute: this name must be unique within a given license technology.
License Technology	License technology that includes the license generator configuration for this attribute. Choose from the drop-down list. This value cannot be changed after it is set.
Is Required?	Will this be a required or optional attribute for license generation?
Type	Type of value the custom attribute accepts. This cannot be changed after it is set. <ul style="list-style-type: none">● Number: An integer.● Text: An alphanumeric string.● Max Length: Maximum number of characters the text field will accept● Text Type: this cannot be changed after it is set.<ul style="list-style-type: none">● Free Form: If you select this option, your custom attribute will take a typed-in alphanumeric string.● Single Select: If you select this option, your custom attribute will take the value of an item from a drop-down list.● Multi Valued Text: If you select this option, your custom attribute will take the value of several selected boxes next to items in a specified list.● Valid Values: Use to specify a list from which Single Select or Multi Valued Text items can be chosen.● Long Text: A text value that can be up to 16384 characters. The value can be typed or pasted into the text box. (The Display Type setting controls how a long text value will be displayed.)● Boolean: A pair of options for mutually exclusive choices, that is, “Yes” or “No”.● Date: A date that can be selected from a calendar tool.

3. Click **Save** to save your changes, **Next** to move to the next page without saving, **Reset** to clear all fields, and **Add New** to specify another attribute.



Note - If necessary, create an attribute for the name of your license generator executable.

4. Click **Next** to [create a license generator configuration](#).

See Also

[Creating a License Technology](#)

Creating a Custom License Model Custom Attribute




Note - In the flow of the **Create a License Technology** wizard, this step precedes creating the license model itself.



Task **To create a custom license model attribute**

1. Navigate to the **Create Custom Attribute** page.
2. Fill in the following fields for each attribute you create:

Field	Description
Name	Name to uniquely identify this custom license model attribute: this name must be unique within a given license technology.
License Technology	License technology of which the attribute is a part. Choose from the drop-down list. If you choose FlexNet Publisher Licensing Toolkit from this list, you will be setting custom attributes on its license models.
When Choices	When the value of this attribute must be specified: <ul style="list-style-type: none"> ● License Model Creation—When creating a license model that uses this attribute ● Entitlement:—When creating entitlements with license models that use this attribute ● Fulfillment—When activating licenses with license models that use this attribute
Is Required?	Will this be a required or optional attribute for license generation? If required, this attribute can only be created for a license technology in the draft state.

Field	Description
Type	Type of value the custom attribute accepts.
	<p>Number An integer (for example, 33452).</p>
	<p>Text An alphanumeric string. If you choose this option, the Producer Portal reveals additional controls for Max Length and Text Type.</p> <p>Max Length: Maximum number of characters the text field will accept.</p> <p>Text Type: Choose one of the following:</p> <ul style="list-style-type: none"> ● Free Form—If you select this option, your custom attribute will take a typed-in alphanumeric string. When you select this option, you also need to choose a Display Type to determine how the text attribute will be displayed: Text Field or Text Area. ● Single Select—If you select this option, your custom attribute will take the value of an item from a drop-down list. When you select this option, you also need to specify Valid Values with Add Value. Valid Values determine the list of values a user can choose for this attribute. ● Multi Valued Text—If you select this option, your custom attribute will take the value of several selected boxes next to items in a specified list. When you select this option, you also need to specify Valid Values with Add Value. Valid Values determine the list of values a user can choose for this attribute. <p></p> <p>Important - The Text Type selection cannot be changed after it is set.</p>
	<p>Long Text An alphanumeric string that can be up to 16384 characters. The value can be typed or pasted into the text box. When the attribute's Type is Long Text, also choose a Display Type to determine how the text attribute will be displayed: Text Field or Text Area.</p>
	<p>Boolean A pair of options for mutually exclusive choices, such as Yes or No.</p>
<p>Date A calendar date.</p>	
Required for Reporting	If Yes, then this attribute will be included in data transformation for reporting.



Note - If you create an attribute called “SERIAL_NUMBER,” its label, by default, is displayed as “Serial Number.” This is because SERIAL_NUMBER is a FlexNet Publisher Licensing Toolkit attribute for which resources are already defined. If you change the label for the custom SERIAL_NUMBER attribute, its FlexNet Publisher Licensing Toolkit display label will also change.

3. Click **Save** to save your changes, **Reset** to clear all fields, and **Add New** to specify another attribute, and **Complete** to save and exit this page.

See Also

[Creating a License Technology](#)

Managing Custom Host Attributes

Licenses are usually bound to either a node or a host. Defining a host attribute allows you to use the host as the criteria for capabilities like batch rehosts, searching and sorting on hosts, and listing all fulfillments for a given host.

The **Custom Host Attributes** page lists attributes with the following information:

Table 22-31 - Custom Attributes Information

Field	Description
Name	Name of the custom attribute
Type	Type of value the custom attribute accepts: Boolean, Date, Text (free form or single select), Multi-valued text, or Long Text.
License Technology	Name of the license technology to which the attribute belongs.
Host Type	Type of host for the custom attribute.

Click an attribute name to view its details.

Click **Add a Host Attribute** to create a custom host attribute.

Select the box next to an attribute and click **Delete** to delete it. Custom host attributes cannot be deleted if the associated license technology is in Deployed status.

See Also

[Creating a Custom Host Attribute](#)

Creating a Custom Host Attribute

If custom host attributes are defined for a host type, FlexNet Operations displays them to users when they create a host of that type. You define custom host attributes in a manner similar to defining custom license model attributes.



Note - You can generate a unique identifier for a host, based on these attributes, by implementing the `HostIdentifierGeneratorByHostType` interface under System Configuration. Also, you can validate whether or not the user supplied the appropriate values for these attributes.



Task **To create a custom host attribute**

1. Navigate to the **Create a Custom Host Attribute** page.
2. Fill in the following fields for each attribute you create:

Field	Description
Name	Name to uniquely identify this custom host attribute. This name must be unique within a given license technology/host type combination.
License Technology	The type of license technology with which the attribute is to be used. FlexNet Operations does not report on host attributes for non-FlexNet license technologies.
Host Type	Select a host type from the drop-down list.
Is Required?	Will this be a required or optional attribute for license generation? Click Yes for required attributes. Click No for optional attributes. Required attributes can only be created for a license technology in the draft state.

Field	Description
Type	<p>Type of value the custom attribute accepts. Type cannot be changed after it is set.</p> <p>Number: An integer (for example, 33452).</p> <p>Text: An alphanumeric string. If you choose this option, the Producer Portal reveals additional controls for Max. Length and Text Type.</p> <ul style="list-style-type: none"> ● Max Length: Maximum number of characters the text field will accept. ● Text Type: Choose from Free Form, Single Select, or Multi Valued Text. (This cannot be changed after it is set.) <p>Free Form: If you select this option, your custom attribute will take a typed-in alphanumeric string. When the Text Type is Free Form, also choose a Display Type to determine how the text attribute will be displayed: Text Field or Text Area.</p> <p>Single Select: If you select this option, your custom attribute will take the value of an item from a drop-down list. When the Text Type is Single Select, also specify Valid Values with Add Value. Valid Values determine the list of values a user can choose for this attribute.</p> <p>Multi Valued Text: If you select this option, your custom attribute will take the value of several selected boxes next to items in a specified list. When the Text Type is Multi Valued Text, also specify Valid Values with Add Value. Valid Values determine the list of values a user can choose for this attribute.</p> <p>Long Text: An alphanumeric string that can be up to 16384 characters. The value can be typed or pasted into the text box. When the attribute's Type is Long Text, also choose a Display Type to determine how the text attribute will be displayed: Text Field or Text Area.</p> <p>Boolean: A pair of options for mutually exclusive choices, such as Yes or No.</p> <p>Date: A calendar date.</p>
Required for Reporting	<p>If Yes, then this attribute will be included in data transformation for reporting. The following custom host attribute types are not available for reporting:</p> <ul style="list-style-type: none"> ● Attributes that use a license technology other than FlexNet Licensing ● Long Text type attributes ● Multi Valued Text type attributes.

3. Click **Save** when complete.

Administering License Models

This section explains what license models are, and how to create and configure license models. Included are the following topics:

Table 22-32 •

Topic	Description
About License Models	Answers the question, “What is a license model?” Subtopics also describe the types of license models directly supported by FlexNet Operations and the provide details on the use of certain license model attributes.
Managing License Models	Briefly describes how to view, add, delete, print, and change the state of a license model.
Creating a License Model	Provides a detailed explanation of the license model creation process.
Copying a License Model	Explains how to use a copy of a license model to quickly create a new license model with settings similar to the original.
Deleting a License Model	Shows how to delete license models.
Deploying a License Model	Describes how to change a license model’s state to Deployed.
Printing a License Model	Explains how to print a license model. Printing a license model opens a pop-up window with details about the license model.
Exporting License Models	Discusses how to export one or more license models, as .jar files, with or without dependencies.
Employing a Predefined Substitution Variable	Describes how to use predefined substitution variables in a license string.
Setting Up Custom License Model Attributes	Discusses how to set up custom license model attributes for a license model.
Setting License Model Policies	Provides an overview of the license model policies you can set after you create a license model.

See Also

[Managing Custom License Attributes](#)

About License Models

A *license model* defines licensing characteristics that determine how, when, where, and by whom a Flex-enabled product or suite can be used. One or more license models are linked with licensed products when the products are packaged.

Additional information about license models and license model attributes is collected in the following topics.

Table 22-33 •

Topic	Description
License Model Types	Discusses the different types of license models. This topic includes the following subtopics: <ul style="list-style-type: none"> • Certificate License Models • Trusted License Models • Embedded License Models • Custom License Models
License Model Attribute Specification Time	Explains how producers can choose when a license model attribute is specified. Typically, attributes can be specified when the license model is created, when an entitlement is created, or when a license is fulfilled.
About Overdraft Support	Explains how the license model attribute, Overdraft, operates for license models that support overdraft.
Predefined Substitution Variables for License Strings	Describes the use of predefined substitution variables in license strings and lists predefined substitution variables.
Custom Attributes in License Strings	Describes the use of custom license model attributes in license strings.



Important • *License models must be deployed before the products with which they are linked are deployed; deploying a product does not deploy the linked license models.*

See Also

[License Model Types](#)
[Managing License Models](#)
[Creating a License Model](#)

License Model Types

FlexNet Operations comes with sample license models of each type, and it is possible to create custom license models as well.

These license models can be categorized into the following types:

Table 22-34 • Types of License Models

License Model	Description
Certificate License Models	The FlexNet license server uses the contents of a license file, or license certificate, to control how a given piece of software can be used. You can vary the contents of a license file to provide variations of your application with different licensing needs, such as an evaluation version and a full version, without being required to provide different binaries or recompile your application. Licensing systems that use license files are referred to as certificate-based licensing.
Trusted License Models	License information is stored securely in trusted storage rather than in license certificates. Trusted storage is a secure location on the target system into which FlexNet Publisher Licensing Toolkit can write licensing data. The licensing data stored in trusted storage is encrypted and authenticated so that the end user cannot read or modify it. Moreover, FlexNet Publisher Licensing Toolkit can detect if trusted storage has been deleted or tampered with.
Embedded License Models	For device manufacturers using FlexNet Embedded. The embedded license model includes two license types: counted and uncounted.
Custom License Models	FlexNet Operations can be configured with a variety of custom license models.

See Also

[Administering License Models](#)
[About License Models](#)

Certificate License Models

Certificate license models are used to generate licenses that are distributed as license certificates. After delivery, license certificates cannot be securely revoked. The following table describes the four certificate models that are delivered with FlexNet Operations.

Table 22-35 • Certificate License Models

Certificate Models	Description
Floating Counted	License rights available network-wide from a license server system that can be shared by a limited number of simultaneous instances of the FLEXenabled application.
Floating Uncounted	License rights available network-wide from a license server system that can be shared by an unlimited number of simultaneous instances of the FLEXenabled application: Very uncommon license model.
Nodelocked Counted	License rights to authorize a limited number of instances of a FLEXenabled application running on a specific machine identified by a unique machine ID or host ID: Uncommon license model.

Table 22-35 • Certificate License Models

Certificate Models	Description
Nodelocked Uncounted	License rights to authorize an unlimited number of instances of a FLEXenabled application running on a specific machine identified by a unique machine ID or host ID.

See Also

[License Model Types](#)
[About License Models](#)

Trusted License Models

FlexNet Publisher Licensing Toolkit version 11 introduced the ability to store license information securely in trusted storage rather than in license certificates.

If a product is licensed with any trusted license model, the product must be linked with a transaction key. A transaction key is linked with a product at the time the first trusted license model is linked with the product, and can be overridden for local trials and short code ASRs.

The following table describes the four trusted models that are delivered with FlexNet Operations.

Table 22-36 • Trusted License Models

Trusted Models	Description
Enterprise Activation	<p>The first step in the life of these license rights is activation on a license server. From there, the vendor daemon can:</p> <ul style="list-style-type: none"> • Transfer the licenses to another license server, or • Activate those licenses on end-user machines. <p>Though the licenses are activated on a license server, they are never floating. Also known as <i>Activatable-Server</i>.</p>
Floating Borrowable	<p>The first step in the life of these license rights is activation on a license server. From there, the vendor daemon can:</p> <ul style="list-style-type: none"> • Transfer the licenses to another license server, • Serve them as floating licenses, or • Activate those licenses on end-user machines. <p>Also known as <i>Hybrid</i>.</p>

Table 22-36 • Trusted License Models

Trusted Models	Description
Floating Transferrable	<p>The first step in the life of these license rights is activation on a license server. From there, the vendor daemon can:</p> <ul style="list-style-type: none">• Transfer the licenses to another license server, or• Serve them as floating licenses. <p>The vendor daemon cannot activate these licenses on end-user machines. Also known as <i>Concurrent</i>.</p>
Retail Activation	<p>These license rights are activated only on an end-user machine and authorize an unlimited number of instances of a FlexEnabled application running on that machine. Also known as <i>Activatable-Client</i>.</p>



Note • If you intend to use trusted storage-based licensing, you must build your publisher-specific activation utilities. There are two types of activation utilities: application activation utilities and server activation utilities.

- An **application activation utility** initiates and manages the installation of license rights into trusted storage on an end user's system.
- A **server activation utility** is responsible for initiating and managing the installation of license rights into trusted storage on a license server machine, enabling it to serve licenses to clients.

See Also

[License Model Types](#)
[About License Models](#)

Embedded License Models

Embedded license models are intended for use with software as well as intelligent hardware devices. FlexNet Embedded hosts can be standard software hosts as well as devices and servers.

Devices typically have limited memory and network connectivity, and are manufactured in a variety of types, with different licensable features.

These hardware devices have two license sources to enable their feature set.

- A *pre-installed license* enables the device's default features.
- An *additional license* enables the features specific to a particular device model. For example, a manufacturer can create a basic camera model with a pre-installed license, and then create any number of additional models in the same line that use the same hardware as the basic camera, but include additional licenses that enable each model's features.

The following table describes the four embedded license models that are delivered with FlexNet Operations:

Table 22-37 • Embedded License Models

Embedded Models	Description
Embedded Counted	License rights authorize a limited number of instances of a device feature set, identified by a unique device ID or host ID.
Embedded Uncounted	License rights authorize an unlimited number of instances of a device feature set, identified by a unique device ID or host ID.
Named User Licensing	Auto-provisioned model that eliminates borrow period for served devices.
Concurrent User Licensing	Auto-provisioned model for any served device.



Note • Models were added as a convenience for those who want to mimic user based licensing scenarios with Cloud Licensing Service.

For producers who use FlexNet Usage Management, FlexNet Operations also supports metered license models. Metered license models reflect licensing scenarios where usage is flexibly tracked and reported so that, while firm limits can still be enforced, end users can consume capacity or counts and later reconcile payment based on their actual usage. (See [About Usage Management](#) for an introduction to usage management.)



Note • Embedded license models are only available for software publishers and device manufacturers who use FlexNet Embedded.

See Also

- [Managing Devices](#)
- [Supporting Embedded Licenses](#)
- [License Model Types](#)
- [About License Models](#)

Custom License Models

You can also configure FlexNet Operations with a variety of custom license models.

See Also

- [License Model Types](#)
- [About License Models](#)

License Model Attribute Specification Time

To help make an individual license model applicable to a set of products, the value of many license model attributes can be set to be specified at one of several times, for example:

- License Model Time—Fixed when a license model is created

- Entitlement Time—Set when an entitlement line item is configured
- Fulfillment Time—Specified when a license is activated

Additional license models can be created through the Producer Portal, either from scratch or by copying one of the existing license models. License models cannot be imported using the Product Packaging Web service.

See Also

- [Creating a License Model](#)
- [Managing Custom License Attributes](#)

About Overdraft Support

As described in [Overdraft](#), you can enable the **Overdraft** option to allow a specified number of users to run a software package during peak usage times, even after the application’s license limit has been reached. When defining overdraft support in a license model, you define a set of rules that govern the total overdraft count available per entitlement, and how much may be applied each time a license is activated.

You specify the overdraft **Maximum** value as either unlimited, a specific number, a specific percentage, or you can choose to specify a number when you create an entitlement based upon this license model. After you specify the Maximum overdraft value, you are then prompted to specify a **Floor** and a **Ceiling** overdraft value:

Table 22-38 •


Field	Definition	Options
Floor	<p>Use to define a per-fulfillment minimum overdraft, which is the overdraft count that must be issued for each license activated using this license model, subject to the overdraft Maximum value. The Floor value must be a non-negative integer.</p> <p></p> <p>Note • <i>If a license is activated such that applying the Floor would violate the overdraft Maximum value, then the Maximum value takes precedence (and therefore, the issued overdraft count may be less than the Floor value.)</i></p>	<p>Choose one of the following options:</p> <ul style="list-style-type: none"> ● Unlimited: There is no Floor value; a license may have zero overdraft. ● Specify now: The license model defines the Floor value for all licenses activated using this model. ● Specify now as percentage: The license model defines the Floor value as a percentage of the fulfillment count. The computed Floor value is rounded down (for example, 7.3 would be rounded down to 7).

Table 22-38 •

Field	Definition	Options
Ceiling	<p>Use to define a per-fulfillment maximum overdraft, which is the overdraft count that must be issued for each license activated using this license model, subject to the overdraft Maximum value. The Ceiling value must be a non-negative integer.</p> <p>If a license is activated such that applying the Maximum would violate the overdraft Ceiling value, then the Ceiling value takes precedence, and therefore, the issued overdraft count may be less than the Maximum value.</p>	<p>Choose one of the following options:</p> <ul style="list-style-type: none"> ● Unlimited: There is no ceiling. ● Specify now: The license model defines the Ceiling for all activations using this model. ● Specify now as percentage: The license model defines the Ceiling as a percentage of each activation count. The computed Ceiling is rounded <i>up</i> (for example, 7.3 would be rounded up to 8).

The **Maximum** overdraft value is stored as a property of the item, and it restricts the total overdraft count that can be issued for that item. Any license activated for the item is validated such that the total overdraft issued remains at or below this maximum value.



Note • The sum of the Overdraft counts issued for every fulfillment against a line item must remain at or below the **Maximum**. This rule takes precedence over the **Ceiling** and **Floor**.

Example 1: Overdraft Maximum Applied to Fulfillments of an Entitlement

The Overdraft Maximum represents a limit on the total count of Overdraft that can be issued against each line item for this model.

The license model used in this example is:

Table 22-39 • License Model Example

Value	Description
Maximum	10
Floor	Unlimited
Ceiling	Unlimited

The entitlement used in this example is:

Table 22-40 • Entitlement Example

Value	Description
Count	15

Table 22-40 • Entitlement Example

Value	Description
Maximum	10 (From Model)
Floor	Unconstrained
Ceiling	Unconstrained

The following table lists the results of four customer fulfillments of this entitlement:

Table 22-41 • Customer Fulfillments

Request Number	Fulfillment Request	Result	Entitlement Remaining
Beginning Count			Count = 15 Overdraft = 10
Request 1	Count = 5 Overdraft = 5	Request succeeds.	Count = 10 Overdraft = 5
Request 2	Count = 3 Overdraft = 3	Request succeeds.	Count = 7 Overdraft = 2
Request 3	Count = 5 Overdraft = 5	Request succeeds, but the returned amounts are Count = 5, Overdraft = 2 because only 2 Overdrafts are available.	Count = 2 Overdraft = 0
Request 4	Count = 7, Overdraft = 0	Request returns an error, because the requested count cannot be satisfied.	Count = 2 Overdraft = 0



Note • Failure to satisfy the requested count is an error condition, whereas the requested overdraft is simply reduced to the amount available.

Example 2: Overdraft Floor and Ceiling Applied to Fulfillments of an Entitlement

The Overdraft **Floor** and **Ceiling** represent lower and upper limits on the total overdraft count that can be issued against each line item for this model.

The license model used in this example is:

Table 22-42 • License Model Example

Value	Description
Maximum	50%

Table 22-42 • License Model Example

Value	Description
Floor	5
Ceiling	25%

The entitlement used in this example is:

Table 22-43 • Entitlement Example

Value	Description
Count	45
Maximum	$45 \times 50\% = 22.5$, which rounds to 23, the nearest whole number.
Floor	5
Ceiling	$45 \times 25\% = 11.25$, which rounds up to 12

The following table lists the results of two customer fulfillments of this entitlement:

Table 22-44 • Customer Fulfillment

Request Number	Fulfillment Request	Results	Entitlement Count Remaining
Beginning Count			Count = 45 Overdraft = 23
Request 1	Count = 12 Overdraft = 0	Request succeeds with Count = 12, but Overdraft is set to 5, due to the Floor.	Count = 33 Overdraft = 18
Request 2	Count = 20 Overdraft = 15	Request succeeds with Count = 20, but Overdraft is set to 12, due to the Ceiling.	Count = 13 Overdraft = 6

Example 3: Overdraft Floor and Ceiling Rounding Example

Each of the three Overdraft values (Maximum, Floor, and Ceiling) rounds differently when computed as a percentage:

- **Maximum:** Rounded to the nearest whole number. If the fractional part of the computed value is less than 0.5, it rounds down; if it is greater than or equal to 0.5, it rounds up. For example, 3.25 rounds down to 3, while 3.6 rounds up to 4.
- **Floor:** Rounded down to the previous whole number. For example, 3.75 rounds down to 3.
- **Ceiling:** Rounds up to the next whole number. For example, 3.25 rounds up to 4.

So, if the license model is:

Table 22-45 • License Model Overdraft Values

Value	Description
Maximum	50%
Floor	25%
Ceiling	25%

The computed Maximum, Floor, and Ceiling overdraft values for this entitlement would be:

Table 22-46 • Entitlement Overdraft Values

Value	Description
Count	15
Maximum	$15 \times 50\% = 7.5$, which rounds to 8, the nearest whole number.
Floor	$15 \times 25\% = 3.75$, which rounds down to 3.
Ceiling	$15 \times 25\% = 3.75$, which rounds up to 4.

See Also

[Creating a License Model](#)

[Managing Custom License Attributes](#)

About the License Expiration Grace Period

As described in [Grace Period Days](#), you can enable the **Grace Period** option to allow a FlexNet Embedded application to function, without interruption, after its license has expired. Granting a license expiration grace period enables a producer to detect that an end customer’s application is functioning in a grace period, and to notify the customer that it is time to renew to prevent disruption of their normal business work flow.

The license **expiration date** is the expiration date that is entered and displayed in FlexNet Operations; for license models that support it, the *grace period* is the number of days beyond the license expiration date that an application continues to function. When the license is generated, FlexNet Operations uses the expiration date plus the grace period to set the *entitlement expiration date* (in other words, the grace expiration date)—the date on which the application stops functioning. For example, if the producer enters a grace period of 14 days for a license that expires on March 1st, then the entitlement expiration date is March 15th.

The grace period is configured by the producer at the license model, where the option can be turned on or off (the default value). It is supported on local and cloud license servers for metered and concurrent license models, and for standalone devices (a standalone device is a FlexNet Embedded device that connects directly to FlexNet Operations).



Note - If a renewal entitlement is mapped before an application's parent entitlement expires (to avoid an interruption of service), the grace period of the parent entitlement is suppressed to prevent creation of an extra entitlement during the grace period.

Grace Period Handling in the Usage Analytics Service

When an entitlement line item uses a license model that includes a grace period, notifications about that entitlement sent to UAS include the extended grace period in their end date. This ensures that reports accurately record any usage during the grace period. Currently, UAS does not highlight grace usage separately in its reports; that functionality is planned for a future release.



Note - It is recommended that producers set the entitlement expiration date right after expiration to prevent gaps in usage tracking and enable usage statistics to carry over to the new entitlement.

Predefined Substitution Variables for License Strings

Variables can be used as values for supported license strings: `VENDOR_STRING`, `NOTICE`, `ISSUER`, and `SERIAL_NUMBER`. These variables are resolved when the license is generated.

To express a predefined substitution variable in a license string, on the **Create a License Model** page, specify the value of the string as the substitution variable enclosed in curly braces. For example, to use the Sold-to account ID use `{SoldTo.name}` or to use the Sold-to account name use `{SoldTo.displayName}`.



Important - Predefined substitution variables can be used with custom license technologies provided the license technology implements the `GeneratorRequest` interface.

The following substitution variables are defined:

Table 22-47 - Predefined Substitution Variables

Substitution Variable	Definition
Sold-to account ID	<code>{SoldTo.name}</code>
Sold-to account name	<code>{SoldTo.displayName}</code>
Ship-to address on an entitlement	<code>{Entitlement.shipToAddress}</code>
Order ID on an entitlement line item	<code>{EntitlementLineItem.orderId}</code>
Order line number on an entitlement line item (only for simple entitlements)	<code>{EntitlementLineItem.orderLineNumber}</code>
Activation ID on an entitlement line item	<code>{EntitlementLineItem.activationId}</code>
Product name on an entitlement line item	<code>{EntitlementLineItem.productName}</code>

Table 22-47 • Predefined Substitution Variables


Substitution Variable	Definition
Product version on an entitlement line item	{EntitlementLineItem.productVersion}
Part number on an entitlement line item	{EntitlementLineItem.partNumber}
Entitlement line item status	<p>{EntitlementLineItem.status}</p>  <p>Note • When an entitlement's line item status is changed to anything other than <i>Deployed</i> after license generation, the information in the Vendor String field is different from the vendor string details in the FNP License field on the Fulfillments Details page.</p> <p>The license can only be generated if the line item status is <i>Deployed</i>.</p>
Channel partner account ID	<p>{ChannelPartner.name}</p> <p>This variable refers to a channel partner of type Distributor.</p>
Channel partner account name	<p>{ChannelPartner.displayName}</p> <p>This variable refers to a channel partner of type Distributor.</p>
Fulfillment ID	{Fulfillment.id}
Entitlement ID	{Entitlement.id}
Feature version	<p>{Feature.version}</p> <p>This variable can only be used in the Vendor String field.</p> <p>The format of the feature version specified using the {Feature.version} variable depends on its location:</p> <ul style="list-style-type: none"> • The Vendor String field outside of the FlexNet Publisher license lists all feature versions that are present in the product as comma-separated values. • Inside the FlexNet Publisher license, each individual INCREMENT line displays the VENDOR_STRING keyword with its feature version.

Table 22-47 • Predefined Substitution Variables

Substitution Variable	Definition
Quantity configured on device	{mappedQuantity} This variable is applicable only to FlexNet Embedded licenses.

See Also

[Custom Attributes in License Strings](#)
[Employing a Predefined Substitution Variable](#)
[Creating a License Model](#)

Custom Attributes in License Strings

In addition to explicitly specified strings and predefined substitution variables, a publisher can configure one or more custom attributes that can be expressed as the value of one of the four license strings: Issuer, Notice, Serial Number, and Vendor String.



Note - Custom license model attributes are defined as part of the license technology and their use is governed, in part, by the way they are set up in the license model. For more information about creating custom license model attributes, see [Adding Custom License Attributes](#). For more information about creating other types of custom attributes, see [Adding Custom Attributes](#).

To express a custom attribute in a license string, at the time the license model is created (on the **Create a License Model** page), specify the value of the attribute in the license string as the name of the attribute, with a prefix depending on the type of attribute, enclosed in curly braces.

Table 22-48 •

Custom Attribute Type	Prefix
License Model	(no prefix)
Product	Product.
Line Item	EntitlementLineItem.
Entitlement	Entitlement.
Account	SoldTo.

For example, to use the value of a license model attribute named CPU_CAPACITY in VENDOR_STRING:

Vendor String | Specify Value Now | {CPU_CAPACITY}

For example, to use the value of a product attribute named PRODUCT_FAMILY in NOTICE:

Notice | Specify Value Now | {Product.PRODUCT_FAMILY}

The name of the attribute as specified in the license string is case sensitive.

If any custom license model attributes have been configured on the license technology, they are displayed in the license model wizard in the **Set Up Custom Attributes** page that appears between the **Create a License Model** and **Set Up Policies** pages. The **Set Up Custom Attributes** page is used to select the time that the true value of the custom license model attribute is set (license model time, entitlement time, or fulfillment time).

Other custom attributes are displayed when creating or editing instances of the entities they are defined on.

See Also

- [Predefined Substitution Variables for License Strings](#)
- [Setting Up Custom License Model Attributes](#)
- [License Model Attribute Specification Time](#)
- [Adding Custom License Attributes](#)
- [Creating a License Model](#)

Managing License Models

License models can be managed on the **License Models** page.



Task

To open the License Model page

- Click **Administer > License Models**.

The **License Models** page automatically displays recently accessed license models, if applicable. To view all license models, select **License Models** from the **Search For** choice list, and click the **Simple Search** button. You can also search for license models based on specific criteria.

Several sample license models are delivered with FlexNet Operations.

From this page, you can

Table 22-49 • Managing License Models

Capability	Description
Add a new license model from scratch	To add a new license model, click Create New License Model .
Make a new license model from a copy of an existing license model	To copy a license model, select exactly one license model and click the Copy button. Follow the guidelines to add a new license model.
Delete a license model	To delete a license model, select one or more license models and click the Delete button.

Table 22-49 • Managing License Models

Capability	Description
Change the state of a license model	<p>To change the state of one or more license models, select the license models, click the Change State choice list, and select a state. License models can be in one of the following states: Draft, Deployed, Inactive, or Obsolete.</p> <ul style="list-style-type: none"> ● Draft: A license model is created and can be edited in the draft state. ● Deployed: A license model must be deployed to be linked to a product. ● Inactive: An inactive license model cannot be linked to a product or used to create an entitlement. Existing fulfillments using an inactive license model can be activated, returned, repaired, and rehosted. ● Obsolete: An obsolete license model can be deleted.
Print a license model	<p>To print a license model, select one or more license models and click the Print button.</p>

Creating a License Model

A license model defines licensing characteristics that determine how, when, and where a Flex-enabled product can be used.



Tip • A license model can be created from scratch or by editing a copy of an existing license model. To start with a copy, select an existing license model on the **License Models** page and click **Copy**.



Task

To create a license model

1. Click **Administer** > **License Models**. This link opens the **License Models** page.
2. Click **Create New License Model**. This button opens the **Create a License Model** page.
3. If more than one license technology is defined, select the license technology for which this license model is valid.
4. If the license model is for FlexNet Publisher Licensing Toolkit or for a custom license technology, follow these steps to define the license model.



Note • Required fields are indicated with a red asterisk.

5. Provide a name and a description for the license model, and specify the expiration setting.

Table 22-50 ■ Identifying a New License Model

Value	Description
Name	Name to uniquely identify this license model: The name can contain spaces.
Description	Describe the characteristics of this license model that make it unique. The description can be changed after the license model is deployed.
State	<p>A license model can be in one of four states: Draft, Deployed, Inactive, or Obsolete:</p> <ul style="list-style-type: none">● Draft: A license model is created as a draft that can be modified or deleted.● Deployed: After a license model is deployed to use in production, it cannot be deleted or modified. Before a product can be deployed, its linked license models must be deployed (deploying a product does not deploy its linked license models). A draft license model can be linked to a deployed product or suite, but the license model cannot be used in an entitlement line item until it is deployed.● Inactive: An inactive license model cannot be deleted or modified. An inactive license model cannot be used to create an entitlement, but a product with an inactive license model on an existing entitlement line item can be activated.● Obsolete: Deployed and inactive license models can be made obsolete. Obsolete license models behave like inactive license models, but can be deleted.
Expiration	<p>Should licenses activated using this license model be permanent or should they expire?</p> <ul style="list-style-type: none">● None: If you choose None, you defer deciding if these licenses are permanent or expiring until the time you configure an entitlement line item.● Permanent: If you choose Permanent, these licenses never expire.● Expiring: If you choose Expiring, set a duration of <i>n</i> days, weeks, months, or years.

6. Click **Next**.
7. Subsequent steps vary depending on whether you are creating a license model with FlexNet license technology or custom license technology:
 - If this is a license model for a custom license technology, configure any custom license model attributes and click **Save** to save the license model or click **Next** to configure **policies** on the license model.
 - If this is a FlexNet Publisher Licensing Toolkit or FlexNet Embedded license model, click **Next** to continue defining the license model. FlexNet Operations presents the license model settings as a dynamic set of decisions. (Additional information about these attributes is available in FlexNet Publisher Licensing Toolkit or FlexNet Embedded documentation.)

a. Is this an Embedded License Model?

Value	Description
Yes	Identifies the license model intended for devices that use the FlexNet Embedded toolkit.
No	Identifies the license model as one intended for software products that use the FlexNet Publisher toolkit.

b. Will this License Model be Sharable? (FNP toolkit)

Value	Description
Yes	A sharable, or floating license can be used by anyone on the network, up to the limit specified in the license. Floating licenses require a license server system to be running to count the concurrent usage of licenses. If a license is floating, it is most common for it to be counted, allowing only limited checkouts.
No	A license that is not sharable, sometimes known as node-locked, can be used only on one machine or a specified set of machines.

c. Is this a Counted Model? (FNE toolkit)

Value	Description
Yes	Counts the number of seats deployed to customers.
No	Provides unlimited copies.

d. Will this License Model allow Unlimited Checkouts? (FNP toolkit)

Value	Description
Yes (unlimited)	An uncounted license allows unlimited concurrent usage. If a license is uncounted, it is most common for it to be nodelocked. The floating uncounted certificate license model in FlexNet Operations is implemented as a floating counted license with DUP_GROUP=SITE.
No (limited)	A counted license allows usage limited by the count in the license. If a certificate license is counted, it is most common for it to be floating. However, it is possible to have a nodelocked counted license.

e. Is this an Activatable License Model?

Is this license delivered into trusted storage or as a certificate?	
Select Yes if license is delivered into trusted storage.	FlexNet Publisher Licensing Toolkit v11.x can activate trusted licenses. Trusted licenses are usually activated automatically and securely with an activation utility written by the publisher of the licensed software. Products linked with a trusted license model must also be associated with a transaction key .
Select No if license is delivered as a certificate.	All versions of FlexNet Publisher Licensing Toolkit can generate certificate licenses that are emailed or otherwise delivered to a software customer.

f. Is this License Model Detachable?

This license can be transferred among license servers. Is it also detachable to a client machine?	
Yes (detachable)	Only applicable to trusted license models. Licenses are floating and served from a license server, but they can also be removed from the floating group of licenses and be activated on an individual client machine.
No (not detachable)	Only applicable to trusted license models. Licenses are floating and only served from a license server. The licenses can be configured to allow them to be transferred between vendor daemons.

g. Is this License Model for an End User or for an Enterprise?

Will this license be activated from FlexNet Operations by a retail client or by a license server in an enterprise environment?	
End User	An end-user license is sold to an individual retail user. Only applicable to trusted license models.
Enterprise	A volume license is sold to an enterprise user. Only applicable to trusted license models.

h. Is this a Metered Model? (FNE toolkit)

Value	Description
Yes	Designates the license model as a usage-based model. (Usage-based licensing is available to producers who use FlexNet Embedded and FlexNet Usage Management.)
No	License does not use the usage management feature to track usage.

i. Fill in the Attributes for this License Model.

Depending on the decisions made above, sets of choices are presented.

Choice	Description
Allow Partial fulfillments	<p>If you select Yes, when you Activate Licenses for a customer, FlexNet Operations allow you to activate a portion of the total amount entitled to that customer (that is, the total amount that they purchased). If you select No, you must activate the total amount in the single transaction.</p>
Package Specification (for uncounted licenses)	<p>Applicable to all uncounted certificate license models.</p> <p>Select None if this license model is to be associated with a product that is not defined as a package.</p> <p>Select Basic if this license model is used to provide a PACKAGE line as a compact, efficient way to distribute a large number of features that share most of their feature line arguments.</p>
Package Specification (for certificate counted licenses)	<p>Applicable to certificate counted licenses.</p> <ul style="list-style-type: none"> ● Select None if this license model is to be associated with a product that is not defined as a package. ● Select Basic for the Package Specification if this license model to provide a PACKAGE line as a compact, efficient way to distribute a large number of features that share most of their feature line arguments. <p>Select Suite if this license model:</p> <ul style="list-style-type: none"> ● Is to be associated with a product that is a package. ● Is counted. ● Allows a license to be shared among the components of the package using OPTIONS=SUITE on a PACKAGE line. Within a package suite, a license is shared by the components of the package rather than being applied to one specific feature. <p>Select Suite Reserved if this license model:</p> <ul style="list-style-type: none"> ● Is to be associated with a product that is a package. ● Is counted. ● Specifies Client Uniqueness, most as commonly User. ● Allows a set of package components to be granted to a fixed number of users at any one time using OPTIONS=SUITE_RESERVED on a PACKAGE line. In addition, after a user checks out a license for one component, licenses for the other package components are reserved for that user. A set of package components remain reserved for the given user until all licenses for the set are checked back in.


Choice	Description
Package Specification (for trusted floating licenses)	<p>Applicable to trusted floating (transferable and borrowable) licenses.</p> <p>Select None if this license model is to be associated with a product that is not defined as a package.</p> <p>Select Suite Reserved if this license model:</p> <ul style="list-style-type: none"> ● Is to be associated with a product that is a package. ● Is counted. ● Specifies Client Uniqueness, most as commonly User. ● Allows a set of package components to be granted to a fixed number of users at any one time using <code>OPTIONS=SUITE_RESERVED</code> on a <code>PACKAGE</code> line. In addition, after a user checks out a license for one component, licenses for the other package components are reserved for that user. A set of package components remain reserved for the given user until all licenses for the set are checked back in.
Client Uniqueness	<ul style="list-style-type: none"> ● Applicable to certificate counted licenses and trusted floating transferable and floating borrowable licenses. Also known as duplicate grouping. ● Duplicate grouping allows a vendor-defined combination of users, hosts, and displays to be considered in the same group such that license requests from any member consumes only one license. Any combination of User, Host, Display, and Vendor can be selected. ● If Vendor is selected, <code>LM_A_CHECKOUT_DATA</code> must be set and all requests with the same vendor-defined data use the same license. This is useful for sharing licenses among otherwise unrelated processes. ● Setting Client Uniqueness for a package suite affects only its enabling feature line. It limits the total number of users of the package to the number of licenses, and allows the package to be shared among the users that have the suite checked out. Without Client Uniqueness constraints specified in the components of package suite, a floating license is shared among the components of the package regardless of the number of users. ● Client Uniqueness must be specified to get suite reserved behavior.

Choice	Description
Terminal Server Usage	<p>Controls whether a licensed application can be run from a Terminal Server client. Choose from</p> <ul style="list-style-type: none"> ● Not Used—Prevents Terminal Server client access in the license model. This is the default setting for Terminal Server Usage. ● Specify Value Now—Permits Terminal Server client access (for one or many clients) in the license model. ● Specify Value at Entitlement Time—Allows Terminal Server Usage to be set during entitlement. ● Specify Value at Fulfillment Time—Allows Terminal Server Usage to be set when the license is fulfilled. <p>To permit access from one Terminal Server client (one session), choose One Connection Allowed. This adds the ONE_TS_OK keyword to the feature line. This setting only applies to Flex-enabled applications built with FlexNet Publisher Licensing Toolkit version 11.5 or later.</p> <p>To permit access from multiple clients (multiple sessions), choose Many Connections Allowed. This adds the TS_OK keyword to the feature line. This setting only applies to Flex-enabled applications built with FlexNet Publisher Licensing Toolkit version 8.0 or later.</p> <p>To prevent access from Terminal Server clients, choose Not Used.</p> <p>Applications built with versions of FlexNet Publisher Licensing Toolkit prior to version 8.0 do not support this license model feature (and thus may always run using Terminal Server). Therefore, in licenses for applications built with version 8.0 or earlier FlexNet Publisher Licensing Toolkit set Terminal Server Usage to Not Used. Similarly, applications built with a version of FlexNet Publisher prior to 11.5 do not support the One Connection Allowed setting.</p> <p>These settings apply to applications using a nodelocked uncouted, retail activation, or enterprise activation license. FlexNet Publisher Licensing Toolkit detects when a nodelocked uncouted license is running under Windows Terminal Server.</p> <p>To allow your Flex-enabled application to run using a Terminal Server client, nodelock the license to the Terminal Server.</p>

Choice	Description
FLEXid Sharing	<p>This property, which is applicable to nodelocked uncounted licenses, enables mobile licensing using a FLEXid with FLOAT_OK for a particular feature line.</p> <p>This feature line must be nodelocked to a FLEXid (a dongle that connects to a parallel or USB port).</p> <p>One feature line containing the FLOAT_OK keyword and one FLEXid is needed for each instance of a license that can be mobile.</p> <p>When the FLEXid is attached to a license server, the license floats on the network. When the FLEXid is removed from the license server, the license is available only on the standalone computer with the FLEXid attached.</p> <p>This property is supported only on Windows machines.</p> <p>If a license is to be moved between different Windows machines, it is nodelocked to a FLEXid. To move a license to a different machine, the dongle must be moved to that machine.</p> <p>Select one of the following options:</p> <ul style="list-style-type: none">● Not Used: Select to disallow mobile licensing.● Allow: Select to allow mobile licensing using a FLEXid with the FLOAT_OK keyword (without a server_hostid). The FLOAT_OK keyword is generated for each FEATURE line in the license file. The nodelocked host ID given at fulfillment time lists the FLEXid to which the license should be attached.● Specify Value At Entitlement Time: Select to prompt the user at entitlement time to specify if mobile licensing is allowed. At that time, the user would enter the host ID of the license server machine to which the FLEXid (specified as the nodelocked host ID) can be attached to allow this license to float.● Specify Value At Fulfillment Time: Select to prompt the user at fulfillment time to specify if mobile licensing is allowed. At that time, the user would enter the host ID of the license server machine to which the FLEXid (specified as the nodelocked host ID) can be attached to allow this license to float.


Choice	Description
FLEXid Sharing <i>(continued)</i>	<p>When generating a license, specify a <i>FLEXid</i> as the Nodelocked Hostid and the server host ID for FLEXid Sharing. A SERVER line is added to the generated license certificate and:</p> <ul style="list-style-type: none">• The <code>server_hostid</code> is the same host ID that appears on the SERVER line of the license file, or could be a different host ID that refers to the same machine. If the SERVER line host ID is ANY, the <code>FLOAT_OK server_hostid</code> must be specific to the license server machine.• The license server can only be run on the machine with the host ID that <code>lmhostid</code> returns equal to the <code>server_hostid</code> specified with <code>FLOAT_OK</code>.• A user can run on the license server machine, but he can use only the license being served by the license server, not the nodelocked license. Otherwise an extra use for each <code>FLOAT_OK</code> license could occur. Note that without the <code>server_hostid</code> specified on the feature line, the <code>FLOAT_OK</code> license can be served from any computer, as long as the <i>FLEXid</i> is attached to it.• The host ID on the <code>FLOAT_OK</code> feature line must be only a single host ID. For multiple <i>FLEXids</i>, use individual feature lines for each <i>FLEXid</i>.

Choice	Description
Time Zone	<p>Controls whether or not licensing is limited to specified regions (expressed as time zones). Choose from</p> <ul style="list-style-type: none">● Not Used—Licenses are not restricted by time zone. This is the default setting for Time Zone.● Specify Value Now—Limits licenses to publisher-defined time zone values in the license model.● Specify Value at Entitlement Time—Allows Time Zone limitations to be set during entitlement.● Specify Value at Fulfillment Time—Allows Time Zone limitations to be set when the license is fulfilled. <p>To limit usage based on time zone, choose a time zone value from the list. Time zone values must be defined by the publisher. For details, see Working with Time Zones.</p> <p>To limit usage to machines running in the same time zone as the license server machine (served licenses only), choose Server Time Zone Only.</p> <p>To ignore time zones for licensing purposes, choose Not Used.</p> <p>Time zone-based licensing is supported for licenses generated by FlexNet Publisher version 11.7 or later, and applies to the following certificate-based licenses: floating counted, floating uncounted, and nodelocked counted.</p> <p>Time zone-based licensing is not available for nodelocked uncounted license models (because limiting licenses based on their geographic location is not required if an unlimited number of licenses is available). In this case, the Time Zone setting will be blank.</p> <p>The special Time Zone setting, Server Time Zone Only, is not applicable to licenses that do not include a SERVER line nor to nodelocked uncounted licenses, generally.</p>

Choice	Description
Virtualization Restrictions	<p>Controls whether or not licensed applications are restricted to running only on physical machines or only on virtual machines. Choose from</p> <ul style="list-style-type: none"> ● Not Used—Permits usage on physical and virtual machines the license model: no restrictions. This is the default setting for Virtualization Restrictions. ● Specify Value Now—Restricts licensed applications to running, either on physical machines or on virtual machines, in the license model. ● Specify Value at Entitlement Time—Allows Virtualization Restrictions to be set during entitlement. ● Specify Value at Fulfillment Time—Allows Virtualization Restrictions to be set when the license is fulfilled. <p>To limit usage to physical machines only, choose Restrict to Physical Machines. This adds VM_PLATFORMS=PHYSICAL to the feature line.</p> <p>To limit usage to virtual machines only, choose Restrict to Virtual Machines. This adds VM_PLATFORMS=VM_ONLY to the feature line.</p> <p>To operate without restrictions, choose Not Used.</p> <p>Virtualization Restrictions are supported for licenses generated by FlexNet Publisher version 11.7 or later, and apply to certificate license models: floating counted, floating uncounted, nodelocked counted, and nodelocked uncounted.</p>
Borrowing	<p>Applicable to counted, certificate licenses. To disable borrowing, select Not Used. If any other setting is selected, license borrowing is enabled.</p> <p>If borrowing is allowed, the maximum number of hours that the license can be borrowed for can be specified as the default (168 hours, or one week) or can be specified in the license model, during entitlement, or during fulfillment.</p> <p>The maximum borrow period is limited by the maximum value of a 32-bit integer: 2 billion hours.</p>
Renew Interval	<p>How often—if ever—the client attempts to re-contact the local license server. Successful contact extends the server-imposed expiration based on the borrow period. When using a finite borrow period, for maximum effectiveness, the renew interval should be set such that the client attempts renewal at least two times per borrow interval. It is set as a percentage of the borrow interval in the license model.</p> <p></p> <p>Note - <i>Renew interval is not enforced; it is for the publisher's convenience to use as they want.</i></p>

Choice	Description
Unique Users and Hosts	<p>Applicable to certificate counted licenses and trusted floating transferable and floating borrowable licenses. Sets the number of users (User Based) or host names (Host Based) that can be specified in INCLUDE statements in the end-user options file.</p> <ul style="list-style-type: none"> ● Select Not Used if you do not want to include the USER_BASED or HOST_BASED keyword. ● Select Use Default Value to use the full license count. ● Select Specify Value Now to specify the number of users or host names in the license model. ● Select Specify Value At Entitlement Time or Specify Value At Fulfillment Time to specify the number of users or host names later.
Reusable	<p>Applicable to metered (usage-based) license models, Reusable specifies whether the usage counts can be increased and decreased by the usage client or only increased. Choose either Yes or No.</p> <ul style="list-style-type: none"> ● Yes: Usage counts can be increased when counts are consumed and decreased if a feature checkout is canceled or reversed. ● No: Usage counts can only increase (with possible exceptions expressed in the Undo Interval).
Undo Interval	<p>Applicable to metered (usage-based) license models, Undo Interval defines a window in which feature checkouts can be canceled even if Reusable is set to No. Choose from Not Used, Specify Value Now, and Specify Value at Entitlement Time.</p> <ul style="list-style-type: none"> ● Select Not Used if Reusable is set to Yes or if Reusable is set to No and you do not want to permit counts to be decreased. ● Select Specify Value Now to set the length of time after feature checkout when the checkout can be canceled and the usage count reverted. Specify a number of seconds, minutes, hours, days, or weeks. ● Select Specify Value At Entitlement Time to allow or require the Undo Interval setting later.

Choice	Description
<p>Overdraft</p>	<p>Select the Overdraft option to allow, for example, a specified number of users to run the software package during peak usage times even after the application's license limit has been reached.</p> <p>Usage above the license limit is reported by the FlexNet Manager reporting tool, expressed using the OVERDRAFT license keyword. By viewing this report on actual usage, you can accurately determine your account's license requirements, and purchase any additional licenses that are needed. The Overdraft option is applicable to both certificate and trusted counted licenses.</p> <p>Overdraft is specified as a Maximum value per entitlement line item with Floor and Ceiling values per fulfillment against that line item. From the Maximum list, select one of the following:</p> <ul style="list-style-type: none"> ● Not Used: Select if you want to disable Overdraft support. ● Unlimited: Select if you want to allow unlimited overdrafts. You are then prompted to specify a Floor and Ceiling value. (For metered license models, Unlimited does not require Floor/Ceiling values.) ● Specify # now: Select if you want to specify a number value for the overdraft maximum. After your selection, enter a number in the box to specify the overdraft maximum for a line item. For non-metered models, you are then prompted to specify a Floor and Ceiling value. ● Specify % now: Select if you want to specify a percentage value for the overdraft maximum. The percentage is applied to the entitlement line item count to compute the overdraft maximum for a line item. The computed value is rounded to the <i>nearest</i> whole number (4.2 would be rounded to 4, while 4.8 would be rounded to 5). After your selection, enter a percentage value in the box. For non-metered models, you are then prompted to specify a Floor and Ceiling value. Overdraft licenses are allocated as a percentage of each fulfillment count. ● Specify % at Entitlement Time: Select if you want to specify the number value for the overdraft maximum at the time of entitlement. For non-metered models, you are then prompted to specify a Floor and Ceiling value. For metered models, designate whether or not the Overdraft value is required at entitlement time. <p>If the decision to set the maximum overdraft is deferred until entitlement time (FlexNet Operations user interface or Web services), only an absolute number can be set, not a percentage.</p> <p>See About Overdraft Support for more information.</p>

Choice	Description
<p>Grace Period Days</p>	<p>Select the Grace Period Days option to enable a FlexNet Embedded application to function for a specified number of days, without interruption, after its license has expired.</p> <p>Choose from</p> <ul style="list-style-type: none"> ● Not Used: Grace period is not used for this license model (default). ● Specify Value Now: Specify the grace period, in number of days, for this license model. ● Specify Value At Entitlement Time: To defer the decision about grace period. Users must choose whether or not to add a grace period when they are creating entitlements based on this license model. <ul style="list-style-type: none"> ● Select the Required check box if the user <i>must</i> add a grace period. <p>See About the License Expiration Grace Period for more information.</p>
<p>Auto Provision</p>	<p>For producers who use FlexNet Cloud Licensing Service, FlexNet Operations can automatically generate a Cloud Licensing Service license server for new customer accounts and automatically map new entitlements to an existing Cloud Licensing Service license server for existing customer accounts.</p> <p>Choose from</p> <ul style="list-style-type: none"> ● No: To manually create license servers for entitlements based on this license model. ● Yes: To permit the automatic creation of Cloud Licensing Service license servers. ● Specify Value at Entitlement Time: To defer the decision about auto-provisioning. Users must choose whether or not to use auto-provisioning when they are creating entitlements based on this license model. <p></p> <p>Note - <i>The following limitations exist for auto-provisioned license servers that have entitlements mapped for metered features:</i></p> <ul style="list-style-type: none"> ● <i>License servers cannot be moved to another account.</i> ● <i>Only unused licenses for metered features can be removed using Licenses > Remove Licenses.</i> ● <i>License servers can be made obsolete, which will remove all licenses mapped to the server. However, this is not recommended, because future line items will not be mapped automatically to the auto-provisioned license server.</i>

Choice	Description
Issuer	<p>Issuer of the license: Applicable to all license models.</p> <p>Select Not Used if you do not want to include the ISSUER keyword, or select Specify Value Now to set the value of ISSUER in the license model.</p> <p>Select Specify Value At Entitlement Time or Specify Value At Fulfillment Time to specify the ISSUER value later.</p> <p>In addition to accepting an explicitly specified string, this field can accept, enclosed in curly braces, one of several pre-defined substitution variables or the name of a custom attribute.</p>
Serial Number	<p>Serial number used to identify feature lines: Applicable to all license models.</p> <p>Select Not Used if you do not want to include the SN keyword, or select Specify Value Now to set the value of SN in the license model.</p> <p>Select Specify Value At Entitlement Time or Specify Value At Fulfillment Time to specify the SN value later.</p> <p>In addition to accepting an explicitly specified string, this field can accept, enclosed in curly braces, one of several pre-defined substitution variables or the name of a custom attribute.</p>
Vendor String	<p>Vendor string used to identify feature lines: Applicable to all license models.</p> <p>Select Not Used if you do not want to include the VENDOR_STRING keyword, or select Specify Value Now to specify the value of the VENDOR_STRING in the license model.</p> <p>Select Specify Value At Entitlement Time or Specify Value At Fulfillment Time to specify the VENDOR_STRING value later.</p> <p>In addition to accepting an explicitly specified string, this field can accept, enclosed in curly braces, one of several pre-defined substitution variables or the name of a custom attribute.</p>
Notice	<p>Notice string used to identify feature lines: Applicable to all license models.</p> <p>Select Not Used if you do not want to include the NOTICE keyword, or select Specify Value Now to specify the value of the NOTICE in the license model.</p> <p>Select Specify Value at Entitlement Time or Specify Value at Fulfillment Time to specify the NOTICE value later.</p> <p>In addition to accepting an explicitly specified string, this field can accept, enclosed in curly braces, one of several pre-defined substitution variables or the name of a custom attribute.</p>

Choice	Description
USE SERVER	<p>Applicable only to certificate licenses.</p> <p>USE_SERVER takes no arguments and has no impact on the server. When the application sees USE_SERVER, it ignores everything in the license file except preceding SERVER lines and transfers checkout validation to the vendor daemon.</p> <p>For uncounted features, USE_SERVER is used to force logging of usage by the daemons.</p> <p>You can specify to use or not use USE_SERVER in the license model, or specify whether to use it at the time of entitlement or fulfillment.</p>
Platforms	<p>Applicable to all license models. Usage is limited to the selected platforms.</p> <p>Select No Platform Restrictions if you do not want to specify any platform restrictions.</p> <p>Select Specify Value Now to specify the allowed platforms in the license model.</p> <p>Select Specify Value At Entitlement Time or Specify Value At Fulfillment Time to specify the allowed platforms later.</p> <p>The platforms are selected with check boxes. They are expressed in a license using the PLATFORMS keyword.</p>

Choice	Description
Client Repair Count %	<p>Applicable only to Floating Borrowable and Enterprise Activation license models.</p> <p>A fulfillment record of a vendor daemon contains a fulfill count and a repair count. The fulfill count indicates how many client activations the vendor daemon can perform and the repair count indicates the number of repairs of those client activations the vendor daemon can perform. After the repair count has been used, no more repairs can ever be done against that vendor daemon fulfillment record.</p> <p>FlexNet Operations license model policies affect only direct transactions between FlexNet Operations and a requesting vendor daemon or client application; they do not affect transactions between a vendor daemon and its clients. Therefore, a parameter has been added to license models to restrict the number of repairs that a vendor daemon can perform on activations from one of its fulfillment records.</p> <p>When a vendor daemon makes an activation request to FlexNet Operations, it can request a fulfill count and a repair count against that fulfill count. The Client Repair Count % is applied to the requested fulfill count and compared to the requested repair count: the minimum of the two values is returned to the vendor daemon as the repair count on the fulfillment record.</p> <p>For example:</p> <ul style="list-style-type: none"> • A vendor daemon requests a fulfill amount of 100 and a repair count of 20. Client Repair Count % is 100%. FlexNet Operations returns a repair count of 20. • A vendor daemon requests a fulfill amount of 100 and a repair count of 200. Client Repair Count % is 100%. FlexNet Operations returns a repair count of 100. • A vendor daemon requests a fulfill amount of 100 and a repair count of 100. Client Repair Count % is 0%. FlexNet Operations returns a repair count of 0.
Max Transfers	<p>Applicable only to trusted models. If a license is bound to a license server, this is the number of transfers of a license allowed between vendor daemons.</p>

8. Complete the license model creation process by clicking **Save**, **Complete**, or **Next**:
- Click **Save** to save the license model and remain on the current page.
 - Click **Complete** to save the license model and return the **License Models** page.
 - Click **Next** to save the license model settings and continue by setting up custom license model attributes (if any have been created) or setting policies for the current license model. (See [Setting Up Custom License Model Attributes](#) and [Setting License Model Policies](#).)

After creating a license model, you can continue creating more license models, or start creating features, feature bundles, or products.



Note - After a license model has been saved, the history of its state change can be viewed by clicking the **View History** button.

See Also

[Setting Up Custom License Model Attributes](#)
[Setting License Model Policies](#)
[About Overdraft Support](#)

Copying a License Model

A license model can be copied on the **License Models** page. Typically, you copy a license model as a shortcut in the license model creation process. Rather than adding a license model and manually specifying all the license model's settings, you can copy an existing license model that most closely matches the new license model and rename and customize the copy.



Task *To copy an existing license model*

1. Click **Administer** > **License Models**. This link opens the **License Models** page.
2. Locate the license model to copy, and click **Copy**. This button opens the **Create a License Model** page.
3. Provide a name for the copied license model and change license model settings as necessary. (For information about particular license model settings, see [Creating a License Model](#).)

See Also

[Creating a License Model](#)
[About License Models](#)
[Administering License Models](#)

Deleting a License Model

A license model can be deleted from the **License Models** page. Deleting a license model removes it from FlexNet Operations. You cannot delete deployed license models. Only draft license models and obsolete license models can be deleted.



Task *To delete a license model*

1. Click **Administer** > **License Models**. This link opens the **License Models** page.
2. Locate the license model to delete, and click **Delete**.
3. Confirm your choice by clicking **OK**.

The Producer Portal removes the license model and refreshes the **License Models** page.

See Also

[About License Models](#)
[Administering License Models](#)

Deploying a License Model

A license model can be deployed on the **License Models** page. Deploying a license model makes it active for linking to products and suites. You deploy a license model by changing its state from Draft to Deployed.



Task *To deploy a license model*

1. Click **Administer > License Models**. This link opens the **License Models** page.
2. Locate the license model to deploy, and click **Change State > Deploy**.
3. Confirm your choice by clicking **OK**.

The **License Models** page refreshes to show the new state for the license model you changed.

See Also

[Creating a License Model](#)
[About License Models](#)
[Administering License Models](#)

Printing a License Model

Details about a license model can be printed on the **License Models** page.



Task *To print a license model*

1. Click **Administer > License Models**. This link opens the **License Models** page.
2. Locate the license model to print, and click **Print**.

The **Print** button starts the print process. The exact behavior varies slightly depending on your browser and operating system.

See Also

[Exporting License Models](#)
[About License Models](#)
[Administering License Models](#)

Exporting License Models

License models can be exported on the **License Models** page. Exporting a license model creates a file that can then be imported into a different instance of FlexNet Operations or modified by a separate program. The Export button provides option to create traditional (.jar) export files of all license models or selected license models, with or without their dependencies. For more information, see [Importing and Exporting Entities](#).



Task **To export license models**

1. Click **Administer > License Models**. This link opens the **License Models** page.
2. Locate the license models to export, and click **Export**, and then choose from the following export options:
 - **Selected Items**
 - **Selected Items with their Dependencies**
 - **All Items**
 - **All Items with their Dependencies**

The Producer Portal downloads the export file according to the export option you chose. (The exact behavior depends on the browser and operating system you are using.)

See Also

[Importing and Exporting Entities](#)
[About License Models](#)
[Administering License Models](#)

Employing a Predefined Substitution Variable

The following instructions describe how to use a substitution variable for a license model attribute that corresponds to a supported license string.



Task **To employ a predefined substitution variable in the license model**

1. On the **Create a License Model** page, locate the license model attribute for which you want to use a predefined substitution variable.
2. For the license model attribute, choose **Specify Value Now**.
3. In the field provided, enter the substitution variable you want to use. For example, `{SoldTo.displayName}`. (See [Predefined Substitution Variables for License Strings](#) for a listing of available substitution variables.)
4. Click **Save**.



Note ▪ The license model attributes for license strings can also take custom attributes as substitution variables. See [Custom Attributes in License Strings](#).

See Also

[Predefined Substitution Variables for License Strings](#)
[Creating a License Model](#)

Setting Up Custom License Model Attributes

After setting license model attributes on the **Create a License Model** page, producers can set the custom license model attributes on the **Set Up Custom Attributes** page. The Producer Portal shows this page when you click **Save** and then **Next** on the **Create a License Model** page.

The custom attributes available on the **Set Up Custom Attributes** page depend on the custom license model attributes that have been defined for the license model's license technology. (See [Managing Custom License Attributes](#) for more information.)



Task *To set up custom license model attributes*

1. On the **Create a License Model** page, click **Next**. This button opens the **Set Up Custom Attributes** page.
2. For each custom license model attribute, choose whether to use it in the license model, and the entitlements and licenses that use the license model.
 - If the custom license model attribute is used, set the time at which its value is to be specified. Choose from
 - **Specify Value Now**
 - **Specify Value at Entitlement Time**
 - **Specify Value at Fulfillment Time.**
 - If the custom license model attribute is not used, set it to **Not Used**.
3. Complete setting up custom license model attributes by clicking **Save**, **Complete**, or **Next**.
 - Click **Save** to save your custom attribute settings and remain on the current page.
 - Click **Complete** to save your custom attribute settings and return to the **License Models** page.
 - Click **Next** to save your custom attribute settings and proceed to the **Set Up Policies** page. (See [Setting License Model Policies](#) for more information.)

See Also

[Managing Custom License Attributes](#)
[Creating a License Model](#)
[License Model Attribute Specification Time](#)
[Predefined Substitution Variables for License Strings](#)

Setting License Model Policies

Policies allowed by a license model are configured after the license model attributes are defined. These settings affect all entitlement line items using the license model, and they are applied to activation both from the Producer Portal and from the End-User Portal.

All of these policies are applied per entitlement line item. For activations done with a Web register key, policies are applied per the entitlement line item in the simple entitlement created when the Web register key is redeemed.

Table 22-51 • License Model Policies


Policy	Description
Number of Rehosts	The number of times a customer can rehost a license generated from a particular entitlement item.
Number of Returns	The number of times a customer can return a license generated from a particular entitlement item.
Number of Repairs	The number of times a customer can repair a license generated from a particular entitlement item.
Number of Extra Activations	The number of extra activations allowed for an entitlement line item. This is the additional number of unpurchased copies of a product the customer is allowed to activate.  Important • This option does not apply to FlexNet Embedded licensing models. It is only applicable for FlexNet Publisher-based trusted activations.
Cancel License Policy	If Yes, on a return, a returned license is credited back to entitlements.

Table 22-51 • License Model Policies

Policy	Description
<p>Virtualization Policy</p>	<p>For trusted or embedded license models, determine whether to allow activations on virtual machines. This policy can be set or reset at the license model level or at the entitlement level. Selections are:</p> <ul style="list-style-type: none"> ● Specify Value Now, then click Yes or No ● Specify Value at Entitlement Time <p>If an activation request comes from a virtual machine, FlexNet Operations evaluates the product's virtualization policy. When virtual machine activations are allowed, FlexNet Operations attempts to use the product's virtualization-aware transaction key to configure trusted storage. (If no virtualization-aware transaction key exists, FlexNet Operations reports an error.) When virtual machine activations are not allowed, the activation fails.</p> <p>If an activation request comes from a physical machine, the virtualization policy is not evaluated at activation time.</p> <p>The virtualization policy is supported for licenses generated by FlexNet Publisher version 11.10 or later.</p> <p>For trusted license models, if virtual machine activations are allowed, determine whether to deny license repair if the virtual machine's ACPI Generation ID (UMN5) is changed. This policy can be set or reset at the license model level or at the entitlement level. Selections are:</p> <ul style="list-style-type: none"> ● Specify Value Now, then click Yes or No ● Specify Value at Entitlement Time <p>By default, this is set to Specify Value Now/Yes. Repair requests from physical machines are not impacted.</p> <p>The repair policy is supported for virtual machine licenses generated by FlexNet Publisher version 11.12.1 or later.</p>
<p>Redundant Server Policy</p>	<p>Redundant servers are supported with certificate-based licensing only for floating counted, floating uncounted, and nodelocked counted license models.</p> <p>Do you want to configure redundant servers?</p> <ul style="list-style-type: none"> ● Yes—The license model supports three-server redundancy for failover support. This is a capability available with certificate-based licenses. When you activate the license, you define the three-server host IDs that are a part of this configuration. For more information about three-server redundancy, see the FlexNet Publisher Licensing Toolkit documentation. ● No—The license model does NOT support three-server redundancy.

Table 22-51 • License Model Policies


Policy	Description
Number of Reinstalls	<p>If a customer has reinstalled a host's operating system (for example, due to a system crash), the trusted storage on the host is lost. Activation must be reconfigured. In this case, you can choose to allow the customer to obtain a license without consuming the entitlement count.</p> <p>FlexNet Operations determines whether a user is reconfiguring activation for a specific host using host identifiers like UMN Types 1, 2, 3, and 5 and MID (Machine Identifier).</p> <p>FlexNet Operations tries to match the host using host identifiers according to the FNP client version and host identifiers sent in the request. (Not all activation requests contain the FNP client version or all of the host identifiers.) If the FNP client version is not sent in the request, the order the host identifiers are checked is UMN1, MID, then UMN2. For FlexNet Operations to correctly handle requests from a range of FNP client versions, UMN values are checked from UMN1 to newer UMN versions, and lastly MID is checked.</p> <ul style="list-style-type: none">• You can choose to enforce the same policy for any host identifier received. To configure this, click Specify Value Now and provide a value.• If you want to specify different policies for each host identifier, click Specify Value Now and select Advanced. Then specify the policy for each host identifier.• If you want FlexNet Operations to always provide the license to the user without decrementing count for a reinstall operation, and not enforce any policy, then select Ignore Policy. <p></p> <p>Note • Depending on the machine that issued the request, FlexNet Operations may not receive all identifiers in a given activation request. Refer to the FlexNet Publisher Licensing Toolkit documentation for more information on host identifiers.</p>

Table 22-51 • License Model Policies

Policy	Description
<p>Host ID Policies for Producer Portal</p>	<p>A host ID is an identifier used to uniquely identify a specific machine. A host ID policy is a rule that defines what <i>type of information</i> about the system is used to identify the machine. Example host ID types are host name, IP address, disk serial number, etc. This policy allows you to specify which host ID types (for example, the host name and IP address) are available when activating a license.</p> <p>When you activate a license, you can define a server host ID to ensure the license is used on only on a specific license server. In addition, you can define a nodelocked host ID that allows only a specific client (or user) to check out the feature and run your application.</p> <p>The policies in this section affect activations performed using the Producer Portal. These settings do not apply to activations performed in the End-User Portal. See Host ID Policies for Portal UI to separately configure host ID policies in the End-User Portal.</p> <p>There are two policies for you to define:</p> <ul style="list-style-type: none"> ● Server Host ID Policies—This policy helps publishers restrict host ID types for server hosts. ● Nodelocked Host ID Policies—This policy helps publishers restrict host ID types for nodelocked hosts. <p>For each policy, select a value:</p> <ul style="list-style-type: none"> ● Specify Value Now—Define the list of valid host ID types for this license model. All licenses generated using this license model can use only these host ID types. ● Specify Value at Entitlement Time—Host ID types must be specified at entitlement time. This gives the publisher flexibility to specify different host ID types for different entitlements. ● Ignore Policy—Any host ID type can be used. <p>Notice that host ID types are grouped into families related to their platform/environment: legacy, virtualization-aware (prefixed with PHY, VM, VMW, HPV, or LMB), and cloud-specific (prefixed with AMZN). For more information about the host ID type options displayed, see Special Host ID Types.</p>
<p>Host ID Policies for Portal UI</p>	<p>Publishers can restrict host ID types used during license generation from the End-User Portal using this policy. Refer to Host ID Policies for Producer Portal for information on policy settings. Also see Special Host ID Types for details about the host ID type options displayed.</p>



Note • If users who have override policy permission log in, all host types are displayed to them, regardless of the policy settings, as they can choose to generate licenses for host types not allowed by policy.

Working with Time Zones

Time zone functionality enables publishers to bind license usage to a specified geographic location by identifying the time zone of that region. This makes it possible for the publisher to vary license model pricing based on the geographic location in which the software is used.

At run time, when a license checkout is requested, the time and time zone of the client machine is read and compared to the time zone specified in the license file. If the time zone read from the client machine matches the time zone in the license file, the checkout proceeds as usual. If, however, there is a mismatch between the time zone read from the client machine and the time zone specified in the license file, the checkout request is denied.

The time zone is expressed in a license file using the TZ keyword to define a region within which license usage is permitted. The SERVERTZ time zone setting is preloaded in FlexNet Operations and binds served license usage to the time zone of the license server. However, before Producer Portal users can select any other time zone settings for a license model (served or nodelocked certificate licenses only), those settings must be configured by manually adding time zones in the Producer Portal (menu **Administer** > **Time Zones**). In the Producer Portal, time zone settings are displayed in a single-select drop-down list.

Only users assigned a role with the **View and Manage Configurations** permission can add time zones.



Important - Time zone licensing is intended for use with customers with whom you have a trusted relationship. There is no secure programmatic restriction with time zone licensing functionality: If an end user manually changes the time zone to match the time zone specified in the license certificate, a license can be consumed.

Supported License Types

Time zone-based licensing is supported for licenses used by applications built with FlexNet Publisher version 11.7 or later, and applies to the following certificate-based licenses: floating counted, floating uncounted, and nodelocked counted. Licenses that contain the TZ keyword must be generated by a version 12.7 Vendor Certificate Generator (VCG) that has its version configured as 12.7 in its license generator configuration.

Time zone-based licensing is not available for nodelocked uncounted licenses (because limiting licenses based on their geographic location is not required if an unlimited number of licenses is available).

FlexNet Publisher supports a time zone range from GMT -12:00 to GMT +12:00 (or GMT -12:00 to GMT +14:00 if using FlexNet Publisher 11.15.1 or later).

Supported License Models

Time zone-based licensing is supported for served and unserved license models. When you add a time zone in the Producer Portal, you need to specify (in the FNP Time Zone Type drop-down list) whether the time zone can be used in served, unserved, or served and unserved license models. The following examples illustrate the three options.

Table 22-52 - Selecting a License Model for Time Zone-based Licensing

FNP Time Zone Type	License Model	Example
Server	Served	Time zone (GMT -6.0) Central America, Central Time (Server: true, Client: false) Features can be used only by clients that are residing in the time zone GMT -6:00.
Client	Unserved	Time zone (GMT +9.0) Japan, Korea Standard Time (GMT +9.5) Australian Northern Territory Time, South Australia Time (Server: false, Client: true) Features can be used only by clients that reside in the time zone GMT +9:00 or GMT +9.5.
Both	Served and unserved	Time zone (GMT -7.0) Mountain Standard Time, Mountain Daylight Time (Server: true, Client: true) Features can be used only by clients that reside in the time zone GMT -7:00.

Adding Time Zones

In the Producer Portal on the Add FNP License Time Zone page, time zone settings are displayed in a drop-down list. Each time zone is specified as a value relative to Greenwich Mean Time (GMT). After you add a time zone, this time zone is available for selection when you create a license model for software products that use the FlexNet Publisher toolkit.

Note that during license model creation, you select a time zone from a single-select drop-down list. Therefore, if you want to bind license usage to multiple time zones or a range of time zones, you need to select all the desired time zones (using CTRL+click or Shift+click) when adding them to the FNP Existing Time Zones table.



Task

To add a time zone

1. Click **Administer > Time Zones**. This link opens the Add FNP License Time Zone page.
2. In the **Select FNP Time Zone** list, select the time zone you want to add. To combine multiple time zones or a range of time zones in a single entry, use CTRL+click or Shift+click, respectively.
3. For **FNP Time Zone Type**, select one of the following (see the table [Selecting a License Model for Time Zone-based Licensing](#) for examples):
 - **Server**—Select for served license models.

- **Client**—Select for unserved license models.
 - **Both**—Select for served and unserved license models.
4. Click **Save**. The selected time zone is added to the **FNP Existing Time Zones** table, which lists the time zones that are available for license model creation.

Administering Device and License Server Setup

Producers who use FlexNet Embedded licensing can manage their device series, device model, and server host types using the **Administer** menu.

The topics, below, describe FlexNet Embedded licensing administration concepts and tasks.

Table 22-53 •

Topic	Description
About Device and License Server Setup	Discusses the device series, device model, and server host type concepts and the administration of these elements as well as publishers and identities.
Managing Publisher Identities	Describes how to create publishers and publisher identities, and how to download identity files from the Producer Portal.
Managing Device Series	Covers listing, adding, and editing device series.
Managing Device Models	Covers searching, viewing, creating, and editing device models.
Managing Server Host Types	Covers listing, creating, and editing server host types.
Viewing Request History	Describes how to use the Request History link in the Administer menu to view request history records based on date-time or request ID criteria.
Monitoring the FlexNet Embedded Back Office	Lists exposed FlexNet Embedded back office endpoints for customers who want to verify that it is responding as expected.

See Also

[Managing Devices](#)
[About Device Management](#)

About Device and License Server Setup

Device and license server setup includes the management of publishers, publisher identities, device series, device models, and server host types. For producers who use FlexNet Embedded licensing to manage features and entitlements for intelligent devices, the foundation for devices and license servers that can be created are the device series, device model, and server host type.

Table 22-54 •

Topic	Description
About Device Series and Device Models	Discusses the role of device series and device models for producers who use FlexNet Embedded licensing.
About Server Host Types	Discusses the role of server host types for FlexNet Embedded license servers.
Device Series Attributes	Describes the attributes of device series.
Device Model Attributes	Describes the attributes of device models.
Server Host Type Attributes	Describes the attributes of server host types.
About Publishers and Publisher Identities	Discusses the role of publishers and publisher identities for FlexNet Embedded devices and license servers.

See Also

- [About Device Management](#)
- [Administering Device and License Server Setup](#)
- [Managing Devices](#)

About Device Series and Device Models

To understand the basic concepts of using FlexNet Embedded licensing in FlexNet Operations, use the following example use case where Acme Networks, Inc. is a manufacturer that has created a series of VPN devices that includes three device models.




Figure 22-4: Device Series and Device Models

- **Device Series**—A collection of device models that are physically identical but upgradable in the field through license changes and additional capabilities. In the figure, above, VPN 5000 is an example of a device series.

A device series sets the maximum limits for device capabilities and capacities. In this example, all device models within the VPN 5000 device series can have

- No more than 10,000 simultaneous users
 - No more than 100 Mbps of throughput
 - Redundancy enabled or disabled
- **Device Model**—A basic model for a device that manufacturers use to create a pre-installed license. A pre-installed license defines a set of capabilities within the maximum limits for the device series. The device model with that particular pre-installed license represents a purchasable configuration for a device. In the figure, above, VPN 5005, VPN 5020, and VPN 5050 are all device models and part of the VPN 5000 device series. They each define and represent a different set of basic capabilities.

In this example, the VPN 5050 device model includes

- 5,000 simultaneous users
 - 50 Mbps of throughput
 - Redundancy Enabled
- **Additional Product**—A product you create to represent a license change that grants additional capabilities for a device. In this example, an additional product might include 1,000 simultaneous users and 10 Mbps of throughput.

See Also

- [Managing Device Series](#)
- [Device Series Attributes](#)
- [Managing Device Models](#)
- [Device Model Attributes](#)

About Server Host Types

A server host type works with servers like a device model works with devices; it establishes a default identity and a default host ID type for servers created based on the server host type.

Producer Portal users have a predefined server host type: FLX_SERVER. FLX_SERVER facilitates the creation of servers without the need for new users to define their own server host types, and is associated, by default, with the first identity that the producer creates. Although FLX_SERVER is initially designated as the default server host type, Producer Portal users can later designate any server host type as the default.

See Also

- [Managing Server Host Types](#)
- [Server Host Type Attributes](#)
- [Administering Device and License Server Setup](#)

Device Series Attributes

Device series include the following attributes.

Table 22-55 •

Attribute	Description
Name	A unique value per producer.
Notes	A short description for the device series.
Alias	An optional, alternate name for the device series.

Device series can have a number of capabilities as well. Any capabilities added to the device series express the maximum capabilities and capacities for devices based on the device series.

See Also

- [Managing Device Series](#)
- [About Device Series and Device Models](#)
- [Administering Device and License Server Setup](#)

Device Model Attributes

Device models include the following attributes.

Table 22-56 -

Attribute	Description
Model Name	Model Name must be unique per producer.
Description	An optional description for the device model.
Alias	An optional, alternative descriptive name for the device model.
Default Host ID Type	Default Host ID Type specifies a host ID type for devices based on this device model. Default Host ID Type is used whenever a device of this model is created without specifying a host ID Type.
License Format	The storage format for the pre-installed license and additional capabilities. <ul style="list-style-type: none">● Pre-installed license in file, additional licenses in trusted storage—Any features in the pre-installed product are expressed in a license file while any additional products applied to the device are expressed in trusted storage.● Pre-installed license and additional licenses in file—All features from the pre-installed product and additional products applied to the device are expressed in a license file.● Pre-installed license and additional licenses in trusted storage—All features from the pre-installed product and additional products applied to the device are expressed in trusted storage.
Device Series	The device series that is the parent of the device model.
Identity	The publisher identity for the device model.
Default	A check box that designates the current device model as the default device model. If you create a device without specifying a device model, the default device model is used for that device.
Pre-installed Product	The product that determines the features included in the pre-installed license for devices of this device model type. Pre-installed product settings also determine the license model, license model attributes, and expiration terms used in the pre-installed license for such devices. When a pre-installed product is specified for a device model, that pre-installed product is used for devices based on that device model unless a different product is specified when the device is created.

See Also

- [Managing Device Models](#)
- [About Device Series and Device Models](#)
- [Administering Device and License Server Setup](#)

Server Host Type Attributes

Server host type attributes are similar to device model attributes. These attributes are used when searching, adding, and editing server host types.

Table 22-57 •

Attribute	Description
Server Host Type Name	A unique identifier for the server host type. This value must be unique per producer.
Description	A description for the server host type.
Alias	An alias for the server host type.
Default Host ID Type	Specifies a default host ID type for servers based on this server host type. This host ID type is used if a server is created without specifying a host ID Type. Two special host types appear in the Default Host ID Type attribute: PUBLISHER_DEFINED and EXTENDED. For more information on these host ID types, see the <i>FlexNet Embedded License Server Producer Guide</i> .
Identity	The publisher identity for the license server.
Default	A check box that designates the current server host type as the default server host type. If you create a license server without specifying a server host type, the default server host type is used for that server.
Pre-installed Product	The product that determines the features included in the pre-installed license for license servers of this server host type. Pre-installed product settings also determine the license model, license model attributes, and expiration terms used in the pre-installed license for such license servers. When a pre-installed product is specified for a server host type, that pre-installed product is used for license servers based on that server host type unless a different pre-installed product is specified when the license server is created.

See Also

- [Managing Server Host Types](#)
- [About Device Series and Device Models](#)
- [Administering Device and License Server Setup](#)

About Publishers and Publisher Identities

Software publishers and device manufacturers can be assigned one or more publisher identities. A publisher identity is binary data that contains a publisher or manufacturer name and encryption data. There are two main components to a publisher identity: the server component used to sign licenses, and a client component (containing public keys) that go into the license-enabled code. In addition, back-office identities facilitate FlexNet Embedded trials.

Public keys for your publisher identity were supplied upon purchase of FlexNet Operations. Please consult the FlexNet Publishing Licensing Toolkit documentation for details.

See Also

[Managing Publisher Identities](#)
[Administering Device and License Server Setup](#)
[Managing Devices](#)

Managing Publisher Identities

The topics, below, describe procedures for publisher and identity management.

Table 22-58 •

Topic	Description
Creating a Publisher	Describes how to add a publisher to FlexNet Operations via the Producer Portal.
Creating a Publisher Identity	Shows how to add a publisher identity in the Producer Portal.
Downloading Identity Files	Shows how to download client, client-server, and back-office identity files from the Producer Portal.

See Also

[About Publishers and Publisher Identities](#)
[Administering Device and License Server Setup](#)

Creating a Publisher

You can add a publisher from the **Administer** menu in the Producer Portal.



Task

To create a publisher

1. Click **Administer** > **Publishers**. The Producer Portal opens the List Publishers page.
2. Click **Add Publisher**. The Producer Portal opens the Create a Publisher page.
3. In **Publisher Name**, enter the name of the publisher.
4. In **Notes**, optionally enter a description of the publisher.

5. In **Publisher Keys**, enter the vendor keys used by the publisher.
6. Click **Save**. You can now add publisher identities for the publisher.

See Also

[About Publishers and Publisher Identities](#)
[Administering Device and License Server Setup](#)

Creating a Publisher Identity

You can add identities from the **Administer** menu in the Producer Portal.



Task

To create a publisher identity

1. Click **Administer > Identities**. The Producer Portal opens the List Identities page.
2. On the List Identities page, click **Add Identity**. The Producer Portal opens the Add Identity page.
3. In **Identity Name**, enter the identity name.
4. In **Notes**, optionally enter a description of the publisher identity.
5. In **Signature Algorithm**, select an algorithm and signature strength combination that will be used to generate digital signatures. For example, **TRL_163**.
6. If you have a custom back office identity to upload, click **Browse** and locate the **.bin** file on your local system. (This step is optional, and controls for choosing a file vary depending on the browser you are using.)
7. Click **Save**.



Important - Because it is impossible to re-create an identity—even by entering the same input parameters in the [Creating a Publisher Identity](#) procedure—it is strongly recommended that you save backup copies of your identity files in case it is necessary to restore your FlexNet Operations instance.

To save a backup identity file:

- a. After you successfully create a publisher identity, the **List Identities** page is displayed.
- b. On the **List Identities** page, click the identity that you just created to display its **View Identity** page.
- c. In the **Identity Files** section of the **View Identity** page, click the **Binary File** link below **Download Back Office Identity**.
- d. When you are prompted to save the identity file, choose a unique name to differentiate it from other publisher identity backup files, and save it in a secure location.

To re-create an identity in the new FlexNet Operations instance from a backup identity file:

- a. After you reinstall FlexNet Operations, click **Administer > Identities** to display the **List Identities** page.
- b. On the **List Identities** page, click **Create Identity** to display the **Create Identity** page.
- c. From the **Publisher Name** list, select the publisher that the identity belongs to.

- d. In the **Custom IdentityBackOffice.bin** field of the **Create Identity** page, click **Browse...** to find and select the backup identity file.
- e. Click **Save** to re-create the identity in the restored FlexNet Operations instance.

See Also

[About Publishers and Publisher Identities](#)
[Administering Device and License Server Setup](#)

Downloading Identity Files

The following instruction sets show how to download client, client-server, and back-office identity files. Identity files are a necessary part of your license-enabled code. See your FlexNet Embedded documentation for details.



Task **To download a client identity file**

1. Click **Administer > Identities**.
2. On the List Identities page, click on the identity name for the identity you want to download.
3. Click the Download Client Identity link for the format you want to download.

This file must be compiled into your license-enabled code for client devices.



Task **To download a client-server identity file**

1. Click **Administer > Identities**.
2. On the List Identities page, click on the identity name for the identity you want to download.
3. Click the Download Client Server Identity link for the format you want to download.

This file must be compiled into your license-enabled code for server devices.



Task **To download a back-office identity file**

1. Click **Administer > Identities**.
2. On the List Identities page, click on the identity name for the identity you want to download.
3. Click the Download Back Office Identity link.

See Also

[About Publishers and Publisher Identities](#)
[Administering Device and License Server Setup](#)

Managing Device Series

Producers who use FlexNet Embedded licensing can manage device series from the **Administer** menu. The following topics cover device series management tasks.

Table 22-59 •

Topic	Description
Listing Device Series	Shows how to list all device series for your account.
Viewing a Device Series	Shows how to view a device series from the List Device Series page.
Adding a Device Series	Explains how to create a new device series.
Editing a Device Series	Explains how to edit an existing device series.

See Also

[About Device Series and Device Models](#)
[Administering Device and License Server Setup](#)

Listing Device Series

You can list all the device series available to your account on the Producer Portal.



Task *To list device series*

- Click **Administer > Device Series**.

The Producer Portal opens the List Device Series page. To view an existing device series, click its name in the list.

See Also

[Editing a Device Series](#)
[Managing Device Series](#)
[Administering Device and License Server Setup](#)

Viewing a Device Series

You can view a device series from the List Device Series page.



Task *To view a device series*

- On the List Device Series page, click the name of the device series you want to view.

The Producer Portal opens the View Device Series page for the device name you clicked.

See Also

[Listing Device Series](#)
[Managing Device Series](#)
[Administering Device and License Server Setup](#)

Adding a Device Series

A device series is a collection of device models that are physically identical but upgradable in the field through license changes and additional capabilities. A device series sets the maximum limits for device capabilities and capacities.



Tip - A pre-defined device series, *FLX_CLIENT_SERIES*, is provided for all producers. Those producers who do not require the additional complexity of defining multiple device series and device models can leverage the *FLX_CLIENT_SERIES* instead of creating their own device series.

You can add a device series from the List Device Series page. Use the following steps to add a device series.



Task

To Add a Device Series

1. Click **Add Device Series**. The Producer Portal opens the Add Device Series page.
2. For **Name**, type a unique identifier for the device series.
3. Optionally type any information needed in **Notes**.
4. Optionally, for **Alias**, type a human-readable name for the device series.
5. Optionally, add capabilities to the device series:
 - Under **Add Capabilities**, click the arrow next to the drop-down menu, select a capability, and then click **Add**.
 - Type the maximum units for each counted capability for the device series.



Note - The maximum unit for uncounted capabilities defaults to Enabled.

6. Click **Add Device Series**.

The Producer Portal adds the device series and opens its View Device Series page.

See Also

[About Device Series and Device Models](#)
[Managing Device Series](#)
[Administering Device and License Server Setup](#)

Editing a Device Series

You can edit a device series from its View Device Series page. For an existing device series, you can change the notes, alias, and capabilities values. (The device series name cannot be changed.)



Task

To edit a device series

1. On the View Device Series page, click **Edit** > **Edit this Device Series**. The Producer Portal opens the Edit Device Series page for the current device series.
2. Make any necessary changes.
3. Click **Edit Device Series**.

The Producer Portal saves your changes to the device series and opens its View Device Series page.

See Also

- [Adding a Device Series](#)
- [Managing Device Series](#)
- [Administering Device and License Server Setup](#)

Managing Device Models

Producers who use FlexNet Embedded licensing can manage their device models from the **Administer** menu.

Table 22-60 •

Topic	Description
Searching Device Models	Shows how to search for device models created for your account.
Viewing a Device Model	Shows how to view a device model from the Search Device Models results page.
Creating a Device Model	Describes how to create a new device model.
Editing a Device Model	Explains how to edit an existing device model.

See Also

- [About Device Series and Device Models](#)
- [Administering Device and License Server Setup](#)

Searching Device Models

You can search for device models on the Producer Portal from the **Administer** menu.



Task

To search for device models

1. Click **Administer** > **Search Device Models**. The Producer Portal opens the Search Device Models page.
2. Type search criteria to match the device models you are looking for.
3. Click **Search**.

The Producer Portal finds device models that match your search criteria and lists them on the Search Device Models results page.

See Also

- [About Device Series and Device Models](#)
- [Managing Device Models](#)
- [Administering Device and License Server Setup](#)

Viewing a Device Model

You can view a device model from the Search Device Models page.



Task

To view a device model

- On the Search Device Models results page, click the model name of the device model you want to view. The Producer Portal opens the View Device Model page for the model name you clicked.

See Also

- [Managing Device Models](#)
- [Administering Device and License Server Setup](#)

Creating a Device Model

A device model is a basic model for a device that producers use to create a pre-installed license and, optionally, define a pre-installed product. A pre-installed license can define a set of capabilities, as defined in the pre-installed product's features, within the maximum limits for the device series. The device model with that particular pre-installed license represents a purchasable configuration for a device. If a device model has a certain capability, that capability can be increased to what is defined as the maximum in the series.



Tip - A pre-defined device model, `FLX_CLIENT`, is provided for all producers. Those producers who do not require the additional complexity of defining multiple device series and device models can leverage the `FLX_CLIENT` instead of creating their own device models.

You can create a device model from the **Administer** menu.



Task

To create a device model


1. Click **Administer > Create Device Model**. The Producer Portal opens the Create Device Model page.
2. For **Model Name**, type a unique identifier for the device model.
3. Optionally, for **Description**, type a short description of the device model.
4. Optionally, for **Name**, type a human-readable name for the device model.
5. For **Default Host ID Type**, select a host ID type. Choose from
 - **ETHERNET**

- INTERNET
 - INTERNET_6
 - FLEXID_9
 - FLEXID_10
 - STRING
 - USER
 - VM_UUID
 - CONTAINER_ID
6. For **License Format**, select a license format. Choose from
 - Pre-installed license in file, additional licenses in trusted storage
 - Pre-installed license and additional licenses in file
 - Pre-installed license and additional licenses in trusted storage
 7. For **Device Series**, choose from a list of available device series.
 8. For **Identity**, choose from a list of available publisher identities.
 9. Optionally, select the **Default** check box. If you select the check box, the current device model becomes the default device model for all new devices.
 10. Optionally, add a pre-installed product to the device model.

A pre-installed product defines a set of built-in features for devices based on this device model. (A device model with no pre-installed product results in devices with no built-in features. In this case, all features would be additional features.) To add a pre-installed product

- a. Click **Add**. The Add Pre-Installed Product page opens in a pop-up window.
- b. On the **Add Pre-installed Product** page, click **By Product**. The **Select Product** page opens in another pop-up window. The **Select Product** page lists products with features permitted by the restrictions imposed (if any) by the device model's device series.
- c. On the **Select Product** page, click the option for the pre-installed product and then click **OK**. The **Select Product** window closes and the product name and version of the selected product are shown on the **Add Pre-installed Product** page.
- d. On the **Add Pre-installed Product** page, specify a license model, license model attributes (optional), and expiration terms.

Setting	Description
License Model	Choose a license model for the pre-installed product. License models available are determined by the license models that are linked to the selected pre-installed product.
License Model Attributes	Optionally, provide settings for license model attributes (such as Notice and Vendor String). Any values set here become the default values for devices based on this device model.

Setting	Description
Expiration Terms	Express the Start Date and Expiration for the pre-installed product.  Note ▪ If the year that you want to set is not currently available from the calendar, select the year that is closest to the desired year. This automatically increases the list by 10 years from the year you selected.

- e. Click **Add**. The **Add Pre-installed Product** window closes and you return to the Create Device Model page. Notice that the Pre-installed Product settings show the product you selected as well as its expiration terms.
11. Click **Create Device Model**. The Producer Portal adds the device model you defined and shows its View Device Model page.

See Also

- [About Device Series and Device Models](#)
- [Device Model Attributes](#)
- [Managing Device Models](#)

Editing a Device Model

You can edit a device from its View Device Model page. For an existing device model, you can change its description, its alias, and whether or not it is the default device model. You cannot change its model name, default host ID type, license format, device series, identity, or pre-installed product (if any).



Task

To edit a device model

1. On the View Device Model page, click **Edit** > **Edit this Device Model**. The Producer Portal opens the Edit Device Model page for the current device model.
2. Make any necessary changes.
3. Click **Edit Device Model**. The Producer Portal saves your changes to the device model and opens its View Device Model page.

See Also

- [About Device Series and Device Models](#)
- [Device Model Attributes](#)
- [Managing Device Models](#)

Managing Server Host Types

You can view fulfillment or license information associated with previously-defined hosts.

Table 22-61 •

Topic	Description
Listing Server Host Types	Shows how to list all server host types for your account.
Viewing a Server Host Type	Shows how to view a server host type from the List Server Host Types page.
Creating a Server Host Type	Explains how to create a new server host type.
Editing a Server Host Type	Explains how to edit an existing server host type.

See Also

[About Server Host Types](#)
[Administering Device and License Server Setup](#)

Listing Server Host Types

You can list all the server host types available to your account on the Producer Portal.



Task

To list server host types

- Click **Administer** > **Server Host Types**.

The Producer Portal opens the **Server Host Types** page. To view an existing server host type, click its name in the list.

See Also

[Editing a Server Host Type](#)
[Managing Server Host Types](#)
[Administering Device and License Server Setup](#)

Viewing a Server Host Type

You can view a server host type from the **Server Host Types** page.



Task **To view a server host type**

1. Click **Administer > Server Host Types**. The **Server Host Types** page is displayed.
2. On the **Server Host Types** page, click the name of the host type you want to view.

The Producer Portal opens the **View Server Host Type** page for the host type name you clicked.

See Also

- [Listing Server Host Types](#)
- [Managing Server Host Types](#)
- [Administering Device and License Server Setup](#)

Creating a Server Host Type

You can create a server host type from the **Server Host Types** page.




Task **To create a server host type**

1. Click **Administer > Server Host Types**. The **Server Host Types** page is displayed.
2. Click **Create Server Host Type**. The Producer Portal opens the **Create Server Host Type** page.
3. For **Server Host Type Name**, type a unique identifier for the host type.
4. Optionally, type a description for the server host type in **Description**.
5. Optionally, for **Name**, type a human-readable name for the server host type.
6. For **Default Host ID Type**, select a host ID type. Choose from
 - **ETHERNET**
 - **INTERNET**
 - **INTERNET_6**
 - **FLEXID_9**
 - **FLEXID_10**
 - **STRING**
 - **USER**
 - **VM_UUID**
 - **EXTENDED**
 - **PUBLISHER_DEFINED**
 - **CONTAINER_ID**
7. For **Identity**, choose from a list of available publisher identities.

8. Optionally, select the **Default** check box. If you select the check box, the current host type becomes the default host type for all new license servers.
9. Optionally, add a pre-installed product to the server host type.

A pre-installed product defines a set of built-in features for license servers based on this server host type. (A server host type with no pre-installed product results in license servers with no built-in features. In this case, all features would be additional features.) To add a pre-installed product:

- a. Click **Add**. The **Add Pre-installed Product** page opens in a pop-up window.
- b. On the **Add Pre-installed Product** page, click **By Product**. The **Select Product** page opens in another pop-up window.
- c. On the **Select Product** page, click the option for the pre-installed product and then click **OK**. The **Select Product** window closes and the product name and version of the selected product are shown on the **Add Pre-installed Product** page.
- d. On the **Add Pre-installed Product** page, specify a license model, license model attributes (optional), and expiration terms.

Setting	Description
License Model	Choose a license model for the pre-installed product. License models available are determined by the license models that are linked to the selected pre-installed product.
License Model Attributes	Optionally, provide settings for license model attributes (such as Notice and Vendor String). Any values set here become the default values for devices based on this device model.
Expiration Terms	Express the Start Date and Expiration for the pre-installed product.  Note - If the year that you want to set is not currently available from the calendar, select the year that is closest to the desired year. This automatically increases the list by 10 years from the year you selected.

- e. Click **Add**. The **Add Pre-installed Product** window closes and you return to the **Create Server Host Type** page. Note that the Pre-installed Product settings show the product you selected as well as its expiration terms.
10. Click **Create Host Type**. The Producer Portal adds the server host type and opens its **View Server Host Type** page.

See Also

- [About Server Host Types](#)
- [Managing Server Host Types](#)
- [Administering Device and License Server Setup](#)

Editing a Server Host Type

You can edit a server host type from its **View Server Host Type** page. For an existing host type, you can change its description, its alias, and whether or not it is the default server host type. You cannot change its name, its default host ID type, or its identity.



Task

To edit a server host type

1. Click **Administer > Server Host Types**. The **Server Host Types** page is displayed.
1. On the **Server Host Types** page, click the name of the host type you want to edit. The **View Server Host Types** page is displayed.
2. On the **View Server Host Type** page, click **Edit > Edit Server Host Type**. The Producer Portal opens the **Edit Server Host Type** page for the current host type.
3. Make any necessary changes.
4. Click **Save**. The Producer Portal saves your changes to the server host type and opens its **View Server Host Type** page.

See Also

- [About Server Host Types](#)
- [Managing Server Host Types](#)
- [Administering Device and License Server Setup](#)

Viewing Request History

Use the following instruction sets to view the history of all device and license server requests and, optionally, to filter the request history by date and time or by request ID.



Task

To view the request history

- Click **Administer > Request History**. The Producer Portal opens the **Request History** page.

The **Request History** page shows all requests, by default.

Request history results can be filtered by date or by ID.



Task

To filter the request history results

1. On the **Request History** page, enter any date or ID values you want to use to filter the request history results.
 - **Max Request Time**—Determines how recent the requests included in the request history results are. No requests that occurred after the specified date are included in the results.
 - **Max Request ID**—Limits the request history results according to the request ID. No requests with a request ID number higher than the specified request ID are included in the results. (Only numbers are possible in the **Max Request ID** field, and wildcards are not permitted.)

2. Click **Get History**. The Producer Portal refreshes the **Request History** page to show only the requests that match the filters.

See Also

[Managing Devices](#)
[Administering Device and License Server Setup](#)

Monitoring the FlexNet Embedded Back Office

For customers who want to periodically ping the FlexNet Embedded back office to verify that it is responding as expected, the following endpoint URLs are exposed.



Note - For information about the site ID used in these URLs, see [About Your Site ID in FlexNet Operations Environments](#).

User Acceptance Testing

The UAT environment is a place to perform configuration, integration development, testing, and training.

Use	URL
End-User Portal	https://<siteID>-uat.flexnetoperations.com/flexnet/operationsportal/deviceservices/ping
Producer Portal	https://<siteID>-uat.flexnetoperations.com/flexnet/operationsportal/deviceservices/ping
License Fulfillment Service	https://<siteID>-uat.compliance.flexnetoperations.com/deviceservices/ping
Cloud Licensing Service	https://<siteID>-uat.compliance.flexnetoperations.com/api/1.0/instances/ping
Notification Server	https://<siteID>-ns-uat.flexnetoperations.com/ping

Production (PROD)

The Production instance is for customer entitlement management and licenses, usage, and delivery activities.

Use	URL
End-User Portal	https://<siteID>.flexnetoperations.com/flexnet/operationsportal/deviceservices/ping

Use	URL
Producer Portal	https://<siteID>-fno.flexnetoperations.com/flexnet/operations/deviceservices/ping
License Fulfillment Service	https://<siteID>.compliance.flexnetoperations.com/deviceservices/ping
Cloud Licensing Service	https://<siteID>.compliance.flexnetoperations.com/api/1.0/instances/ping
Notification Server	https://<siteID>-ns.flexnetoperations.com/ping

Working with Transaction Keys

A product is linked with a transaction key only if the product is licensed with a trusted license model. A transaction key is linked with a product at the time the first trusted license model is linked with the product, and can be changed later or overridden for local trials and short code ASRs that use the product. Therefore, **create** at least one transaction key before linking a trusted license model with a product.

Table 22-62 -

Topic	Description
About Transaction Keys	Discusses the use of transaction keys and anchoring with products that use trusted licensing models.
Managing Transaction Keys	Briefly describes the management of transaction keys—including adding, deleting, printing, and viewing the history of transaction keys.
Creating a Transaction Key	Covers the creation of transaction keys in greater detail.
Configuring Anchoring	Explains how to configure anchoring for a transaction key.

Do not define transaction keys if products are licensed only with certificate license models.



Important - Transaction keys cannot be imported using the Product Packaging web service.

About Transaction Keys

Products that use FlexNet licensing with a trusted license model require at least one transaction key. (Do not define transaction keys if products are licensed only with certificate license models.)

A transaction key consists of a trusted ID, a set of transaction key seeds, and a set of bindings. The transaction key determines a FlexNet Publisher Licensing Toolkit Trusted ID configuration. FlexNet Operations provides no direct access to the Trusted ID configuration.

Anchoring Types

Anchors record the deletion and restoration of trusted storage. Available anchors are dependent on the operating system and provide different levels of security. The following table describes the anchoring types on different platforms:



Note - When the transaction key binding type is set to **Virtualization-aware Fingerprint**, only Windows (registry and track zero) and Linux (file based) anchoring are supported.

Table 22-63 - Anchors and Supported Platforms

Anchoring Type	Description
Registry	Windows: Windows registry entry
Track Zero	Windows: Write to track zero
File Based	Macintosh, Solaris, Linux: Anchors written to system files
OSX File Based	Macintosh: Anchors written to system files

Transaction Key Usage

As long as all transaction key seeds are random, no transaction key is intrinsically more secure than another. However, if a Trusted ID configuration is compromised, the transaction key that created that Trusted ID configuration may be compromised.

Consider creating several transaction keys to use for different types of activations or products. For example, one transaction key could be used for regular activations, one for local trials, and one for short code activations. If you support activation of products of different values, consider linking high value, narrowly distributed products with one transaction key and lower value, widely distributed products with a different transaction key.

Linking different transaction keys (and, therefore, different Trusted ID configurations) to different distribution mechanisms or products has a security benefit: high value or securely distributed products are not at risk if the Trusted ID configuration for lower value or less-securely-distributed products is compromised.

Virtualization-Aware Transaction Keys

Similarly, consider using virtualization-aware transaction keys (in addition to default transaction keys) for products that may run on virtual machines. A virtualization-aware transaction key binds to the VMID of a virtual machine and, therefore, results in a binding that is specific to that instance of the virtual machine. (Clones of a virtual machine each have a different VMID.) However, when running on a virtual machine that the licensing client does not recognize as a virtual environment, the licensing client uses the default transaction keys, treating the machine as if it were a physical machine.



Note - Virtualization-aware transaction keys require FlexNet Publisher 11.10 or later.



Important - Transaction keys cannot be imported using the Product Packaging web service.

See Also

- [Working with Transaction Keys](#)
- [Managing Transaction Keys](#)
- [Configuring Anchoring](#)

Managing Transaction Keys

The Transaction Keys page automatically displays recently accessed [transaction keys](#), if applicable. From this page, you can add, delete, print or export transaction keys:

- **Add:** To add a new transaction key, click Add.
- **Save:** To save a transaction key to a file, click Save to file.
- **Delete:** To delete transaction keys, select one or more transaction keys and click Delete.
- **Print:** To print transaction keys, select one or more transaction keys and click Print.
- **Export:** To export transaction keys to a .jar file, select one or more transaction keys and click Export.
- **Revision History:** Shows revisions to transaction keys.

To search transaction keys, select **Transaction Key Name** from the **Search For** choice list, and click **Simple Search**. You can also search for transaction keys based on transaction key name, trusted ID, transaction key seed, product, or keys without products.

See Also

- [About Transaction Keys](#)
- [Working with Transaction Keys](#)

Creating a Transaction Key

Create at least one [transaction key](#) before linking a trusted license model with a product.



Task

To create a transaction key

1. Click **Administer > Transaction Keys**. The Package Products page opens.
2. Click **Add a Transaction Key**. The Create a Transaction Key page opens.
3. Provide values for the following fields. Required fields are indicated with a red asterisk.

Table 22-64 • Transaction Key Fields

Field	Description
Name	Name to uniquely identify this transaction key: The name can contain spaces and can be changed at any time.
Description	Describe the characteristics of this transaction key that make it unique. The description can be changed at any time.

Table 22-64 • Transaction Key Fields

Field	Description
Publisher ID	Select a publisher ID from the drop-down list to associate with this transaction key.
Transaction Key Seeds	<p>Enter 8 unique 32-bit hexadecimal numbers as key seeds. (See example below.) Do not specify the same seeds in a transaction key that are specified in <code>publisher.xml</code>. These key seeds cannot be edited after the transaction key is saved.</p> <p>Example 32-bit Hexadecimal Number: 2e24ec82</p> <p>A single 32-bit hexadecimal number consists of 4 pairs of 2 valid hex digits. Valid hexadecimal digits are 0-9 and A-F.</p>
Binding Type	<p>Select a binding type for the transaction key. Choose from</p> <ul style="list-style-type: none"> ● Default Fingerprint—Binds to supported physical machines and virtual machines. The transaction key is used to configure trusted storage by the physical machine’s characteristics. ● Virtualization-aware Fingerprint—Binds to supported virtual machines only. The transaction key is used to configure trusted storage by the virtual machine’s VMID. <p>For trusted licensing, a product can have up to two transaction keys—one default transaction key and one virtualization-aware transaction key.</p>
Short Code Response Strength	<p>Signature strength of the short code response. Choose from</p> <ul style="list-style-type: none"> ● Low – Short_21 transaction key, for pre-11.5 FNP kits (default option) ● Medium – Short_24 transaction key ● High – Short_26 transaction key

- Decide if you want to use anchoring.
 - **Yes** - Default
 - **No** - Not recommended
- If you are not using anchoring, click **Save** to save the transaction key or click **Add New Transaction Key** to save this transaction key and create a new transaction key. Click **Reset** to reset all the transaction key fields.
- If you are using anchoring, click **Next** to continue with [Configuring Anchoring](#).

See Also

[About Transaction Keys](#)
[Working with Transaction Keys](#)

Configuring Anchoring

If you have decided to configure **anchoring**, the following decisions are presented. Based on these decisions, you are presented with additional decisions and finally a set of attributes to select. The usefulness and ramifications of these attributes can be further explored in FlexNet Publisher Licensing Toolkit documentation.

1. Do you want to use the same anchoring for end users and enterprise users?

License models that apply to end users are retail activation, enterprise activation, and floating borrowable license models. License models that apply to enterprise users are enterprise activation, floating transferable, and floating borrowable license models.

- **Yes** - Default: If this transaction key is associated with a product meant to be activated on both end-user and license server machines, the same anchoring is used.
- **No** - Different anchoring is used for the same product when activated on end-user and license server machines.

2. Do you want to use default anchoring for all supported operating systems?

- **Yes** - Default. The Default anchoring configuration is displayed but not changeable. See the default anchoring configuration in the next table.
- **No** - You are asked to choose anchoring for each supported operating system from the available anchoring.



Note - When the transaction key binding type is set to **Virtualization-aware Fingerprint**, only Windows (registry and track zero) and Linux (file based) anchoring are supported.

OS	Anchoring Type
Windows	Registry
Linux	File Based
Macintosh	File Based and OSX File Based
Solaris	File Based

3. If you answer **Yes** to Question 1 and Question 2, click the **Save** button to save the transaction key. If not, decide whether to use default **anchors** for different types of users on different operating systems.

4. For End Users: Do you want to use default anchoring for supported operating systems?

- **Yes** - Default anchoring for end-user machines displayed.
- **No** - You are asked to choose anchoring for each supported operating system from the available anchoring.

5. For Enterprise Users: Do you want to use default anchoring for supported operating systems?

- **Yes** - Default anchoring for license server machines displayed.

- **No** - You are asked to choose anchoring for each supported operating system from the available anchoring.
6. If you selected **No** to either Question 4 or Question 5, configure the anchors for end users and/or enterprise users, if necessary.
 7. Click the **Save** button to save the transaction key.

See Also

[About Transaction Keys](#)
[Working with Transaction Keys](#)

Working with Application Specification Records (ASRs)

Application Specification Records (ASRs) are transactions codes that use shorter length values to support local trial and short code activation scenarios.

Table 22-65 •

Topic	Description
About Activation Specification Records (ASRs)	Discusses what ASRs are and how they can be used for local trials and short code activations.
Local Trials	Explains how to create, manage, and email ASRs for local trials.
Short Code ASRs	Explains how to create, link, email, and otherwise manage ASRs for short code activation.

About Activation Specification Records (ASRs)

An *Activation Specification Record (ASR)*, which is tied to a product in FlexNet Operations, is a digitally signed XML file describing the licensing terms of a particular product. Local trials and short code activations are implemented by creating an ASR in FlexNet Operations and bundling the ASR with a product. The activation utility for the product uses the bundling ASR to activate a license instead of communicating with the FlexNet Operations server.

The two scenarios supported by FlexNet Operations that use ASRs are local trials and short-code activations.

- A **local trial** is typically a time-limited license intended for use as an evaluation license or an emergency license. The application activation utility reads the license rights from the ASR instead of communicating with the server, and installs the rights in trusted storage. A local trial license cannot be returned, repaired, or rehosted. See [Local Trials](#) for more information.



Note • In the FlexNet Publisher Licensing Toolkit, local trial ASRs are referred to as Embedded Activation.

- A **short-code activation** is one intended for customers that do not have the network connection resources needed for typical activation transactions, and therefore need to activate a product manually, such as over the telephone. Using a short-code ASR, a customer can provide a short request code and receive a short response code (to be typed into the application interface, for example) over the telephone, without the prohibitively long codes used in typical activations. Unlike a local trial license, a license activated with short-code activation can be returned, repaired, and rehosted. See [Short Code ASRs](#) for more information.

See Also

- [Local Trials](#)
- [Short Code ASRs](#)
- [Working with Application Specification Records \(ASRs\)](#)

Local Trials

A local trial is one of two kinds of trusted activation that do not require a real-time response from the FlexNet Operations server when a product is activated. Local trials usually expire after a short time and are used to:

- Allow evaluations of a product (trial)
- Cover a situation in which an application machine loses contact with the license server system machine (emergency)

Local trial licenses cannot be rehosted, returned, or repaired.

Table 22-66 •

Topic	Description
Managing Local Trial ASRs	Briefly discusses viewing, creating, and deleting local trial ASRs.
Creating a Local Trial ASR	Provides a more detailed explanation of creating local trial ASRs.
Emailing a Local Trial ASR	Describes how to email a local trial ASR.

See Also

- [Working with Application Specification Records \(ASRs\)](#)
- [About Activation Specification Records \(ASRs\)](#)
- [Short Code ASRs](#)

Managing Local Trial ASRs

The Local Trials page automatically displays recently accessed local trials for a product.

To view all local trials for a product, click the **Search** button.

From this page, you can perform several tasks. Among them are

- [Creating a Local Trial ASR](#): To add a new local trial, click **Add**.

- Deleting a local trial: To delete local trial ASRs, select one or more local trials and click **Delete**.

Creating a Local Trial ASR

Local Trial ASRs can be created in the Producer Portal on the **Local Trial ASRs** page.



Task

To create a local trial ASR

1. Click **Administer > Local Trial ASRs**. This link opens the **Local Trial ASRs** page.
2. Click **Add**. This button opens the **Create a Local Trial ASR** page.
3. Provide values for the following fields. Required fields are indicated with a red asterisk.

Table 22-67 ▪ Local Trial Fields

Field	Description
Name	Name to uniquely identify this local trial ASR: The name can contain spaces, however, you may not want to include spaces because this name is used to construct the local trial ASR file name.
Trial Type	Select whether this is for a trial or an emergency.
Description	Describe the characteristics of this local trial ASR that make it unique.
Product Details:	Search for a product by name or part number.
- Product Name	To search by product name:
- Product Version	<ul style="list-style-type: none"> • Click By Product. A pop-up window displays a list of products by product name and allows you to search for a specific product.
- Part Number	<ul style="list-style-type: none"> • Search for and select a product. The version number is added to the Product Version field automatically. If the product is mapped to more than one part number, select the correct one from the Part Number drop-down list. <p>To search by part number, click By Part Number. A pop-up window displays a list of products by part number and allows you to search for a specific product.</p> <p>The product name, product version, and part number fields are populated automatically.</p>
Duration	<p>Set Duration so an individual local trial activation expires at a fixed time from the activation date. If you want to set the duration, enter the units of time (Days, Weeks, Months, Years) and enter the number of those units.</p> <p>If unlimited activations per computer are allowed by this local trial ASR, the local trial can be reactivated up until the expiration date.</p>

Table 22-67 • Local Trial Fields


Field	Description
Expiration Date	<p>Set the date that this local trial ASR expires. This is the absolute expiration date of the license, regardless of when it is activated by the client. No new local trial activations can use this ASR after the expiration date, regardless of how many activations per computer are allowed.</p> <p>If a product in the local trial contains a feature with an Expiration Date, set the date.</p> <p>To specify an Expiration Date, click the Calendar button next to the Expiration Date field and click a date.</p>  <p>Note • If the year that you want to set is not currently available from the calendar, select the year that is closest to the desired year. This automatically increases the list by 10 years from the year you selected.</p>
Activations per Computer	<p>Select whether this local trial ASR allows only one or unlimited numbers of activations on a computer. Even if unlimited, no more activations can be done after the Expiration date.</p>
Enable Local Trial Anchors	<p>Select whether or not to enable local trial anchors. Trial anchors serve as additional identifiers for types of trials, and are numbered from 0 to 255, allowing each publisher to support 256 distinct trial types.</p> <p>The number shown here is decremented by 1 each time a trial anchor is assigned to a Flex-enabled product. If a trial anchor is created in error, delete the ASR so its anchor is added back to the pool.</p>
License Model	<p>Select one of the trusted license models that is associated with the selected product. Specify any entitlement-time license model attributes.</p>
Virtualization Keyword	<p>Specify the Virtualization Keyword associated with this Local Trial ASR. This option determines whether or not FlexNet Operations adds a Virtualization Policy to the ASR and, if so, whether the trial uses default or virtualization-aware binding. Choose from</p> <ul style="list-style-type: none"> ● Omitted—No Virtualization Policy added to the ASR. ● Default—Adds a Virtualization Policy to the ASR and specifies default binding for the ASR. ● Virtual—Adds a Virtualization Policy to the ASR and specifies virtualization-aware binding for the ASR. <p>The choice you make here also determines the type of transaction keys available in Transaction Key (below).</p>

Table 22-67 • Local Trial Fields

Field	Description
Transaction Key	Select a transaction key to link with this local trial. If a transaction key is not specified here, the key associated with the product is used. The choice you make for Virtualization Keyword determines which transaction keys are available for selection. When Virtualization Keyword is set to Omitted or Default , only default transaction keys are available. When Virtualization Keyword is set to Virtual , only virtualization-aware transaction keys are available.

4. Click **Save To File** to save the local trial to a file (default file name LocalTrial_namexxxxx.asr) that can be bundled in a software product, click **Email** to [email this local trial ASR](#) to a customer, or click **Complete** to finish working with this local trial ASR.

Emailing a Local Trial ASR

A newly or previously generated local trial ASR can be sent as an email attachment to one or more email addresses. The email attachment is sent as a file, by default called LocalTrial_namexxxxx.asr, where xxxxx is a random number. The default subject line is:

File containing your activation specification record (ASR) attached

The **Ship To Email** field contains the email address where the local trial ASR should be sent. Additional email addresses can be entered, and multiple email addresses are formatted in a comma-separated list that contains no spaces.



Note - If FlexNet Operations is localized with multiple locales, you can select which language to send the email in.

After the email is sent, a confirmation message appears on the page.

See Also

[Configuring the FlexNet Platform Server](#)
[Managing Email and Email Templates](#)

Short Code ASRs

Short code activations are implemented by creating a short code Activation Specification Record (ASR) in FlexNet Operations and bundling the short code ASR with the software product. The ASR is tied to an entitlement in FlexNet Operations.

Table 22-68 -

Topic	Description
About Short Code Activations	Discusses the intended use of short code activations.
Managing Short Code ASRs	Briefly covers viewing, creating, deleting, and saving short code ASRs.
Creating a Short Code ASR	Describes the process of creating a short code ASR in greater detail.
Linking a Short Code ASR with a Bulk Entitlement	Shows how to link a short code ASR with an existing bulk entitlement.
Viewing Short Code Summary	Explains how to view a short code ASR summary.
Emailing a Short Code ASR	Shows how to email a short code ASR.



Note - The amount of information transmitted in short code transactions is much less extensive than ordinary programmatic activations. For example, only part of the UMN is passed. This reduces the security of short code transactions.

See Also

- [Managing Short Code ASRs](#)
- [Creating a Short Code ASR](#)
- [Linking a Short Code ASR with a Bulk Entitlement](#)
- [Viewing Short Code Summary](#)
- [Emailing a Short Code ASR](#)

About Short Code Activations

A short code activation is one intended for customers who do not have the network connection resources needed for typical activation transactions, and therefore must activate a product manually, such as over the telephone.

Using the short code ASR, a customer can provide a short request code and receive a short response code (to be typed into the application interface, for example) over the telephone, without the prohibitively long codes used in typical activations.

You can use either pre-loaded Web Reg Keys or dynamic Web Reg Keys and use the Web Reg Key as Activation ID while generating the short code. If you use dynamic Web Reg Keys, make sure to enable the **Load web reg keys as part of activation for trusted type bulk entitlements?** property (found in **System > Configure > Trusted Storage**).

Unlike local trial licenses, licenses activated with short code activation can be rehosted, returned, or repaired like licenses activated using secure transactions.



Note ▪ The amount of information transmitted in short code transactions is much less extensive than ordinary programmatic activations. For example, only part of the UMN is passed. This reduces the security of short code transactions.

See Also

[Working with Application Specification Records \(ASRs\)](#)
[Short Code ASRs](#)
[Local Trials](#)

Managing Short Code ASRs

The **Short Code ASRs** page displays short code ASRs for all products. You can also search the list of short code ASRs by name, part number, license model, or product.

From this page, you can create or delete short code ASRs, email them, or save them to an XML file.

Instructions for deleting a short code ASR and for saving a short code ASR to a file are below. For instructions on creating a short code ASR, see [Creating a Short Code ASR](#).



Task **To delete a short code ASR**

1. Select the short code ASR you wish to delete and click **Delete**.
2. Click **OK** to confirm deletion.



Task **To save a short code ASR to a file**

1. Select the short code ASR you wish to save and click **Save to File**.
2. Browse to a location to save the file.

See Also

[About Short Code Activations](#)
[Creating a Short Code ASR](#)
[Emailing a Short Code ASR](#)
[Short Code ASRs](#)

Creating a Short Code ASR

Short code ASRs can be created in the Producer Portal on the **Short Code ASRs** page.



Task **To create a short code ASR**

1. Click **Administer > Short Code ASRs**. This link opens the **Short Code ASRs** page.
2. Click **Add**. The **Create a Short Code ASR** page opens.
3. Provide values for the following fields. Required fields are indicated with a red asterisk.

Table 22-69 • Short Code ASR Fields

Field	Description
Name	Name to uniquely identify this short code ASR. The name can contain spaces, however, you may not want to include spaces because this name is used to construct the short code ASR file name.
Description	Describe the characteristics of this short code ASR.
FNP client library version	<div style="border: 1px solid #ccc; padding: 5px; margin-bottom: 10px;"> </div> <p>Note - Not available when bulk entitlement linking is enabled in Trusted Storage system configuration (System > Configure > Trusted Storage).</p> <p>Specify which FlexNet Publisher Licensing client library version the short code ASR is to be used with. Choose from</p> <ul style="list-style-type: none"> ● Pre 11.5? ● Between 11.5 and 11.14? ● 11.14 and above? <p>For FlexNet Publisher client versions 11.14 and above:</p> <ul style="list-style-type: none"> ● A UMN length of 8 to 40 hexadecimal characters is specifiable ● License server ASR is supported ● UMN3 is supported for client and server ASRs
Generate alphanumeric Code?	<div style="border: 1px solid #ccc; padding: 5px; margin-bottom: 10px;"> </div> <p>Note - Only valid for FlexNet Publisher Licensing Toolkit 11.5 and later. Not available when bulk entitlement linking is enabled in Trusted Storage system configuration (System > Configure > Trusted Storage).</p> <p>Specify whether to generate alphanumeric or numeric short code values for both request and response. (Alphanumeric short codes contain letters and numbers and can encode the same information in a shorter string than just numeric codes.) Choose either</p> <ul style="list-style-type: none"> ● Yes. Short codes use alphanumeric values. ● No. Short codes use numeric values.

Table 22-69 • Short Code ASR Fields




Field	Description
Product Details - Product Name - Product Version - Part Number	Search for a product by its name or a part number. To search by product name: <ul style="list-style-type: none"> Click By Product. A pop-up window displays a list of products by product name and allows you to search for a specific product. Search for and select a product. The version number is added to the Product Version field automatically. If the product is mapped to more than one part number, select the correct one from the Part Number drop-down list. To search by part number, click By Part Number. A pop-up window displays a list of products by part number and allows you to search for a specific product. The product name, product version, and part number fields are populated automatically.
Permanent	If the license generated using this keyboard (short code) activation must be permanent, select Yes . If an individual keyboard activation expires, select No , then set Duration or Expiration Date .
Duration	Set either Duration or Expiration Date for an expiring keyboard (short code) activation. <ul style="list-style-type: none"> Set Duration if you want the keyboard activation to expire at a fixed time from the activation date. If you want to set the duration for an expiring keyboard activation, enter the unit of time (Days, Weeks, Months, Years) and enter the number of units.
Expiration Date	If a license generated from this short code must expire on a certain date, enter that date here. To specify an Expiration Date , click the Calendar next to the Expiration Date field and click a date.  <p>Note - If the year that you want to set is not currently available from the calendar, select the year that is closest to the desired year. This automatically increases the list by 10 years from the year you selected.</p> The specific Expiration Date Format to use is defined in the FlexNet Operations system configuration.
License Model	Select one of the trusted license models that is associated with the selected product.
Transaction Key	Select a transaction key to link with this short code ASR. If a transaction key is not specified here, the key associated with the product is used.

Table 22-69 • Short Code ASR Fields

Field	Description
No. of environment aware UMN characters	 <p>Note - Only valid for FlexNet Publisher Licensing Toolkit 11.5 and later. Not available when bulk entitlement linking is enabled in Trusted Storage system configuration (System > Configure > Trusted Storage).</p> <p>Number of environment aware UMN characters to be used in the short code request. A UMN length of 8 to 40 hexadecimal characters is specifiable when FNP client library version is set to FlexNet Publisher client version 11.14 and above. For older versions, UMN values are hard-coded to 8 chars for activation requests and 6 chars for return/repair requests. Environment aware UMN means UMN1 on physical machines and UMN3 on virtual machines.</p>
No. of UMN-2 characters	 <p>Note - Only valid for FlexNet Publisher Licensing Toolkit 11.5 and later. Not available when bulk entitlement linking is enabled in Trusted Storage system configuration (System > Configure > Trusted Storage).</p> <p>Number of UMN2 characters to be used in the short code request.</p>

- Click **Create short code ASR** to save the short code ASR.

After a short code ASR is created, you can use the controls on the **Short Code ASRs** page to email the short code ASR to a recipient or save it to a file for later reference.



Tip - When the Producer Portal is configured to support linking bulk entitlements to short code ASRs, you can click **Next** to show controls for linking the short code ASR to a bulk entitlement.

See Also

- [Managing Short Code ASRs](#)
- [Emailing a Short Code ASR](#)
- [Short Code ASRs](#)

Linking a Short Code ASR with a Bulk Entitlement

When the Producer Portal is configured to support it, short code ASRs can be linked with one or more bulk entitlements.



Important - The ability to link short code ASRs with bulk entitlements is controlled by the **Enable Bulk Entitlement Linking while Creating Short Code** system configuration setting. Administrators can change this setting on the Trusted Storage system configuration page (**System** > **Configure** > **Trusted Storage**).

A *bulk entitlement* represents a large number of individual entitlements (for the reseller channel, for example) for a single product, each of which is expected to be resold to a different customer. The bulk entitlements can already exist or can be created now.

When linking to a bulk entitlement, you must first choose to either create a new bulk entitlement or link an existing bulk entitlement containing the product used to create the short code ASR.

- [Creating a New Bulk Entitlement to Link with this Short Code ASR](#)
- [Linking an Existing Bulk Entitlement](#)

Creating a New Bulk Entitlement to Link with this Short Code ASR

Use the instructions, below, to create a bulk entitlement during the short code ASR creation process.



Task

To create a new bulk entitlement to link with this short code ASR

1. Click **Create a Bulk Entitlement**. The Producer Portal shows controls for bulk entitlement creation.
2. Provide values for the following fields. Required fields are indicated with a red asterisk.

Table 22-70 • Create a Bulk Entitlement to Link to the Short Code ASR

Field	Description
Order ID	ID of an order, perhaps in an ERP system, on which the entitlement is based: FlexNet Operations does not validate or use the Order ID; it is included as a reference to an external order system.
Entitlement ID	The entitlement identifier uniquely identifies the bulk entitlement: Select Auto Generate to let FlexNet Operations assign an entitlement ID, or select User Supplied to enter an entitlement ID of your choice. When you generate an entitlement, you ship an entitlement ID to the customer. The ID is input to FlexNet Operations when generating or activating a license. A customer can also use the entitlement ID to log in to the FlexNet Operations End-User Portal.
Description	Describe the characteristics of this entitlement that make it unique.
Number of Copies	Enter the number of seats that are available per Web register key.
Sold To	Click Search and select the account associated with this entitlement. The Sold To account has the right to activate against this entitlement.
Ship To Email	This field contains the email address where the short code ASR for this entitlement is sent. After the sold-to account is specified, a Search button appears next to the Ship To Email field. Click Search to select an email address for one of the contacts in the sold-to account. Additional email addresses may be entered in a comma-separated list that contains no spaces.

Table 22-70 • Create a Bulk Entitlement to Link to the Short Code ASR

Field	Description
Ship To Mail	Enter the mailing address where the short code ASR for this entitlement is sent. It may be the mailing address of one of the contacts in the account.

3. Click **Save** to save the bulk entitlement. It appears in the list of **Associated Bulk Entitlements**.
 - This bulk entitlement must be deployed before it can be used for short code activations. Deploy the entitlement and load Web register keys from the **Entitle Customers to Licenses** pages.
 - To delete an associated bulk entitlement, select the bulk entitlement and click **Delete**.
4. Click **Next** to view a [summary of short code ASRs](#).

Linking an Existing Bulk Entitlement

Use the instructions, below, to link to an existing bulk entitlement during the short code ASR creation process.



Task To link this short code ASR with one or more existing bulk entitlements

1. Click **Link a bulk entitlement**. The Producer Portal shows controls for finding a bulk entitlement.
2. Click **Search**. The Producer Portal opens the Select Entitlements page in a pop-up window. Bulk entitlements containing the same product as the short code ASR appear in the new window.
3. On the Select Entitlements page, select bulk entitlements to link with the current short code ASR. Click one or more bulk entitlements and then click **OK**. The Producer Portal closes the Select Entitlements page. The selected entitlements appear in the list of **Associated Bulk Entitlements**.



Note • You can also remove bulk entitlements from the Associated Bulk Entitlements list. To remove an associated bulk entitlement, select its check box and then click **Delete**.

4. Click **Next** to view a summary of short code ASRs. (See [Viewing Short Code Summary](#).)



Note • After a short code ASR is linked to a bulk entitlement, it can only be used with web register keys belonging to that bulk entitlement.

See Also

[Managing Short Code ASRs](#)
[Emailing a Short Code ASR](#)
[Short Code ASRs](#)

Viewing Short Code Summary

The short code summary page shows bulk entitlements associated with the selected short code ASR.

Click **Save To File** to save the short code ASR to a file (default file name SC_namexxxxx.asr) that can be bundled in a software product, click **Email License** to email this short code ASR to a customer, or click **Complete** to finish working with this short code ASR.

See Also

[Managing Short Code ASRs](#)
[Emailing a Short Code ASR](#)
[Short Code ASRs](#)

Emailing a Short Code ASR

A newly or previously generated short code ASR can be sent as an email attachment to one or more email addresses. The email attachment is sent as a file, by default called SC_namexxxxx.asr, where xxxxx is a random number. The subject of the ASR email cannot be edited; the subject line is:

File containing your activation specification record (ASR) attached

The **Ship To Email** field contains the email address where the short code ASR is sent. Additional email addresses can be entered, and multiple email addresses are formatted in a comma-separated list that contains no spaces.

After the email is sent, a confirmation message appears on the page.

See Also

[Managing Short Code ASRs](#)
[Short Code ASRs](#)
[Configuring the FlexNet Platform Server](#)
[Managing Email and Email Templates](#)

View and Manage Trusted Activation Requests

You can view and edit information on trusted storage requests made by users.



Task

To manage trusted storage requests

1. Click **Administer > Trusted Activation Requests**.
2. On the **Trusted Activation Requests** page, click **Publisher XML Details** to view the publisher ID, the vendor name, the vendor encryption seeds, and the publisher XML file path. You can search the list of requests by Activation ID or Fulfillment ID.

Table 22-71 • Trusted Storage Requests

Field	Description
Request #	Unique identifier of the trusted storage request.
MID/UMN	Machine ID (MID) and Unique Machine Identifiers (UMNs) of the host that made the request.
Submitted On	Date and time the request was submitted.

Table 22-71 • Trusted Storage Requests

Field	Description
Status Updated On	Date and time the request was processed.
Status	Indicates whether or not the request was processed successfully.
Completed	Indicates whether or not the request was completed.
Processed By	Host that processed the request.
Request Type	Type of trusted storage request.
Activation ID	Activation ID of the request.
Fulfillment ID	Fulfillment ID of the request.

Other options include:

- To view a request in detail, click the request number.
- To download the trusted activation response to a local XML file, select the trusted activation request and click **Download Response**.
- To delete a trusted activation request, select the request to be deleted and click **Delete**.
- To email a response, select the request to be emailed and click **Email Response**.

See Also

- [Configuring Trusted Activation Settings](#)
- [Creating a FlexNet Publisher Licensing Toolkit License Generator \(VCG\) Configuration](#)
- [Local Trials](#)
- [Email Template Types](#)

Managing Email and Email Templates

The Producer Portal can send email messages to your customers and create email templates for your account to use to communicate about new entitlements, or other events.

Email messages can be generated automatically based on certain event triggers or generated manually as needed. Through the **Administer** menu, you can send email messages and also create, modify, or delete email templates.

If FlexNet Operations is running in an Amazon Web Services (AWS) environment, FlexNet Operations can only send emails to addresses and domains that have been verified by AWS beforehand. For more information and procedural information, see section [Verifying Email Addresses and Domains \(AWS Only\)](#).

Table 22-72 -

Topic	Description
<p>Managing Email</p>	<p>Explains how to manage the email messages sent via the Producer Portal. Managing Email includes the following subtopics:</p> <ul style="list-style-type: none"> ● Verifying Email Addresses and Domains (AWS Only) ● Creating a Download Package Notification ● Creating a File Notification ● List Sent Emails ● View Sent Emails ● Resend Email
<p>Managing Email Templates</p>	<p>Shows how to manage your account's email templates. Managing Email Templates includes the following subtopics:</p> <ul style="list-style-type: none"> ● About Email Templates ● Listing Email Templates ● Adding Email Templates ● Viewing Email Templates ● Editing an Email Template
<p>Prevent Blocking of Email Sent by FlexNet Operations</p>	<p>Describes the "best practice" for preventing the rejection of emails that are sent by FlexNet Operations on behalf of an email server belonging to a FlexNet Operations tenant. Steps involve:</p> <ul style="list-style-type: none"> ● Authorizing FlexNet Operations to Send Email on Behalf of the Your Email Server ● Configuring the Email Template

See Also

- [Viewing Emails Related to a Download Package](#)
- [Creating an Email Notification for a Download Package](#)
- [Viewing Emails Related to a File](#)
- [Creating an Email Notification for a File](#)

Managing Email

Use the following topics to manage your account's email messages.

Table 22-73 •

Topic	Description
Verifying Email Addresses and Domains (AWS Only)	Describes how to submit email addresses and domains to AWS for validation.
Creating a Download Package Notification	Describes how to create an email to send to all the customers entitled to a particular download package.
Creating a File Notification	Describes how to create an email to send to all the customers entitled to download a specified file.
List Sent Emails	Describes how to view a list of sent emails.
View Sent Emails	Describes how to get a detailed view of a sent email.
Resend Email	Describes how to resend a previously sent email.



Tip • Email messages can also be sent from other pages in the Producer Portal. For example, you can create notifications from the **View Download Package** page or the **View File** page for a download package or file. You can also send an email from pages like the **Activatable Line Items** page and the **Local Trial ASRs** page.

See Also

[Managing Email and Email Templates](#)
[Managing Email Templates](#)

Verifying Email Addresses and Domains (AWS Only)



Version • This functionality is applicable only to Amazon Web Services (AWS) deployments of FlexNet Operations.

In AWS environments, FlexNet Operations uses AWS technology called Simple Email Service (SES) to send emails. However, SES does not allow FlexNet Operations to send emails to unverified email addresses or unverified domains, which can affect the producer's ability to send emails. To address this, AWS environments contain a tool which enables producers to add verified email addresses or domains to SES. This tool is available in the Producer Portal on the Email/Domain Verification page. You can submit an individual email address or an email domain for verification.



Task **To submit an email address or domain for verification**

1. Click **Administer > Email/Domain Verification**. This link opens the **Email/Domain Verification** page.
2. Choose whether to submit an email address or a domain for verification:

- **To verify an email address**—Under **Email Verification**, enter the email address and click **Submit**.

The status of the verification request is displayed in the **Verified Email/Domain Details** table on the **Email/Domain Verification** page. After you submit the email address for verification, the request is marked as “Pending”. The email address owner receives a link which enables them to verify their email address. Once they have clicked on the link, the status of the verification request is displayed as “Verified”. FlexNet Operations can now send emails to this email address.

- **To verify a domain**—Under **Domain Verification**, enter the domain name and click **Submit**.

The status of the verification request is displayed in the **Verified Email/Domain Details** table on the **Email/Domain Verification** page. After you submit the domain name for verification, the request is marked as “Pending”.

To complete the verification, perform the following steps:

- a. You must add certain information to the DNS record of your domain. To access this information, in the **Verified Email/Domain Details** table, click the relevant **Details** button for your domain verification request. It is recommended that you work with your IT department to configure your company’s DNS records.
- b. Optionally, you can enable DKIM signing for the domain. To do so, add the CNAME records to your company’s domain’s DNS settings. To access the CNAME records, in the **Verified Email/Domain Details** table, click the relevant **Details** button for your domain verification request. Again, it is recommended that you work with your company’s IT department.

After you have updated your company’s DNS settings, AWS will detect the updates within 48-72 hours, and the domain will be marked as “Success” in the **Verified Email/Domain Details** table. FlexNet Operations can now send emails to this domain.

Creating a Download Package Notification

You can create an email notification for one or more download packages on the **Create Update Notification Email by Download Package** page. There, you can enter the download package IDs of the download packages, directly, or search for download packages to which the email pertains.



Important - If FlexNet Operations is running in an Amazon Web Services (AWS) environment, FlexNet Operations can only send emails to addresses and domains that have been verified by AWS beforehand. For more information and procedural information, see section [Verifying Email Addresses and Domains \(AWS Only\)](#).



Tip - To successfully send an email notification for a download package, the default variation of the Update Notification Email template must be active and permitted to send messages (**Will Email Be Sent** set to **Yes**).



Task **To send a download package notification email**

1. Click **Administer > Send Download Package Notification**. This link opens the **Create Update Notification Email by Download Package** page.
2. Identify the download packages for which you want to send an email. Choose whether to enter download package IDs or to search for download packages:
 - Enter download package IDs when you already know their download package IDs or system download package IDs.
 - a. In the download package IDs field, type the download package IDs as a comma-separated list or enter them one per line. Note: If you enter system download package IDs, remember to select the **Use System IDs** check box.
 - b. Click **Create Email**.
 - Search for download packages by entering search criteria if you do not know the IDs of the download packages.
 - a. Type your search criteria into the download package search fields.
 - b. Click **Search**. The Producer Portal shows a list of download packages that match your criteria.
 - c. Select download packages and click **Save**.

The Producer Portal shows the **Distribution List Options** and **Choose an Email Template** settings.

3. Set Distribution List Options for the email message.

Setting	Description
Effective Date	The first date (inclusive) that this entitlement is available to the end user.
Include Expired Entitlements	Determines whether or not to include expired entitlements in the distribution list. By default, only users with active entitlements are included in the distribution list.
Exclude Email Filters	Allows you to identify specific email addresses or email address ranges to exclude from the distribution list. For a single address, type the address in the space provided. For multiple addresses, add a comma-separated list of email addresses in the space provided. Use an asterisk as a wildcard to exclude ranges of email addresses. For example, *@somedomain.com, *.edu .
Limit to Countries	Restricts the delivery of notifications to countries identified by their two-character country code. Use a comma-separated list of country codes to permit delivery to multiple countries. For example, specifying US,FR permits notification delivery to users in the United States and France. When no country codes are specified, FlexNet Operations places no notification delivery restrictions based on the recipient's country.

Setting	Description
Send Separate Email for Each Download Package	Determines whether to send a single message for all download packages (when multiple download packages have been selected) or to send a separate message for each download package.
Send Email Immediately	Determines whether the message is sent as soon as it is created or sent later. If you select this check box, the Producer Portal sends the message as soon as you click Create on this page. Do not use this option if you want to modify the message before it is sent.

4. **Choose an Email Template** variation for this message.

Download Package notification messages use the Update Notification Email template. Select any active variation of that template for the download package notification.



Tip - You can manage your email templates in the Producer Portal. For more information about email templates, see [Managing Email Templates](#).

5. Click **Create**. The Producer Portal creates the email message for the download packages you specified, using the settings you provided, and shows the **View Email** page.
6. On the **View Email** page, click **Edit > Send Email**. The Producer Portal opens the **Send Email** page.
7. On the **Send Email** page, choose to send the email or schedule its delivery.
 - To send immediately, click **Send**.
 - To schedule delivery for a later date,
 - a. Click **Queue to be sent at**.
 - b. Set the Send Date.
 - c. Specify the Send Time (24-hour format).
 - d. Click **Send**.

The Producer Portal sends the email notification.

See Also

[Creating a File Notification](#)

Creating a File Notification

You can create an email notification for customers of one or more files on the **Create Update Notification Email by File** page. There, you can enter the file IDs of the files, directly, or search for files to which the email pertains.



Important - If FlexNet Operations is running in an Amazon Web Services (AWS) environment, FlexNet Operations can only send emails to addresses and domains that have been verified by AWS beforehand. For more information and procedural information, see section [Verifying Email Addresses and Domains \(AWS Only\)](#).



Task **To send a file notification email**

1. Click **Administer > Send File Notification**. This link opens the **Create Update Notification Email by File** page.
2. Identify the files for which you want to send an email. Choose whether to enter file IDs or to search for files:
 - Enter file IDs when you already know their file IDs or system file IDs.
 - a. In the **File IDs** field, type the file IDs as a comma-separated list or enter them one per line. Note: If you enter system file IDs, remember to select the **Use System IDs** check box.
 - b. Click **Create Notification**.
 - Search for files by entering search criteria if you do not know the IDs of the files.
 - a. Type your search criteria into the file search fields.
 - b. Click **Submit**. The Producer Portal shows a list of files that match your criteria.
 - c. Select files and click **Create**.

The Producer Portal shows the **Distribution List Options** and **Choose an Email Template** settings.

3. Set Distribution List Options for the email message.

Setting	Description
Effective Date	The first date (inclusive) that this entitlement is available to the end user.
Include Expired Entitlements	Determines whether or not to include expired entitlements in the distribution list. By default, only users with active entitlements are included in the distribution list.
Downloaded Status	<p>Identifies the accounts and users (members) who are to receive the notification based upon whether or not the file on which the notification is based has been downloaded. Choose from</p> <ul style="list-style-type: none"> ● All Members to deliver the notification regardless of whether or not the file has been downloaded. ● Members with Download Activity to deliver the notification only to users who have downloaded the file. ● Accounts with Download Activity to deliver the notification only to users in an account that has downloaded the file.
Exclude Email Filters	Allows you to identify specific email addresses or email address ranges to exclude from the distribution list. For a single address, type the address in the space provided. For multiple addresses, add a comma-separated list of email addresses in the space provided. Use an asterisk as a wildcard to exclude ranges of email addresses. For example, <code>*@somedomain.com</code> , <code>*.edu</code> .

Setting	Description
Limit to Countries	<p>Restricts the delivery of notifications to countries identified by their two-character country code. Use a comma-separated list of country codes to permit delivery to multiple countries. For example, specifying US,FR permits notification delivery to users in the United States and France.</p> <p>When no country codes are specified, FlexNet Operations places no notification delivery restrictions based on the recipient's country.</p>
Send Separate Email for Each File	Determines whether to send a single message for all files (when multiple files have been selected) or to send a separate message for each file.
Send Email Immediately	Determines whether the message is sent as soon as it is created or sent later. If you select this check box, the Producer Portal sends the message as soon as you click Create on this page. Do not use this option if you want to modify the message before it is sent.

4. **Choose an Email Template** variation for this message.

File notification messages use the Update Notification Email template. Select any active variation of that template for the file notification message.



Note ▪ For localized email template variations, if either the *Text* and *HTML Content* fields or the *Subject* field is left blank, the default locale (US English) variation will be used when sending emails. If the *Subject*, *Text*, or *HTML content* fields are not empty, then the localized template variation will be used.



Tip ▪ You can manage your email templates in the Producer Portal. For more information about email templates, see [Managing Email Templates](#).

5. Click **Create**. The Producer Portal creates the email message for the files you specified, uses the settings you provided, and shows the **View Email** page.
6. On the **View Email** page, click **Edit** > **Send Email**. The Producer Portal opens the **Send Email** page.
7. On the **Send Email** page, choose to send the email or schedule its delivery.
 - To send immediately, click **Send**.
 - To schedule delivery for a later date,
 - a. Click **Queue to be sent at**.
 - b. Set the Send Date.
 - c. Specify the Send Time (24-hour format).
 - d. Click **Send**.

The Producer Portal sends the email notification.

See Also

[Creating a Download Package Notification](#)

List Sent Emails

The Producer Portal allows you to list, view, and resend emails previously sent. Email retention is defined by a retention policy set in the system configuration. To prevent performance issues, sent email has a set number of days that it is retained. See [Configuring the FlexNet Platform Server](#) for more information on setting this configuration.



Important - If FlexNet Operations is running in an Amazon Web Services (AWS) environment, FlexNet Operations can only send emails to addresses and domains that have been verified by AWS beforehand. For more information and procedural information, see section [Verifying Email Addresses and Domains \(AWS Only\)](#).



Note - Email is only retained for a limited number of days as set by the email retention policy. See [Configuring the FlexNet Platform Server](#) for more information.



Task


To list all sent emails

1. Click **Administer > Sent Emails**.

The Producer Portal opens the **Sent Emails** page. By default, the emails are listed by the Sent date (most recent first).

The table contains the following columns:

Table 22-74

Column	Description
Subject	Lists the subject of the email with a link to view the details of the email.  Note - If the template used to create the email has the View Email in Sent history setting turned off, the subject line does not contain a link and the details of the email cannot be viewed, nor can the email be resent.
Email Type	Lists the template used to create the email.
Recipients	List of the recipients on the To list of the email. If there is more than one, they are all displayed in a comma separated list.
Sent	The date the email was sent.



Task *To search sent emails*

1. Use the drop-down menu to select the search criteria. Options include:
 - Recipient
 - Email Type
 - Sent Before
 - Sent After
 - Sent On
2. Enter a value to search on.



Task *To download a list of sent emails*

1. From the **Sent Emails** page, click the  download icon to download a list of the sent emails.
2. The downloaded file is in the format: `SentEmails-timestamp.csv`. For example: **.SentEmails-2017-03-28-12-14-11.csv**. The CSV file contains the following columns:

Table 22-75 •

Column	Description
Email Type	The template used to generate the email.
Subject	The subject of the email.
TO Recipient	The address(es) the email was sent to.
CC Recipient	The address(es) the email was CC'd to.
From	The address that sent the email.
Sent	The timestamp the email was sent.

See Also

- [Editing an Email Template](#)
- [Configuring the FlexNet Platform Server](#)

View Sent Emails

To view an email, click the link in the **Subject** column of the **Sent Email** screen. The **View Sent Email** screen is displayed. Any email created from a template that has the **View Email in Sent history** unselected does not have a link and cannot be viewed.



Important - If FlexNet Operations is running in an Amazon Web Services (AWS) environment, FlexNet Operations can only send emails to addresses and domains that have been verified by AWS beforehand. For more information and procedural information, see section [Verifying Email Addresses and Domains \(AWS Only\)](#).

The **View Sent Email** page lists the **From**, **Reply To**, **Subject**, original **Sent** date and the **Template** used to generate the email. In addition it contains the following::

Table 22-76 -

Column	Description
Type	Lists if the recipient was a “To,” “CC,” or “BCC” recipient.
Email	Lists the email of the recipient.
Account	Lists the account of the recipient.
Sent Language	Lists the language selected for the email. English is the default.
Text Content	Lists the content of the email in ASCII text.
HTML Content	Lists the content of the email with any HTML formatting.

See Also

- [Editing an Email Template](#)
- [Configuring the FlexNet Platform Server](#)

Resend Email



Task **To resend an email**

1. On the **View Sent Email** screen, click the **Resend** button. A pop-up screen appears and lists the **Email To:** field. This is the only editable field. Enter a comma separated list of emails to resend the email to.
2. Click either **Save** to send the email or click **Cancel** to cancel the operation.

Managing Email Templates

The Producer Portal allows you to change the templates that are used by FlexNet Operations to send email to your end users.



Important - If FlexNet Operations is running in an Amazon Web Services (AWS) environment, FlexNet Operations can only send emails to addresses and domains that have been verified by AWS beforehand. For more information and procedural information, see section [Verifying Email Addresses and Domains \(AWS Only\)](#).

The following topics discuss email template management in detail.

Table 22-77 -

Topic	Description
About Email Templates	Discusses email templates, email template concepts, and email template examples.
Listing Email Templates	Shows how to list all the existing email templates. From the List Email Templates page, you can view and edit existing email templates and create new email template variations.
Adding Email Templates	Explains how to add new email template variations.
Viewing Email Templates	Describes how to use the options in the View menu of the View Email Template page.
Editing an Email Template	Describes how to edit email template definitions and email template content.

See Also

[Managing Email and Email Templates](#)
[Managing Email](#)

About Email Templates

The Producer Portal offers you flexibility in editing your email templates. This topic includes short discussions and examples on the following subjects:

- [Email Template Types](#)
- [About Email Template Status Settings](#)
- [Email Template Attributes](#)
- [More About Email Template Content](#)
- [Merge Tag Example: Repeating Blocks](#)
- [Merge Tag Example: Selected Contact](#)
- [Merge Tag Example: Maintenance Line Items](#)
- [Merge Tag Example: Using IF to Display Conditional Text](#)
- [Merge Tag Example: Custom Attributes](#)
- [Merge Tag Example: Custom Attributes for Accounts and Users](#)
- [Merge Tag Example: CHILD-ONLY](#)
- [Special Handling of Alert Email Templates](#)
- [Common Email Template Questions](#)

Email Template Types

The Producer Portal includes a number of email template types for producers to use with FlexNet Operations, such as the Entitlement Certificate template and the Update Notification Email template.

Initially, the set of email templates includes only the default variation of each template type. Producers can choose to edit the default variation—creating new versions of the default email template—or to add new variations of an existing email template type. For some emails that FlexNet Operations sends, users can choose from active variations of an email template prior to sending the message. Multiple active variations of a given email template type can exist, but each email template variation can only have one active version. (See [About Email Template Status Settings](#).)

There are a number of built-in email template types in FlexNet Operations. You can create one or more variations for each email type, but not all template types support the use of custom variations. Custom email template variations are supported for only the following email template types: **Entitlement**, **Entitlement Certificate**, **License**, **Multiple Licenses**, **Consolidated License**, **Multiple Consolidated Licenses**, **Update Notification Email**, and **Product Upgrade Job Email**. The original (and in most cases, the only usable) email template for each type has a variation name of DEFAULT.

Template variations must be set to Active and their Send indicators set to true to be used.

Table 22-78 -

Email Template Types	Notes
Approve Entitlement On Hold (Portal Admin)	<p>Entitlements that are created as the result of transferring an entitlement in the End-User Portal are created with an on-hold status. On-hold entitlements must be approved by a producer user before they are deployed.</p> <p>An email using this template is triggered when a producer user approves the on-hold entitlement from the Producer Portal. The email is sent to the partner or customer user that initiated the transfer.</p> <p>Only the default variation of this template is used by FlexNet Operations.</p>
Consolidated License	<p>FNP certificate or custom technology licenses can be consolidated and downloaded or emailed.</p> <p>An email using this template is triggered when a single consolidated fulfillment is selected and its consolidated license attachment is emailed to the specified email addresses from the End-User or Producer Portal, or via web services (emailConsolidatedLicenses).</p> <p>If multiple active variations of this template exist, producers can choose which email template variation to use for each license technology.</p>
Create Entitlement On Hold (Portal Admin)	<p>Entitlements that are created as the result of transferring an entitlement in the End-User Portal are created with an on-hold status. On-hold entitlements must be approved by a producer user before they are deployed.</p> <p>An email using this template is triggered and sent to the partner or customer user that initiated the transfer when an on-hold entitlement is created in the End-User Portal.</p> <p>Only the default variation of this template is used by FlexNet Operations.</p>

Table 22-78 •

Email Template Types	Notes
<p>Create Entitlement On Hold (Publisher)</p>	<p>Entitlements that are created as the result of transferring an entitlement in the End-User Portal are created with an on-hold status. On-hold entitlements must be approved by a producer user before they are deployed.</p> <p>An email using this template is triggered and sent to a producer email address when an on-hold entitlement is created, to notify the producer that the entitlement is waiting to be approved. The producer email address is specified in the System Configuration setting, System > Configure > FlexNet Operations > General > Email for On-Hold Fulfillments or On-Hold Entitlements.</p> <p>Only the default variation of this template is used by FlexNet Operations.</p>
<p>Entitlement</p>	<p>This email template is used for the body of the email message sent for either a single line item or entire entitlement.</p> <p>An entitlement certificate can be optionally attached to the entitlement email. To <i>always</i> attach an entitlement certificate, use the Entitlement Certificate template (see next entry).</p> <p>To attach an entitlement certificate only to <i>selected</i> entitlement emails, use the Entitlement template. The following conditions must be met:</p> <ul style="list-style-type: none"> • The system configuration setting System > Configure > FlexNet Operations > General > Always Attach Entitlement Certificate in Email must be unselected. • The Attach Entitlement Certificate option must be set to Yes (see also Editing an Email Template Definition). <p>An email using this template is triggered when an entitlement email is sent to the specified email addresses from the End-User or Producer Portal, or via web services (emailActivatableItem or emailEntitlement). See the web services documentation that describes how email addresses can be specified, validated, and filtered in the web service request.</p> <p>If multiple active variations of this template exist, producers can choose which email template variation to use for each license technology or entitlement.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p>Note • <i>One or more variations of both this entitlement template and the entitlement certificate template must be set to active for FlexNet Operations to send out entitlement emails.</i></p> </div>

Table 22-78 •

Email Template Types	Notes
<p>Entitlement Certificate</p>	<p>Entitlement emails as described above can optionally include an entitlement certificate attachment, depending on the system configuration setting which is enabled by default, System > Configure > FlexNet Operations > General > Always Attach Entitlement Certificate in Email. This email template is used for that certificate attachment.</p> <p>An email with an attachment using this template is triggered when an entitlement email is sent to the specified email addresses from the End-User or Producer Portal, or via web services (emailActivatableItem or emailEntitlement) if certificate attachments are enabled. See the web services documentation that describes how email addresses can be specified, validated, and filtered in the web service request.</p> <p>If multiple active variations of this template exist, producers can choose which email template variation to use for each license technology.</p> <div data-bbox="581 793 618 835" style="border: 1px solid black; width: 20px; height: 20px; margin: 10px 0;"></div> <p>Note - One or more variations of both this entitlement certificate template and the entitlement template must be set to active for FlexNet Operations to send out entitlement emails.</p>
<p>Entitlement Split</p>	<p>Partner users can split entitlements to related partner or customer accounts.</p> <p>An email with an attachment using this template is triggered when an entitlement is split from the End-User Portal, or via web services, if the System Configuration is enabled to System > Configure > FlexNet Operations > General > Send Email When New Entitlement is Created after Split. The recipient of the email is the contact that is specified in the target account distributor tier. If no contact is specified in the target tier, no email is sent.</p> <p>Only the default variation of this template is used by FlexNet Operations.</p>
<p>Fulfillment License Set</p>	<p>Fulfillments for some custom technologies, for example manual technologies, are created in FlexNet Operations and license files are generated outside of FlexNet Operations. These fulfillments are created with on-hold status and license files are set later.</p> <p>Emails using this template are triggered when a license generated outside of FlexNet Operations is set on a fulfillment and the Send Email is selected when the license is set and if the System Configuration setting System > Configure > FlexNet Operations > General > Send Email on Set License for On-Hold Fulfillments is enabled. The emails are sent to the ship-to email address on the fulfillment and to the producer email address is specified in the System Configuration setting, System > Configure > FlexNet Operations > General > Email for On-Hold Fulfillments or On-Hold Entitlements.</p> <p>Only the default variation of this template is used by FlexNet Operations.</p>

Table 22-78 •

Email Template Types	Notes
<p>Fulfillment On Hold</p>	<p>Fulfillments for some custom technologies, for example manual technologies, are created in FlexNet Operations and license files are generated outside of FlexNet Operations. These fulfillments are created with on-hold status and license files are set later.</p> <p>An email using this template is triggered and sent to a producer email address when an on-hold fulfillment is created, to notify the producer that the fulfillment is waiting for a license to be set. The producer email address is specified in the System Configuration setting, System > Configure > FlexNet Operations > General > Email for On-Hold Fulfillments or On-Hold Entitlements.</p> <p>Only the default variation of this template is used by FlexNet Operations.</p>
<p>License</p>	<p>This email template is used for the body of the email message sent with a FlexNet Publisher certificate or custom technology license file attachment for a single fulfillment.</p> <p>An email using this template is triggered when one fulfillment is selected and an email is sent to the specified email addresses from the End-User or Producer Portal, or via web services (emailLicense). See the web services documentation that describes how email addresses can be specified, validated, and filtered in the web service request.</p> <p>If multiple active variations of this template exist, producers can choose which email template variation to use for each license technology.</p>
<p>Local Trial</p>	<p>An email using this template is triggered when a user Producer Portal sends a notification for a FlexNet Publisher Local Trial ASR. (For example, a user can click Administer > Local Trial ASRs. Select the check box of the local trial ASR, click Email, and specify email addresses.)</p> <p>Only the default variation of this template is used by FlexNet Operations.</p>
<p>Multiple Consolidated Licenses</p>	<p>FlexNet Publisher certificates or custom technology licenses can be consolidated and downloaded or emailed.</p> <p>An email using this template is triggered when multiple consolidated fulfillments are selected and their consolidated license attachments are emailed to the specified email addresses from the End-User or Producer Portal, or via web services (emailConsolidatedLicenses). See the web services documentation that describes how email addresses can be specified, validated, and filtered in the web service request.</p> <p>If multiple active variations of this template exist, producers can choose which email template variation to use for each license technology.</p>

Table 22-78 •

Email Template Types	Notes
Multiple Licenses	<p>This email template is used for the body of the email message sent with a FlexNet Publisher certificate or custom technology license file attachments for more than one fulfillment.</p> <p>An email using this template is triggered when multiple fulfillments are selected and an email is sent from the End-User or Producer Portal, or via web services (emailLicense). See the web services documentation that describes how email addresses can be specified, validated, and filtered in the web service request.</p> <p>If multiple active variations of this template exist, producers can choose which email template variation to use for each license technology.</p>
Order Media	<p>An email using this template is triggered when a user in the End-User Portal places an order for physical media for files from a selected download package.</p> <p>An email is sent to a producer email address configured in System > Configure > End-User Portal Setup > Downloads Page > Order media request recipient.</p> <p>Only the default variation of this template is used by FlexNet Operations.</p>
Product Upgrade Job Email	<p>Used to send email messages to end users for whom FlexNet Operations has automatically created upgrade line items. (FlexNet Operations only creates these upgrade line items automatically when you have qualifying products and line items and have scheduled the Product Version Upgrade job.)</p> <p>This email template is only triggered by upgrades that result from running the Product Version Upgrade job. It is not triggered for manual upgrades nor for bulk upgrades.</p> <p>For details about the Product Version Upgrade job, see FlexNet Operations Alert Types.</p> <p>Producers set the variation of this email template to be used on the Create a Product page. (Only active variations of this template can be selected. Draft variations are not shown.)</p> <p>For instructions about specifying a variation to use, see Creating a Product.</p>
Reject Entitlement On Hold (Portal Admin)	<p>Entitlements that are created as the result of transferring an entitlement in the End-User Portal are created with an on-hold status. On-hold entitlements must be approved by a producer user before they are deployed.</p> <p>An email using this template is triggered when a producer user rejects the on-hold entitlement from the Producer Portal. The email is sent to a partner or customer user.</p> <p>Only the default variation of this template is used by FlexNet Operations.</p>

Table 22-78 •

Email Template Types	Notes
<p>Renewal Intent for End Customer</p>	<p>Allows an end user to let the producer know they want to renew an entitlement.</p> <p>Emails using this template are triggered when an end user clicks the Request button on the End-User Portal Expiring Entitlements page. Copies of the intent-to-renew email are sent to the end user who initiated the request and also to the producer at the address specified for the system configuration setting, System > Configure > FlexNet Operations > Renewals > Request Renewal Notification Email.</p> <p>Unlike other email templates, Renewal Intent for End Customer does not use the From address. Instead, the value for From is always the email address of the end user who initiates the message.</p> <p>Only the default variation of this template is used by FlexNet Operations.</p>
<p>Renewal Reminder</p>	<p>If a producer has configured and runs the Expired Entitlements job, producers can send Renewal Reminder emails to end users for entitlements that expires in the near future. For an end user to receive these emails, they must have the View Expiring Entitlements permission and subscribe by selecting the Expiring Entitlements Email check box in their user profiles.</p> <p>The frequency that this email is sent to a user is based on Configure > FlexNet Operations > Renewals > Expiring email frequency.</p> <p>Only the default variation of this template is used by FlexNet Operations.</p> <p>See More About the Expiring Entitlements Job for details.</p>
<p>Renewal Reminder for Expired Entitlements</p>	<p>If a producer has configured and runs the Expired Entitlements job, producers can send Renewal Reminder emails to end users for entitlements that have expired. For an end user to receive these emails, they must have the View Expiring Entitlements permission and subscribe by selecting the Entitlements Email check box in their user profiles.</p> <p>The frequency that this email is sent to a user is based on Configure > FlexNet Operations > Renewals > Expired email frequency. Each expired entitlement appears in only one email message.</p> <p>Only the default variation of this template is used by FlexNet Operations.</p> <p>See More About the Expired Entitlements Job for details.</p>

Table 22-78 •





Email Template Types	Notes
Reset Password	<p>Used to send email messages when FlexNet Operations must send a system-generated, temporary password, for logging into either the End-User or Producer Portal.</p> <p>Emails using this template are triggered when new users request a password, when existing active or inactive users forget their password, or when administrators reset a user's password.</p>  <p>Tip • Producers who use single sign-on can prevent FlexNet Operations from sending Reset Password email messages by setting Will Email Be Sent? to No on the Edit Email Template Definition page.</p> <p>Only the default variation of this template is used by FlexNet Operations.</p>  <p>Note • This template must always be set to Active unless single sign-on is used.</p>
Short Code	<p>An email using this template is triggered when a user Producer Portal sends a notification for a FlexNet Publisher Short Code ASR. (For example, a user can click Administer > Short Code ASRs. Select the check box of the short code ASR, click Email, and specify email addresses.)</p> <p>Only the default variation of this template is used by FlexNet Operations.</p>
Trusted Activation	<p>An email using this template is triggered when a user in the Producer Portal sends a notification for a trusted activation request. (For example, a user can click Administer > Trusted Activation Requests. Select the check box of the activation request, click Email response, and specify email addresses.)</p> <p>Only the default variation of this template is used by FlexNet Operations.</p>
Update Notification Email	<p>An email using this template is triggered when a user in the Producer Portal sends a notification email for a download file or download package. (For example, a user can click Administer > Send File Notification or Administer > Send Download Package Notification.)</p> <p>If multiple active variations of this template exist, producers can choose which email template variation to use for each file or download package notification.</p>

Table 22-78 •

Email Template Types	Notes
User Enabled	<p>An email using this template is triggered when a user is reactivated through the UI. If this template has not been configured with any content, an email with default content is sent from FlexNet Operations when the user is reactivated. [Email is currently not sent when user is reactivated using the updateUser web service operation.]</p> <p>Only the default variation of this template is used by FlexNet Operations.</p>  <hr/> <p>Note ▪ <i>This template must always be set to Active unless single sign-on is used.</i></p>
Welcome Email for End Users	<p>Welcome emails are sent to new users. An email using this template is triggered when a customer, partner, or self-registered user is created in the End-User or Producer Portals, or via web services (createUser).</p> <p>Producers who use single sign-on typically make this template inactive. Otherwise, the default variation of this template must be active to support basic functionality of FlexNet Operations.</p> <p>Producers who want to offer trial registration to their end users can create a variation of this template to use specifically for trial registrations. This variation name is then used in the custom content page, based on the TrialRegistration custom content template, in place of <code>{{formData.emailTemplate}}</code>.</p> <p>See About Product Trial Registration Support and About Trial Products for more information.</p>  <hr/> <p>Note ▪ <i>The configuration option Display Password in Welcome Email Template controls whether the <code>[[Password]]</code> merge tag can be used in welcome emails. For more information about this option, see Display Password in Welcome Email Template in General Options.</i></p>
Welcome Email for Producers	<p>Welcome emails are sent to new producer users. An email using this template is triggered when a producer user is created in the Producer Portal or via web services (createUser).</p> <p>Only the default variation of this template is used by FlexNet Operations, and the default variation of this template must be active to support basic functionality of FlexNet Operations.</p>  <hr/> <p>Note ▪ <i>The configuration option Display Password in Welcome Email Template controls whether the <code>[[Password]]</code> merge tag can be used in welcome emails. For more information about this option, see Display Password in Welcome Email Template in General Options.</i></p>

About Email Template Status Settings

Each email template variation can have one or more versions. There are three possible status settings for an email template version:

- **Active**—This version is used by the application to send an email. Only one version (per variation) can be active at any given time.
- **Draft**—This version is in the process of edit and review. Changes have been made but it is not ready to be used as the active version yet. Only one version (per variation) can be in draft status at any given time.
- **Archived**—These versions were once the active or draft version of an email template variation but have been replaced by newer versions. The system keeps these archived versions of your email template variations, and you can always revert to an old version if necessary.

Email template versions are set to Active or Draft status, depending on how they are saved on the Edit Email Template page. There is no separate status-setting control in the Producer Portal.

When you create or edit an email template, you can choose to save it as the Active version or the Draft version of that template variation. If version of the same template variation already exists in the same state, its state becomes Archived. To return an archived email template version to Draft or Active status, open its Edit Email Template page and save it as the Active or Draft template according to your needs.

Email Template Attributes

An email templates consist of

- Email Address:
 - **From:** Whom the email is sent from. The application uses an email alias specific to your site for this.
 - **TO:** The email address that appears as the addressee in the To field of the actual email message.
 - **Reply To:** Typically the same as the From. When the user replies to the email sent out by the system, this is the email address to which the email is sent.
 - **CC:** Who is copied on outgoing emails. Typically used for all people who want to monitor the correct working of your site.
 - **BCC:** Same as CC, except that the recipients are not visible to each other.
- Email Template Content:
 - **Subject:** The subject of the email, you can change this field.
 - **Text Content** and **HTML Content:** The message content of the email. The body of the email can be HTML content or text content. Depending on your preferences, you can use one or the other, or both. When you use HTML, make sure you enter valid HTML. (You can write this content with an external HTML editor and then copy it into the body field). If you choose to fill out both types of content, the recipient, your customer, receives both types of content as well.

More About Email Template Content

The text of the email template body (Text Content and HTML Content) and the Subject can be of two types:

- **Fixed text:** Text that is the same for all the receivers of the email; this is text that you can change.

- Merge tags for user-dependent information:** Information that is different for each receiver of the email, such as first and last name, company name, and order number. In an email template, this information is shown as a *merge tag*. You can place the merge tags in the body and the subject of the email. Before an email is sent, these merge tags are replaced with the data specific to the recipient of the email. When you edit an email template, the Producer Portal shows the merge tags that are available for the current email template in the **Merge Tags List**. (Some email templates require specific merge tags, meaning that you must use the tag at least once in the body of the email.) Not all merge tags are available for all email templates. The list varies by template.



Tip ▪ To avoid errors, copy the merge tag from the Merge Tag List and paste it in the body or subject area. Merge tags must be opened and closed with double square brackets, like this: `[[MERGE_TAG]]`.



Note ▪ The merge tags `[[OrgName]]` and `[[AcctId]]` are functional duplicates, which both return the account ID. They have been retained for backward compatibility.

See the merge tag examples in the following sections.

Merge Tag Example: Repeating Blocks

The Producer Portal allows you to set up repeating blocks of content to, for example, display an order with multiple order lines. To do this, start by creating the content that you need for one order line. Then put the `[[for-each]]` tag at the beginning of this block and the `[[end for-each]]` at the end of the block.

```
[[FOR-EACH TAG="EntitlementLineItem"]]
    [[OrderID]]
    [[OrderID]]
    Activation ID: [[ActivationID]]
    Quantity: [[SeatCount]]
    Start Date: [[StartDate]]
    Expiration: [[ExpirationDate]]
[[END FOR-EACH]]
```

Merge Tag Example: Selected Contact

The SelectedContact merge tag enables users to include additional criteria when defining contact information for an entitlement.

```
[[FOR-EACH TAG="Entitlement" child-only="true"]]
    [[FOR-EACH TAG="ChannelPartners" child-only="true"]]
        [[FOR-EACH TAG="ChannelPartner"]]
            Partner Tier Name: [[PartnerTierName]]
            Acct Display Name: [[Name]]
            Acct ID : [[AcctId]]
            [[FOR-EACH TAG="SelectedContact" child-only="true"]]
                Contact Name: [[ContactName]]
                Firstname: [[Firstname]]
                Lastname: [[Lastname]]
                Country: [[Country]]
                Email: [[Email]]
            [[END FOR-EACH]]
        [[END FOR-EACH]]
    [[END FOR-EACH]]
```

```
[[END FOR-EACH]]
```



Important - Only use the Contact merge tag inside the FOR-EACH entitlement loop to populate the contact. Do not use the Contact merge tag to populate all organization contacts.

Merge Tag Example: Maintenance Line Items

The LinkedMaintenanceLineItems and MaintenanceLineItem merge tags enable users to iterate through maintenance line items.

```
[[FOR-EACH TAG="Entitlement" child-only="true"]]
  [[FOR-EACH TAG="ChannelPartners" child-only="true"]]
    [[FOR-EACH TAG="ChannelPartner"]]
      Partner Tier Name: [[PartnerTierName]]
      Acct Display Name: [[Name]]
      Acct ID : [[AcctId]]
      [[FOR-EACH TAG="SelectedContact" child-only="true"]]
        Contact Name: [[ContactName]]
        Firstname: [[Firstname]]
        Lastname: [[Lastname]]
        Country: [[Country]]
        Email: [[Email]]
      [[END FOR-EACH]]
    [[END FOR-EACH]]
  [[END FOR-EACH]]
  [[FOR-EACH TAG="EntitlementLineItems" child-only="true"]]
    [[FOR-EACH TAG="EntitlementLineItem" child-only="true"]]
      ActivationID: [[ActivationID]]
      Order ID: [[OrderID]]
      Quantity: [[SeatCount]]
      Start Date: [[StartDate]]
      Expiration Date: [[ExpirationDate]]
      Permanent: [[Permanent]]
      Duration :
      Length: [[Length]]
      Units: [[Units]]
      [[FOR-EACH TAG="LinkedMaintenanceLineItems" child-only="true"]]
        [[FOR-EACH TAG="MaintenanceLineItem" child-only="true"]]
          Maintenance Activation Id: [[ActivationID]]
          Order ID: [[OrderID]]
          Quantity: [[SeatCount]]
          Start Date: [[StartDate]]
          Expiration Date: [[ExpirationDate]]
          Permanent: [[Permanent]]
          State: [[Status]]
          [[FOR-EACH tag="Product"]]
            Maintenance Product: [[Name]]
          [[END FOR-EACH]]
        [[END FOR-EACH]]
      [[END FOR-EACH]]
    [[END FOR-EACH]]
  [[END FOR-EACH]]
[[END FOR-EACH]]
```

Merge Tag Example: Using IF to Display Conditional Text

You can make some email content conditional with the use of IF tags.

```
[[IF TAG="OrgType" value="PUBLISHER"]]  
You can now login to your FlexNet Producer account by clicking this link: https://<siteID>-fno-  
uat.flexnetoperations.com/flexnet/operations/logon.do  
[[ELSE]]  
You can now login to your FlexNet End User Portal account by clicking this link: https://<siteID>-fno-  
uat.flexnetoperations.com/flexnet/operationsportal/logon.do  
[[END ELSE]]  
After your initial login, you will be prompted to change this password.  
If you have problems with your account, please contact your Administrator.
```

Best Regards,
Administrator

```
[[END IF]]
```

Using the "no value" clause:

```
[[IF TAG="ServerIDs" VALUENOT=""]]  
Server Ids : [[ServerIDs]]  
[[END IF]]  
[[IF TAG="NodeLockedIDs" VALUENOT=""]]  
Node Locked Ids : [[NodeLockedIDs]]  
[[END IF]]
```

Merge Tag Example: Custom Attributes

If you use custom attributes, you can also use them in your email templates.

Look in the list of Merge Tags and see if you find a tag like this "[[ENT_CA]]". If that tag is in the list of allowed tags, you can add any custom attribute (CA) that is defined on that level in your Email Template (in the example, that would mean you can use Entitlement CAs but not Member CAs).

Because you can have many custom attributes, you must add the CA-ID to properly identify the custom attribute to use. If you do not know the value of the CA-ID, go to the **Custom Attributes** page in the Producer Portal.

Here is the login and password to [[ACCOUNT_NAME]]'s XXXXXXXX Download Center site:

```
[[IF TAG="ENT_CA" CODE="SHIP_LANGUAGE" VALUE="US"]]  
Dear [[DisplayName]]
```

Thank you for your order.

Your Activation ID is: [[ActivationID]]

The Activation ID will be required to login. You will also need the Hostid of the computer with which this license will be associated.

If you have any questions, contact your local XYZ Corporation office.

```
[[END IF]]
```

```
[[IF TAG="ENT_CA" CODE="SHIP_LANGUAGE" VALUE="FR"]]
```

Cher `[[DisplayName]]`,

Nous vous remercions de votre commande.

Votre code d'activation : `[[ActivationID]]`

Le code d'activation est nécessaire pour vous connecter. Vous aurez également besoin de l'adresse d'hôte de l'ordinateur pour lequel la licence sera associée.

Si vous avez des questions, n'hésitez pas à contacter le bureau XYZ corp le plus proche.
`[[END IF]]`

Merge Tag Example: Custom Attributes for Accounts and Users

The Welcome Email templates for end users and producers can also be customized using custom attributes for accounts and users. Look in the Merge Tag List for the tags `[[ACCOUNT_CA]]` and `[[USER_CA]]`.

The following example shows how to use the FOR-EACH tag to iterate through accounts:

Dear `[[DisplayName]]`,

```
[[FOR-EACH TAG="Accounts"]]  
[[FOR-EACH TAG="Account"]]
```

```
[[IF TAG="ACCOUNT_CA" CODE="REGION" VALUE="EU"]]
```

Welcome to XXXXXXXX

```
[[END IF]]
```

```
[[END FOR-EACH]]  
[[END FOR-EACH]]
```

Use this URL to set your password: `[[PASSWORD_RESET_URL]]`
This is your FlexNet account user ID: `[[UserId]]`

You will receive another email with a temporary password and further instructions.

If you have problems with your account, please contact your administrator.

Best Regards,
XXXXXXX



Note • The custom attribute for accounts (tag `[[ACCOUNT_CA]]`) can also be used with the Reset Password, Entitlement, Entitlement Certificate, and Update Notification Email templates.

Merge Tag Example: CHILD-ONLY

Useful when the logical flow of the merge tags in an email template encompasses multiple FlexNet Operations entities (such as entitlements and entitlement line items, accounts and members, and the like) and the same attribute is present in two or more of the entities, CHILD-ONLY, allows you to restrict the evaluation of a condition to a particular entity.

For example, the Status tag exists for both entitlements and entitlement line items. In a FOR-EACH loop of entitlement line items, you might want to force the parser to look for the Status tag only in the entitlement line item rather than allowing it to consider the Status tag value in the parent entitlement.

```
[[FOR-EACH TAG="EntitlementLineItem"]]
[[IF TAG="Status" VALUE="Deployed" CHILD-ONLY="true"]]
...
[[END IF]]
[[END FOR-EACH]]
```

Special Handling of Alert Email Templates

Email templates for alerts are managed differently from most other email templates. While the templates for sending license certificates, entitlement certificates, shortcode ASRs, and so forth are managed through the Producer Portal UI, the alert email templates cannot be customized.

Common Email Template Questions

Here are some common questions about email template management:

- The extra white space (like returns and extra lines) is not showing. Why?
You are writing HTML mail and therefore you must use the
 and <p> tags to create your line breaks and paragraph breaks.
- I want to include an image from my company, how can I do that?
Use the image tag like you would on an HTML page, but ensure that the SRC parameter is a full path that points to the image on your own web server. There is no need to upload these images to FlexNet Operations.
- Why do I still see a merge tag when I preview email template content? I thought all merge tags would be replaced.
There is probably an error in the brackets and therefore the application does not consider it a merge tag and, as a result, leaves it unchanged. Merge tags must be opened and closed with a double square bracket like this: `[[MERGE_TAG]]`.
Read the email carefully and verify that all the merge tags are replaced with preview values. Ensure that the sentences make sense when the merge tags are replaced with real content. If you are satisfied with the result you can save the email template as an Active or as a Draft template.

See Also

[Managing Email Templates](#)
[Managing Email](#)

Listing Email Templates

You can show all email templates by clicking the Email Templates link in the System menu.



Task

To list all email templates

- Click **Administer > Templates**.

The Producer Portal opens the **Templates** page. From this page, you can click on the ID of an email template variation to view or modify that variation. See [About Email Templates](#) for a list of email template types.

See Also

[Viewing Email Templates](#)
[Editing an Email Template](#)
[About Email Templates](#)

Adding Email Templates

You can add email template variations from the **Administer** menu.



Tip - FlexNet Operations supports the use of custom email template variations only for license technology emails.

Before saving an email template variation, you preview the way the final mail message will appear to its recipients. Prior to showing the preview page, the system validates any merge tags included in the email template content. If any invalid merge tags are used, the Producer Portal returns you to the edit page. Otherwise, the preview page shows how the email appears for recipients, replacing the merge tags with preview values.



Task

To add an email template

1. Click **Administer > Add Email Template**. The Producer Portal opens the **Add Email Template Variation** page.
2. For **Variation Name**, type a short description (maximum 25 characters) for this email template variation. The original email template has a variation name of DEFAULT.
3. Choose an **Event Type**. The event type reflects the email template type name shown on the **List Email Templates** page.
4. Click **Add Template**. The Producer Portal opens the **Edit Email Template Content** page.
5. In **Email Template Content**, insert a subject line plus text content or HTML content (or both).

Email template content can make use of merge tags to substitute specific values at the time the email message is generated. For examples of merge tag use, see [About Email Templates](#).



Tip - To avoid errors, copy the merge tag from the Merge Tag List and paste it in the body or subject area. Merge tags must be opened and closed with double square brackets, like this: `[[MERGE_TAG]]`.

6. Click **Validate Template**. The Producer Portal validates the merge tags in the template content and opens the preview page for the email template variation.



Tip - When you click **Validate Template**, the Producer Portal only validates the merge tags in the template content. It does not validate your HTML.

7. Complete the email creation process by saving the variation or returning to the edit page for additional changes.

- Click **Save** to save the current version as the Active template for this email template variation.
- Click **Save Draft** to save the current version as the Draft template for this email template variation.
- Click **Back to Edit** to return to the edit page.

When you save it as a Active template, the Producer Portal uses it for all the email of that variation from then on. If you save it as Draft, you can go back to this version at a later time, change it, and save it as the Active version. If you want to make more changes, click **Back to Edit**.



Tip - The name you provide for Variation Name distinguishes your variation from the default variation of that same template type. When you create or edit a license technology, you can specify customized variations of selected template types to use with that license technology by providing their variation names. See [Creating a License Technology](#).

See Also

[About Email Templates](#)
[Email Template Types](#)
[Editing an Email Template](#)
[Managing Email](#)

Viewing Email Templates

You can view an email template in the Producer Portal and, from its **View Email Template** page, you can also choose to view as an active template, view as draft, or list all versions of that template (archived, active, and draft).

Viewing Active and Viewing Draft

From the **List Email Templates** page, you can view any of the listed template versions by clicking its template ID.

The Producer Portal clearly identifies whether the email template version you are viewing is in draft status versus active status. Links for opening the **View Email Template** page also reflect the template's status. When a template is in draft status, its view page is **View Draft Email Template** and the link in the **View** menu to return to the basic view page is **View Draft**.

When working with email templates, you can return to the basic view page by clicking **View Active** or **View Draft** in the on-page **View** menu.



Task

To view an email template

- From the **View Email Template** page, click **View > View Active** or **View > View Draft**.

The Producer Portal shows the **View Email Template** page for the current email template.

Listing All Versions

There can be a number of versions for each email template variation. A variation can have one active version, one draft version, and several archived versions.



Task **To view all versions of an email template**

- On the **View Email Template** page, click **View > List All Versions**.

The Producer Portal opens the **List All Versions** page. From this page, you can click the status of any listed email template version to open its **View Email Template** page.

See Also

- [About Email Templates](#)
- [Editing an Email Template](#)
- [Listing Email Templates](#)

Editing an Email Template

From the **View Email Template** page, you can edit an email template. Editing is divided into two primary tasks:

- Editing an Email Template Definition
- Editing Email Template Content

Editing an Email Template Definition

An email template's definition includes its email template ID, its email type, its variation name, and its send indicator. Only the variation name and the send indicator are editable on this page.



Task **To edit an email template definition**

1. On the **View Email Template** page, click **Edit > Edit Definition**. This link opens the **Edit Email Template Definition** page.
2. Make email template definition changes as necessary:
 - **Variation Name**—Change the name of the email template variation.
 - **Will Email Be Sent**—Choose whether email messages based on this template is sent.
 - Click **Yes** to enable email messages for this template to be sent. When the send indicator is **Yes**, the Producer Portal's default behavior is to attempt to send the email. (Email can be suppressed on certain transactions or by the preferences of the recipients.)
 - Click **No** to prevent email messages based on this template from being sent.
 - **View Email in Sent history**—Choose whether the content of an email is visible from the **View Sent Email** page of the Producer Portal.
 - Click **Yes** to enable the content to be viewed.
 - Click **No** and only the "To," "CC," and "BCC" fields are visible.



Note ▪ *The **Welcome Email** and **Reset Password** templates default to **No** and, because they contain sensitive password information, are not permitted to be viewed.*

- **Attach Entitlement Certificate** (only available for Entitlement email templates)—Choose whether an Entitlement Certificate should be attached to the email:
 - Click **Yes** to attach an Entitlement Certificate.
 - Click **No** if no Entitlement Certificate should be attached.



Note ▪ The system configuration setting **Attach Entitlement Certificate in Email** (under **System > Configure > FlexNet Operations > General**) must be unselected. If it is selected, the option **Attach Entitlement Certificate** is ignored.

3. Click **Save Template**.

The Producer Portal saves your definition changes to the email template. (No changes occur to the email template's status. Active templates remain active. Draft templates remain in Draft status.)

Editing Email Template Content

Email template content includes the template's subject line, text content, and HTML content.



Task

To edit email template content

1. On the **View Email Template** page, click **Edit > Edit Draft Content** or **Edit > Edit Active Content**. This link opens the **Edit Email Template Content** page.
2. In Email Template Content, insert a subject line plus text content or HTML content (or both).

Email template content can make use of merge tags to substitute specific values at the time the email message is generated. For examples of merge tag use, see [About Email Templates](#).



Tip ▪ To avoid errors, copy the merge tag from the Merge Tag List and paste it in the body or subject area. Merge tags must be opened and closed with double square brackets, like this: `[[MERGE_TAG]]`.

3. Click **Validate Template**. The Producer Portal validates the merge tags in the template content and opens the preview page for the email template variation.



Tip ▪ When you click **Validate Template**, the Producer Portal only validates the merge tags in the template content. It does not validate your HTML.

4. Complete the email creation process by saving the email template or returning to the edit page for additional changes.
 - Click **Save** to save the current template as the Active template for this email template type.
 - Click **Save Draft** to save the current template as the Draft template for this email template type.
 - Click **Back to Edit** to return to the edit page.

When you save it as a Active template the Producer Portal uses it for all the email of that type from then on. If you save it as Draft, you can go back to this version at a later time and change it and save it as the Active template. If you want to make more changes click **Back to Edit**.

See Also

[About Email Templates](#)

[Viewing Email Templates](#)

[Prevent Blocking of Email Sent by FlexNet Operations](#)

Prevent Blocking of Email Sent by FlexNet Operations



Note - This functionality is applicable only to FlexNet Operations deployments in the Revenera-hosted Data Center.

By default, automatically generated email messages are sent directly from the FlexNet Operations email server, with the sender identified as belonging to the **flexnetoperations.com** domain and having an email alias specific to your organization (for example, **abc@flexnetoperations.com**).

The following shows an excerpt from an example email template in FlexNet Operations:

View Email Template

View Edit

Email Template Details

Email Template ID 21882
Event Type Consolidated License
Variation Name VAR-1
View Email in Sent history true

Email Addresses

From abc@flexnetoperations.com
TO
Reply To abc@flexera.com

Figure 22-5: View Email Template page with email address of the **flexnetoperations.com** domain

However, you might prefer that FlexNet Operations send these emails of behalf of your own email server. If you attempt to simply update the email template to specify your email server address as the sender (the From value), the resulting emails can be blocked by the recipient because the From address appears to be masking the originating sender—in this case, FlexNet Operations. To avoid rejected emails, the domain to which your email server belongs must recognize the domain of the FlexNet Operations email server as authorized to send mail on your behalf.

The next sections describe how to authorize and configure FlexNet Operations so that it can successfully send emails on behalf of your email server:

- [Authorizing FlexNet Operations to Send Email on Behalf of the Your Email Server](#)
- [Configuring the Email Template](#)

Authorizing FlexNet Operations to Send Email on Behalf of the Your Email Server

To authorize FlexNet Operations to send email on behalf of your email server, you must set up an SPF (Send Policy Framework) record.

About the SPF Record

The SPF record is a public record that anyone can access. It lists the authorized IP address of each email server belonging to your domain. It also identifies the domain of the FlexNet Operations email server so that it can send email as a third party on behalf of the listed IP addresses. Once the SPF record is created, it is published as a DNS record in the DNS registry.

Then, whenever FlexNet Operations sends an email on your behalf, SPF authenticates the IP address of the "sending" email server (belonging to you) to an authorized IP address in your DNS record. SPF also verifies the originating sender's domain (that is, **flexnetoperations.com**) against the DNS record to verify that FlexNet Operations is indeed authorized as third-party email sender on your behalf. Once all checks clear, the email can reach the recipient.

Setting Up the SPF Record

The following procedure describes how to set up the necessary SPF record.

The record authorizes the FlexNet Operations email server to be a third-party server that can send emails on the behalf the email servers in your domain.



Task

To set up the SPF record

1. Obtain the IP address for each email server on whose behalf FlexNet Operations will send emails to your end users. These email servers must belong to the same domain.
2. Contact your IT department to set up an SPF record for your domain. Once the contents are created (see the next steps), the IT department will publish the record to the DNS registry.
3. To create the file contents, enter the `v=spf1` tag followed by the IP address for an email server:

```
v=spf1 ip4:1.2.3.4
```

To list more than one email server belonging to the same domain, leave a space between each address:

```
v=spf1 ip4:1.2.3.4 ip4:5.6.7.8
```

4. Add an `include` statement (in the format `include:<domain>`) to identify the FlexNet Operations domain. This statement identifies the FlexNet Operations email server as a third party that can send emails on behalf of any of the listed IP addresses.

```
v=spf1 ip4:1.2.3.4 include:flexnetoperations.com
```

5. End the record with an -all tag:

```
v=spf1 ip4:1.2.3.4 include:flexnetoperations.com -all
```

SPF records cannot be over 255 characters in length (and cannot have more than ten include statements).

Configuring the Email Template

As a final step in configuring FlexNet Operations to send emails on your behalf, you must configure the email template to specify your email address.



Task *To configure the email template with your email address*

1. In the Producer Portal, click **Administer** and then select **Templates** in the **Email** section to open the list of available email templates.
2. Click the link for the email template that will be used to generate the email sent to the end user.
The **View Email Template** page is displayed showing details for the selected template.
3. Select **Edit > Edit Definition** to open the **Edit Email Template Definition** page.
4. In the **From** field, enter your email address (ensuring the email server used by this address is identified by an IP address in the SPF file).
5. (Optional) In the **Reply To** field, enter the same email address provided in the previous step (or an email address belonging to the same domain).
6. Save the edits.

Now when an email generated from this template is sent by FlexNet Operations on behalf your email server, the email will successfully reach the recipient. The recipient will see the sender address as your email address.

See Also

[About Email Templates](#)
[Viewing Email Templates](#)

Part 4

Viewing Reports

This part of the FlexNet Operations User Guide includes the following sections:

- [Reporter Quick Reference](#)
- [Managing Web Intelligence Reports](#)
- [Reporter Standard Reports](#)

Reporter Quick Reference

This quick reference section provides a high-level description on how to use the FlexNet Operations Reporter. In the remainder of this document, FlexNet Operations Reporter is also simply referred to as *Reporter*.

The following information helps you get started with the FlexNet Operations Reporter to generate and manage Web Intelligence reports:

- [Accessing the Reporter](#)
- [Using Help](#)
- [Terminology Used in this Guide](#)
- [Data Refresh Intervals](#)

Accessing the Reporter

To get started with the FlexNet Operations Reporter, open the Producer Portal and select **Reports** in the **System** menu, as shown below:




Figure 23-1: Reports Selection on the System Menu

Using Help

Separate help libraries support the Producer Portal, generally, and the Reporter, specifically.

Using Context-Sensitive Reporter Help

Reporter has its own online help library separate from the FlexNet Operations User Guide.



Task

To open the context-sensitive online help

Click the Help button in the main toolbar within Reporter.

When you have questions about Reporter, first consult the online help.

You can also check for answers or log a ticket in the [Reverera Customer Community](#).

FlexNet Operations User Guide

Help for the Producer Portal is available both from the FlexNet Operations User Guide link and directly from certain individual interface elements.

When you have questions about the Producer Portal, first consult the FlexNet Operations User Guide. This user guide is the main manual for the FlexNet Operations Producer Portal.

Terminology Used in this Guide

The following are key terms used in this guide:

- **Web Intelligence**—A reporting tool that is part of the FlexNet Operations Reporter and used for analytical and ad hoc reporting.

- **Reporting data warehouse**—A data warehouse of report-readable FlexNet Operations information refreshed with data from the FlexNet Operations transactions database daily for FlexNet Operations LLM and every four hours for FlexNet Operations ALM. The reports are run against this data warehouse.
- **Reporter universe**—A collection of data from the Reporting data warehouse. For example, a universe could consist of entitlements, device history or usage, served features, or another FlexNet Operations entity type on which to generate a report.

Data Refresh Intervals

Universes are refreshed on a daily basis. The exception are the following universes, which are refreshed every four hours, starting at 00:00 Coordinated Universal Time (UTC):

- ALM Accounts And Users
- ALM Device Addon History
- ALM Device History
- ALM Entitlement
- ALM Fulfillments



Important - *The daily refresh of the universes (with the exception of the universes listed above) finishes at 5:00 AM Pacific Time. It is recommended that you do not schedule a report to run between 00:00 and 5:00 AM Pacific Time, to avoid conflicts between the scheduled report running and the refresh.*

Managing Web Intelligence Reports

A Web Intelligence report helps you to understand trends and root causes with easy-to-use tools for ad hoc queries, reporting, and analysis.

This section covers what you need to get started to use Reporter and explains how to create Web Intelligence reports. The next chapter covers how to run standard reports.

Topic	Content
Folder and Document Organization	Covers the initial requirements for using Reporter and explains a number of basic concepts and common tasks.
Running a Standard Report	Explains how to run the pre-built reports included in Reporter.
Creating a Web Intelligence Report	Describes how to create a Web Intelligence report based on information currently in the Reporting data warehouse.
Modifying the Report	Describes how to modify the Web Intelligence report, including inserting cells and charts, applying formatting, and using customized variables.
Viewing the History of Reports	Covers how to display a history of report instances.
Refreshing Reports	Explains the options for refreshing a report.
Exporting Reports in Different Formats and Purpose	Describes how to export a complete document or one/more reports to a text file, a PDF, an Excel spreadsheet, a CSV file, or a CSV archive.
Scheduling Reports	Shows how to schedule and then email report documents.
Enabling Reports from Legacy Reporter	Discusses how to enable reports that have been automatically copied from the legacy Reporter.

Folder and Document Organization

The Reporter interface has the following tabs:

- The **Home** tab lists your recently viewed documents and recently run reports, as well as unread messages (see [Accessing Recent Documents and Messages](#)).
- The **Documents** tab lists all your documents and messages, organized into folders (see [Navigating Folders and Documents](#)).

Accessing Recent Documents and Messages

The default Home tab features modules that enable you to better manage the documents you work with most. The default Home tab layout contains the following modules:

- **My Recently Viewed Documents**—Shows the last ten documents that you have viewed recently. The list is sorted by view date with the most recently viewed document at the top.
- **Unread Messages in My Inbox**—Shows the last ten unread messages in your BI Inbox.
- **My Recently Run Documents**—Shows the last ten documents in the repository that you scheduled or ran recently along with the status of each document instance. You can view successful instances or details of failed instances by clicking the instance link.
- **Unread Alerts**—Alerts display the daily refresh date and time. No other alerting functionality is supported in this implementation.
- **My Applications**—Provides quick access to applications within the BI launch pad.

Navigating Folders and Documents

In Reporter, a document is a query and its results. Documents are organized into folders.

Personal folders are in the **My Documents** drawer; public folders are in the **Folders** drawer.

Expand or collapse folders by clicking **+** or **-**.

Click a folder name to show its contents in the right pane.




Figure 24-1: Navigating the folders and documents.

Default Folders in the “My Documents” Drawer

- **My Favorites** folder
 - Save personal documents here.
 - Organize documents by creating sub-folders by choosing from drop-down: **New > Folder** or right-click folder name > **New > Folder**.
- **My Favorites/~Webintelligence** folder
 - Drafts of documents are saved automatically here.
 - Can be removed, but will re-appear next time a document is created.
- **Inbox** stores documents that have been sent to you via Reporter's **Send To** functionality.
- **My Alerts**—Alerts display the daily refresh date and time. No other alerting functionality is supported in this implementation.
- **Subscribed Alerts**—Alerts display the daily refresh date and time. No other alerting functionality is supported in this implementation.
- **Personal Categories** offer an alternative way to organize your objects. When you save a report, you can assign it to a category, and the report is then listed under its respective category.

Default Folders in the “Folders” Drawer

- **Shared - Company Name**
 - Reports saved here can be accessed by other users in your organization.
 - Only the owner/creator of the report can delete or save the same named document to this folder.
 - You cannot schedule a report from the shared folder.

- **ALM Standard Reports** (FlexNet Operations ALM only) This folder contains sample documents created by Revenera for ALM.
- **Standard Reports** (FlexNet Operations LLM only) This folder contains sample documents created by Revenera for LLM.



Note - Some customers using FlexNet Operations ALM might also see the **FlexNet Standard** folder. This folder contains legacy reports which should not be run.

Document Organization and Actions

Right-click an object for a list of actions. This menu includes commands in the **New**, **Organize** and **Send** submenus.




Figure 24-2: Menu options.



Note - The **Local Document** option (available under **New**) is not supported.

Creating a Folder

You can create additional folders to organize your objects. You cannot add folders in the **Standard Reports** or **ALM Standard Reports** folders in the **Folders** drawer.



Task **To create a folder**

1. On the **Documents** tab, navigate to the location where you want to create a folder:
 - To create a personal folder, expand the **My Documents** drawer, and click **My Favorites**.
 - To create a public folder, expand the **Folders** drawer.
2. On the **New** menu, click **Folder** (or right-click and select **New > Folder**).
3. When prompted, enter a name for the new folder.
4. Click **OK**.

Deleting a Folder

You cannot delete folders from the **Standard Reports** or **ALM Standard Reports** folders in the **Folders** drawer.



Task **To delete a folder**

1. On the **Documents** tab, locate and select the folder that you want to delete.
2. On the **Organize** menu, click **Delete** (or right-click and select **Organize > Delete**).
3. When prompted, confirm that you want to delete the folder.

Running a Standard Report

Standard reports are sample documents (pre-defined queries) created by Revenera. For a list of standard reports, see [Reporter Standard Reports](#).



Task **To run a standard report**

1. In the panel on the left side, click **Folders** to expand it.
2. Click **+** to expand **Public Folders**.
3. Click **ALM Standard Reports** (for FlexNet Operations ALM) or **Standard Reports** (for FlexNet Operations LLM) to view a list of available standard reports.



Note - Some customers using FlexNet Operations ALM might also see the **FlexNet Standard** folder. This folder contains legacy reports which should not be run.

4. Double-click the document name to run.
5. Enter required prompts. The **Prompts** window pops up if there are required prompts to fill in for the report. Click each prompt and enter appropriate values.
6. Click **Run Query**. (If there were no prompts, this step is skipped.)

The document opens with the requested data.

Creating a Web Intelligence Report

The following procedure creates a Web Intelligence report once you open FlexNet Operations Reporter. The report is based on information currently in the Reporting data warehouse.


- [Steps to Create a Web Intelligence Report](#)
- [Building a Query](#)
- [Controlling the Retrieval of Duplicates](#)
- [Opening a Report in Reading or Design Mode](#)

Steps to Create a Web Intelligence Report




Task *To create a Web Intelligence report*


1. Click **Applications** and select **Web Intelligence**.



2. Click the **New** icon to create a document.




3. Select the **Universe** data source, and then click **OK**.




4. From the Universe dialog box, select a universe on which to create the report, and click **OK**. (For a brief description of a universe, click its entry in the list to view the description at the bottom of the dialog.)



Note • The Revision and Folder columns on the Universe panel are mainly used by development teams.



The Query Panel is displayed.




Building a Query




Task To build a query using the selected universe

1. Drag and drop dimensions and measures that you want to include in the query from the universe into the Result Objects pane. Note the following:
 - **Dimensions** are qualitative and do not total a sum. A dimension object is the object being tracked; in other words, it can be considered the focus of the analysis. A dimension can be an object such as Service, Price, or Customer. Dimension objects retrieve the data that will provide the basis for analysis in a report. Dimension objects typically retrieve character-type data (customer names, resort names, etc.), or dates (years, quarters, reservation dates, etc.)
 - **Measures** are numerical values that mathematical functions work on. For example, a sales revenue column is a measure because you can determine a total or average its data.



2. In the Results Objects pane, select the objects on which you want to define query filters, and drag them to Query Filters pane.



3. On the Query Filters pane, enter a **Constant** against the selected object.



Important • In general, pre-built filters—such as those that are in standard reports, indicated by a yellow funnel icon —use the * wildcard (unless the filter description mandates a different wildcard character). Non pre-built filters (filters created from scratch) use the % wildcard.

4. On the Data Preview pane, click **Refresh** to preview the data for the selected objects.
5. Click **Run Query** to create and view the report of the selected object.


Controlling the Retrieval of Duplicates

By default, the option to retrieve duplicates is enabled. However, you can turn off this option.




Task **To disable the retrieval of duplicate records for a report**

1. On the Query Panel, click **Query Properties**.



- 2. In the Query Properties dialog box, clear **Retrieve duplicate rows** to avoid duplicate records.



- 3. Click **OK**.

Opening a Report in Reading or Design Mode

When you open an existing Web Intelligence report, you can view it in either Reading mode or Design mode.

Reading Mode

This mode allows you to view the existing report, search its content, and monitor changes in the report.




Figure 24-3: Reading Mode

You can also use the left panel and tool bar in the Reading mode.

Design Mode

Design mode allows you to add, delete objects in a report, apply conditional formatting, apply formulas in report, create variables, and more. Two types of Design mode are available:

- **Design mode (Structure only)**—Allows you to view and modify only the structure of the report. All the changes that you make in this mode are applied to the server only when you populate the report with data.




Figure 24-4: Design Mode (Structure Only)

- **Design mode (With Data)**—Allows you to view and modify the report with its data displayed. All the modifications applied in the report are automatically saved to the server. If you need to make extensive changes to an existing report, best practice is to make changes in Structure Only mode and then populate the report with data.




Figure 24-5: Design Mode (With Data)

Modifying the Report

The following section describes how to modify the Web Intelligence report as needed:

- [Modifying Report Elements](#)
- [Formatting the Report](#)
- [Data Access: Providing a Customized Variable](#)
- [Analysis: Providing Filters and Input Controls](#)
- [Page Setup: Adding Multiple Reports to a Document](#)

Modifying Report Elements

This section helps you to insert cells and charts; to convert tables to charts, and view a query summary.


- [Inserting Cells](#)
- [Inserting Charts](#)
- [Converting a Report to Tables or Charts](#)
- [Modifying Charts](#)
- [Viewing a Query Summary](#)

Inserting Cells



Task *To insert a new cell in the report*

1. On the Report Elements pane, click the **Cell** tab.
2. Then click the **Blank** icon to insert a cell.




Click to insert the cell here (Press ESC Key to cancel this action)

Inserting Charts




Task To insert a new chart in the report

1. On the Report Elements pane, select the required chart.




2. Right-click the table, and then select **Assign Data**.
3. In the Assign Data dialog box, modify the chart labels and title.



4. Click **OK**.

The following shows an example chart:



Converting a Report to Tables or Charts




Task *To convert a report into tables or charts*

Right-click a table and select **Turn Into** > <table or chart type>.

End Customer Country	End Customer City	Lin C
BD	Dhaka	
BD	Freiberg	
CG	undefined	
CL	-	
CL	Colina	
CL	Madrid	
CL	Puente Alto	
CL	Roebuck	
CL	San Miguel	
CL	Santiago	
CL	undefined	
CL	Viña del Mar	

- Cut Ctrl+X
- Copy Ctrl+C
- Paste Ctrl+V
- Comment...
- Delete
- Turn Into
 - Vertical Table
 - Horizontal Table
 - Cross Table
- Assign Data...
- Linking
 - Column Chart
 - Line Chart
 - Pie Chart
 - More Transformations... Ctrl+Shift+T
- Filter
- Sort
- Break
- Hide
- Order
- Align
- Format Table...

The following example shows the previous table converted to a column chart:



Modifying Charts



Task To modify a chart

Right-click the chart, and then select **Assign Data**.

Virtual dimension composed of Measure Name is restricted to one occurrence.

Category Axis

- Entitlement Id (Que... + - X
- Entitlement Descript... + - X
- Parent Bulk Entitle... + - X
- Order Id (Query 1) + - X
- Tenant Id (Query 1) + - X
- State Id (Query 1) + - X
- End Customer Acco... + - X
- End Customer City (... + - X
- End Customer Coun... + - X
- End Customer Resi... + - X

Buttons: OK, Cancel, Apply


You can add or delete an occurrence or edit its formula.

Viewing a Query Summary




Task To view the query summary of the report

1. On the Report Elements pane, click the **Cell** tab and select **Query Summary** from the drop-down menu.




2. Drag and drop the Query Summary input to the Reports screen.



Order Id	Tenant Id	State Id	End Custome	End Customer	End Custome
		19	US		UNKNOWN
6700		19	US		UNKNOWN
GERMANY		19	US		UNKNOWN
		19	US		UNKNOWN
		19			UNKNOWN

Click to insert the cell here (Press ESC Key to cancel this action)

The Query Summary is displayed:




Formatting the Report

This section helps you to format the table or chart by changing the font, border, or cell. It also helps you to align the table or chart, change styles, and apply headers and footers.




Task To format your report

1. On the Formatting pane, click the **Formatting** icon.



- 2. In the Format Table dialog box, select a format entity in the left pane to modify the report's general content display or its border, appearance, or layout.



Data Access: Providing a Customized Variable

This section helps you to replace null values with a customized variable in a report.



Task *To add values*


- 1. In the Report screen, select a cell with a null value.

Testing Report

Tenant Id	End Customer Country	Line Item Count
	AD	1
	AM	4
	FI	34
	GB	802


Tenant Id	End Customer Country	End Customer City	Line Item Count
	BD	Dhaka	1
	BD	Freiberg	1
	CG	undefined	6
	CL		22
	CL	Colina	1
	CL	Madrid	1
	CL	Puente Alto	1
	CL	Roebuck	1
	CL	San Miguel	1
	CL	Santiago	12
	CL	undefined	34
	CL	Viña del Mar	1

2. On the Data Access pane, click **New Variable**.



3. To replace the null value, enter a name and description for the variable.
4. Select a Qualification.
5. Define the formula for the given variable by selecting one or more object, functions, and operators.

The following example shows the setup for creating a new variable that replaces null values with a hyphen (-):



6. Click **OK** to complete creating a new variable.

The following example report shows the results of a variable that replaces null values with a hyphen. You can always rename variables.

Tenant Id	End Custome	Customer City	Line Item Count
	BD	Dhaka	1
	BD	Freiberg	1
	CG	undefined	6
	CL		22
..	CL	Colina	1
	CL	Madrid	1
	CL	Puente Alto	1
	CL	Roebuck	1
	CL	San Miguel	1
	CL	Santiago	12
	CL	undefined	34
	CL	Vifia del Mar	1

Analysis: Providing Filters and Input Controls

This section describes how to add a filter to a report or to an individual block in a report.


- Adding Filters
- Creating Input Control

Adding Filters




Task To add filter to the report


1. On the Analysis pane, select **Add Filter** from the Filter drop-down menu.



2. Right-click the column on which to create the filter, and then select **Filter > Add Filter**.



For a report with two or more blocks, use this same step to create a filter for either or both blocks.




Creating Input Control




Task To create an input control to restrict the unwanted data in the report


- 1. On the Analysis pane, click **Input Controls**.




- 2. In the Select Object dialog box, select the report object on which to assign the input control, and click **Next**.




- 3. In the Control Type dialog box, select a control type, provide its value properties, and click **Next**.



4. In the Assign Report Elements dialog box, select either **Entire document** or **Current report** to specify the scope of the input control.
5. Select the report elements, and then click **Finish**.



6. From the Side panel, select **Input Controls** to view the list of input control values for the selected object.




Page Setup: Adding Multiple Reports to a Document

This section helps you to add multiple reports to a document. (You can also format the page with headers and footers and scale it with margins.)



Task To insert multiple reports in a document


1. On the Page Setup pane, click **Add Report**.
2. Repeat this step for each report you want to add.



OR

You can also right click on an existing report tab to select **Add Report/Duplicate Report**.

3. Repeat the same step for each report you want to add.



The multiple reports are now available in the document.

Viewing the History of Reports

This section explains how to view a report's history.



Task To view the history of a report

1. On the Report Panel, click the **Documents** tab.
2. Select the required document to view the document details.
3. On the Details pane, right-click the required document.

	Title ^	Type	Last Run	Instances
	~Webintelligence	Folder		
	Test	Folder		
	New Document	Web Intelligence		0

- View
- Properties
- Modify
- Schedule
- Mobile Properties
- History
- Categories
- Document Link
- New >
- Organize >
- Send >
- Details


4. Click **History** to view the history details of the report.

Refreshing Reports

The 'refresh' icon:



is in multiple locations in both **Reading** and **Design** modes:



Also, there are different types of prompts. Some allow values to be selected from a list and others require values to be manually entered.



Task **To refresh a report**

1. Open the report to be refreshed.
2. Double-click left on the report tile to open it in 'View' mode, OR single-click right on the report title and click **View** from the pop-up menu of options.


	Title ^	Type	Last Run
	~Webintelligence	Folder	
	Mani	Folder	
	ENT - Entitlement Lines Expiring in X Days	Web Intelligence	
	Entitlements created by User	Web Intelligence	15-Nov-2020 11:20
	Milan Entitlement	Web Intelligence	
	New Web Intelligence Document2	Web Intelligence	
	Product Line Change in Download Report test	Web Intelligence	
	Test_entitlement	Web Intelligence	

View
Properties
Modify
Schedule



Task *To refresh your report each time you reopen it*

- 1. In the Document Summary dialog box for an existing document or one you are creating, select **Properties**, and then **Document**.
- 2. Select the **Refresh on open** check box to refresh the current report automatically every time you open the report.



Note • To improve report performance, refresh the document as needed instead of using **Refresh on open**.


Exporting Reports in Different Formats and Purpose

You can export a complete document or one/more reports to a text file, a PDF, an Excel spreadsheet, a CSV file, or a CSV archive. If you want to export raw data, only the .CSV format is available. You can select whether you want to export all data or just the data for specific queries. Except for the text file format, each file type has several settings available when you are in the Export dialog box.




Task To export a report

1. On the New Document panel, click the **Export** icon to export the reports.



2. Select either **Reports** or **Data**.



3. Select the File Type from the drop-down menu. The available file formats and their descriptions are described in the following table:

Format	Purpose
PDF	<ul style="list-style-type: none"> ● This format is useful to provide the document in a printable format. ● The page layout and formatting of the Web Intelligence report is retained in the PDF file. ● The PDF file is the exact copy of the document/report and can be shared to other users (non-BO users) via email, shared location. ● The data in the PDF cannot be modified by anyone.
Excel	<ul style="list-style-type: none"> ● Export excel means export snapshot of the generated report. ● This format is useful if you want to combine the information in Web Intelligence document with other data in an Excel spreadsheet. ● Unlike Web Intelligence documents, the Excel files are not connected to the database. You cannot refresh the data in the Excel file. To display up-to-date data in Excel format, refresh the Web Intelligence document and then save it as a new Excel file. ● Each report within the Web Intelligence document converts to a separate Excel worksheet within the Excel file. ● This format does not include the header and footer displayed in the Web Intelligence report. ● The charts are converted to images, not actual charts. ● SAP BO supports export as excel, you can customize or create new reports to export excel sheet and perform further pivot or other transformations with this excel data. ● If you have used drill functionality, cross-launch and hyperlinks inside the report, export to excel may not work as expected. The formatting and grouping of the Web Intelligence report is not retained in the Excel worksheet.
Text File	<ul style="list-style-type: none"> ● The groupings and columns of the Web Intelligence report is retained in the Text file. But the formatting (for example: Header row color) is not retained. ● In page mode, the report elements are exported page by page. ● The separator used is a tab space. ● The charts and images does not get exported. ● If several reports are selected, they are appended one after another in the same text file.

Format	Purpose
CSV File	<ul style="list-style-type: none">• The formatting and grouping of the Web Intelligence report is not retained in the CSV file.• Best choice for 'raw data' as its export data from microcube/data provider.• This format dumps the full content of all columns were retrieved from the database into the CSV file.• The computations and filters applied in the Web report are not applied in the CSV file.• Data providers does not result any output, users may see special chars due to object names used in the data providers.• The following properties can be configured:<ul style="list-style-type: none">• Text qualifier• Column Delimiter• Charset
CSV Archive	<ul style="list-style-type: none">• This format generates an archive file (.zip) that contains data from the document.• This format contains one CSV file per report from the document. Each CSV file contains the report data without any headers, footers, or charts.• This format supports all or only some of the reports to export in the CSV archive file.• This format is supported only from Rich Client and the SAP BusinessObjects Web Intelligence Launch pad. This format does not support Scheduling.• The exported data will be separated using comma, and text qualifier• The following properties can be configured:<ul style="list-style-type: none">• Text qualifier• Column Delimiter• Charset

4. Click **OK**.

Scheduling Reports

The following topics describe how to schedule a report:

- [Scheduling a Report](#)
- [Events Options for a Scheduled Report](#)

- Destination Options for a Scheduled Report
- Delivery Rules for Scheduled Documents
- Deleting a Report's Schedule
- Pausing a Report's Schedule
- Recycle Bin Accordion

Scheduling a Report




Important - You can only schedule reports from the My Favorites folder. If you attempt to schedule a report from a shared folder, the report will not run.



Task To schedule a report

1. Right click the report title.
2. From the drop-down menu click **Schedule**.
The Schedule window is displayed.
3. In the Recurrence panel, click the **Run object** drop-down menu, and select the desired option. For example, select **Weekly**.

The scheduling criteria are displayed.



Note - Based on the selected scheduling criteria, the subsequent menus are displayed for the reports to be run. In this example, since the Weekly option was chosen, the day(s) of the week is displayed and one of the days must be selected to run the scheduled report.

4. Select your desired options to run the report.

In this example, Friday is selected. The Start Date/Time and the End Date/Time settings specify the effective date/time range for this schedule. The default values make the schedule effective immediately and for a 10-year period. If you wish to change the default values, click the down pointing arrowheads to change the times. To change the date range, click the calendar icon or manually enter the start/end dates in the specified format.

Schedule – Test_entitlement

Schedule

- Instance Title
- Recurrence
- Formats
- Caching
- Events
- Scheduling Server Group
- Destinations
- Delivery Rules

Recurrence

Run object: Weekly

Object will run every week on the following days.

Monday Friday

Tuesday Saturday

Wednesday Sunday

Thursday

Start Date/Time: 05 07 30/12/2020

End Date/Time: 05 07 30/12/2030

December 2020

Sun	Mon	Tue	Wed	Thu	Fri	Sat
29	30	1	2	3	4	5
6	7	8	9	10	11	12
13	14	15	16	17	18	19
20	21	22	23	24	25	26
27	28	29	30	31	1	2
3	4	5	6	7	8	9



Note - If you want the report to be triggered by an event, the date when the report runs depends on the timing of the event. See [Events Options for a Scheduled Report](#).



Important - The daily refresh of the universes (with the exception of the universes listed above) finishes at 5:00 AM Pacific Time. It is recommended that you do not schedule a report to run between 00:00 and 5:00 AM Pacific Time, to avoid conflicts between the scheduled report running and the refresh. See [Data Refresh Intervals](#).

5. To set the output format for the scheduled report instances, under Schedule, click **Formats**.

Schedule – Test_entitlement

Schedule

- Instance Title
- Recurrence
- Formats
- Caching
- Events
- Scheduling Server Group
- Destinations
- Delivery Rules

Formats

Output Format


- Web Intelligence
- Microsoft Excel
- Adobe Acrobat
- Comma Separated Values (CSV) - Data
- Comma Separated Values (CSV) Archive - Reports
- Plain Text
- HTML Archive

Following are the most common output formats that are used:

Output Format	Description
Web Intelligence	By default, the Web Intelligence option is selected. Selecting this option is good if the report will be sent to the BI Inbox destination as this option sends the report in Business Objects report format.
Microsoft Excel	When you wish to send the reports to an email address, you can select this option. Selecting this option sends the report in Excel (.xlsx) format.
Adobe Acrobat	When you wish to send the reports to an email address, you can select this option. Selecting this option sends the report in PDF (.pdf) format.

- To define the destination to send the scheduled report, click **Destinations** and specify destination options, as described in [Destination Options for a Scheduled Report](#).

If the destination is not set, then by default the report will run as scheduled, but it will only be viewable as an instance on the report's History page.



- If desired, specify an event (see [Events Options for a Scheduled Report](#)).
- Click **Schedule**.

Events Options for a Scheduled Report

When you schedule a report with an event, the report runs after the specified event occurs.

The date when the report runs depends on the timing of the event. The only event that is available in this implementation is Daily Data Refresh, which occurs each day at 05:00 AM PST. When you schedule a report to be triggered by the Daily Data Refresh, you must schedule the report to run before 05:00 AM PST for the report to run on the same day. If you schedule the report to run after 05:00 AM PST, the report will run on the following day.



Task **To specify an event for a scheduled report**

1. Schedule the report as described in [Scheduling a Report, Step 1](#) through [Step 6](#).
2. In [Step 7](#), under Schedule, select **Events**.
3. The event that you select will trigger the scheduled report. Select the event in the **Available Events** list, and click > to move the event to the **Events to wait for** list.
4. Click **Schedule**.

Destination Options for a Scheduled Report

The destination options for a scheduled report are:

- [Default Enterprise Location](#)
- [BI Inbox](#)
- [Email](#)
- [FTP Server](#)
- [SFTP Server](#)
- [File System](#)



Note ▪ The most common destinations are [BI Inbox](#) and [Email](#).

Default Enterprise Location

The scheduled job will run on the Output File Repository Server (FRS). You do not need to set additional options for this destination. Historical instances are saved to the default Enterprise server but not to any other destination.

BI Inbox

Sends the object to a user's BI Inbox.

Setting the Destination to “BI Inbox”




Note ▪ You must know the Personnel ID of the recipient to use this destination.



Task **To set the destination to “BI Inbox”**

1. In the Destinations drop-down menu, select **BI Inbox**.
The corresponding options for BI Inbox are displayed.



2. Optionally, select the following check boxes:

- **Keep an instance in the history**—Saves a copy of the instance in the history.
- **Use default settings**—The report runs as scheduled but is not sent to any recipients.

If you want to select the recipients, leave this option unselected and specify the intended recipients using the options in Available Recipients (see below).

3. In the Available Recipients section, you can manually find the recipients or search recipients by using the search function.



Note - To search the recipients, use the **Personnel ID**.

4. Select the recipients' email ID and click the **Move** icon (>) to move the recipients to the Selected Recipients section.

5. Select an option for Target Name.



Note - By default, the **Use Automatically Generated Name** option is selected.

6. Under **Send As**, accept the default option (**Copy**).



Note - If you want to create a shortcut to the object, use **Shortcut** instead.

7. Click **Schedule**.

The report's History screen is displayed.

8. Click **Running/Recurring**. The report's status window is displayed.

History – Test_entitlement

View | Organize | Send | More Actions

Instance Time	Title	Status	Created By
30-Dec-2020 07:31	Test_entitlement	Running	UAT-1102
30-Dec-2020 07:26	Test_entitlement	Success	UAT-1102
30-Dec-2020 05:36	Test_entitlement	Success	UAT-1102

9. The defined Schedule is listed in the Status screen.

Sends the object to a user's BI Inbox.

Status

Title:	Test_entitlement
Document Type:	Web Intelligence
Status:	Recurring
Destination:	Inbox
Owner:	UAT-1102
Creation Time:	7/27/2021 12:30 PM
Next Run Time:	7/28/2021 12:28 PM
Recurrence Type:	Object runs once every 1 days.
Parent Object Path:	User Folders/UAT-1102/
Remote Instance in Federated Cluster:	No
Expiry:	7/27/2031 12:28 PM
Formats:	Web Intelligence
Parameters:	

Back

Email

Sends the object to a user's email address.

Setting the Destination to “Email”



Task To set the Destination to “Email”

1. In the Destinations drop-down menu, select **Email**.

The corresponding options for Email are displayed.

2. Optionally, select the following check boxes:

- **Keep an instance in the history**—Saves a copy of the instance in the history.
- **Use default settings**—The report runs as scheduled but is not sent to any recipients.

If you want to select the recipients, leave this option unselected and specify the intended recipients using the options below.

3. Enter your email address in the **From** field and recipient's email address in the **To** field, and add email addresses in **Cc** (optional), and **Bcc** (optional) fields.



Important - If you leave the **From** field blank, the object will be sent from the login of the user who is currently logged on. Using a **From** email other than one from the flexnetoperations.com domain may result in email being flagged as spam.

4. (Optional) Enter a subject and message for the email body.

5. If you want to include an attachment, select **Add Attachment**.

Under **File Name**, it is recommended that you select **Use Specific Name** and add the placeholder “Title”. Otherwise, an auto-generated string of characters will be appended to the file name.

6. Click **Schedule**.

The report's History screen is displayed.

FTP Server

Sends the object to an FTP (File Transfer Protocol) server location:

Table 24-1 • FTP Server Location Options

Option	Description
Destination	FTP server.
Keep an instance in the history	<p>Saves a copy of this instance in the document's history. This option is selected by default.</p> <p>If you want the BI platform to automatically delete the instance from the Output FRS to minimize the number of instances on the server, clear the Keep an instance in the history check box.</p>
Use default settings	<p>Uses the default Adaptive Job Server values for FTP Servers.</p> <ul style="list-style-type: none"> • If you do not want to use the default Adaptive Job Server values, clear the check box, and set the destination recipient options that appear. • You can change the values in the Servers area of the CMC. For more information, refer to the <i>SAP BusinessObjects Business Intelligence Platform Administrator Guide</i>.
Host	Enter the IP address of the FTP server host computer where you want to send the instance.
Port	Enter the port of the FTP server where you want to send the instance. The default is 21.




Table 24-1 • FTP Server Location Options

Option	Description
User Name	Enter a user name with access rights to upload the object to the FTP server.
Password	Enter the password required to access the FTP server.
Account	Enter the account required to access the FTP server. The account is part of the standard FTP protocol but is rarely implemented. Enter an account only if your FTP server requires it.
Directory	Enter the path to the FTP directory where you want to send the instance.
File Name	To use a system-generated file name for the instance, select Use Automatically Generated Name . <ul style="list-style-type: none"> To select the file name for the instance, select Use Specific Name, and enter a name or select variables for the file name from the Add Placeholder list. You can select from several types of variables: Title, ID, Owner, DateTime, (your) Email Address, (your) User Full Name, and File Extension. Select Add File Extension to automatically add the file extension to the instance file name. If you do not add a file extension, you might be unable to open the document.

SFTP Server

SFTP Destination support is one of the more interesting new features introduced with the recently released SAP BusinessObjects BI Platform 4.1 Support Pack 6.

SFTP protocol is a computing network protocol for accessing and managing files on remote file systems, similar to FTP. SFTP encrypts commands and data both, preventing passwords and sensitive information from being transmitted in the clear over a network. The advantages of having SFTP is that it allows secure transmission of data using Fingerprint authentication.



Task **Steps for SFTP scheduling**

1. The destination has to be enabled in CMC on the Adaptive Job Server. Enter the details of the SFTP Server, along with the SHA FingerPrint of the server. Contact your administrator to enable FTP/SFTP in CMC.

2. Enable the SFTP Server in CMC. Enter the SFTP Server details, along with the Fingerprint Value
 - **Host**—IP address of SFTP Server.
 - **Port**—Port of SFTP Server (the standard SFTP port is 22).
 - **Username**—Username to access SFTP Server
 - **Password**—Password to access SFTP Server.
 - **Account**—Account needed to access SFTP Server.
 - **Directory**—Directory location in SFTP Server where the document is to be delivered.
 - **File Name**—Select **Use Automatically Generated Name** or **Use Specific Name**.
 - **Fingerprint**—Host key fingerprint of the SFTP server and save the details.

File System

The **File System** destination type is not supported in this implementation.

Delivery Rules for Scheduled Documents

Prevent the sending of erroneous or empty documents by setting delivery rules for scheduled documents. Define a status for the documents that fail to meet the rules so you can identify them and reschedule them, change the connection details, or take other, appropriate action.

You define conditions that the document must meet for it to be sent to the following destinations:

- BI Inbox
- Email
- FTP server
- SFTP server

When the document fails to meet those conditions, it is not sent. You can choose one or both of the following conditions for a document:



Figure 24-6: Delivery Rules

- **The scheduled content has been successfully refreshed**—The document is sent only when all the data providers for the document have been successfully refreshed. A document that contains data from incomplete results isn't sent.
- **The scheduled content contains data**—The document is sent only when at least one report in the document contains data. An empty document isn't sent.

When you select a condition, you can also define the status that is displayed in the history for a document that fails to meet the condition, as follows:

- **Warning**
- **Failed**

The default status is **Warning**.

When you select both conditions for the sending of the document and the status of one condition is **Warning** and the status of the other condition is **Failed**, the history shows **Failed**.

Deleting a Report's Schedule


If you no longer require a report, you can delete the scheduled report instance. This will also remove the history of the report (including the scheduler and past results).

If you only want to stop the report temporarily to revisit it later, you can pause the report instead (see [Pausing a Report's Schedule](#)).




Task **To delete a report's schedule**

1. Open the History window.
2. Select the report.
3. Right-click the **Status** column of the report. From the context menu, click **Organize** and then **Delete**.



The Delete confirmation window is displayed.



4. Click **OK**.

Pausing a Report's Schedule

Pausing enables you to temporarily stop a scheduled report instance from running and resume it later.



Task **To pause a report's schedule**

1. Locate your scheduled report on the Documents tab.
2. Right click the report title to open the menu options and select **History**.
3. From the History page, select the report instance that you want to pause.



Tip - To select the report, avoid clicking the instance time, title, or status of the report, because this will open the instance itself. Instead, click anywhere in the report's row on a blank space.

4. Above the report, in the **More Actions** drop-down menu, click **Pause**.

The History window shows the status as "Paused".



Task **To resume a paused report**

1. Locate your report on the Documents tab.
2. Right click the report title to open the menu options and select **History**.
3. From the History page, select the paused report instance.
4. Above the report, in the **More Actions** drop-down menu, click **Resume**.

If the start date and time of the scheduled report are in the past, the report runs immediately. Otherwise, the report will run as per its scheduled date and time.

Recycle Bin Accordion

Note the following about the Recycle Bin accordion:

- The Recycle Bin accordion for the user is created in BI Launchpad only after the user has deleted any data.
- The 'Recycle Bin' is not visible under documents in BI Launchpad for the users.
- The behavior is the same for default enterprise administrator.
- The behavior is consistent for administrators and non-administrator users.
- The Recycle Bin accordion is visible for the user after the user deletes any data at least once.

Enabling Reports from Legacy Reporter

Scheduled reports in legacy Reporter are automatically copied to the new FlexNet Operations Reporter and set as paused to prevent the sending of duplicate reports. If you have any scheduled reports in legacy Reporter that should continue to run in the new FlexNet Operations Reporter, you must enable these reports in the new FlexNet Operations Reporter. Otherwise, they will not run in the new Reporter after the switch-over date on August 6, 2021.



Task **To reschedule a paused report**

1. Locate your scheduled report in the new FlexNet Operations Reporter. Scheduled reports typically show a value in the Instances column.
2. Right click the report title to open the menu options and select **History**.
3. From the History page, select the report instance that has **Paused** in the **Status** column.
4. Above the report, in the **More Actions** drop-down menu, click **Reschedule**.

The Reschedule window opens where you can review all parameters to reschedule the report. See [Scheduling Reports](#).



Note - If you decide not to reschedule now, you have the following options:

- **Resume:** The report runs immediately, because the start date and time of the report scheduled in the legacy Reporter is likely before today.
 - **Run Now:** The report runs immediately, regardless of its scheduled date and time.
5. For rescheduling a report, the Replace and Recurrence settings are the most significant. On the **Replace** panel, select one of the following options:
 - **Replace existing schedule**—This option overwrites the existing schedule that was paused. Select this if you do not want to create an additional scheduled instance of the report.
 - **Create new schedule from existing schedule**—This is the default and results in another scheduled instance of the report. This might be desirable if you want to create a similar schedule with different prompts or distribution.
 6. The Recurrence panel shows the original recurring schedule for the report. This reflects the original start date and time of the report, which is likely to be in the past. Update the **Start Date/Time** to reflect the next time you want the report to run. If the **Start Date/Time** is prior to today, the report will run immediately when scheduled.



Important • The End Date/Time must be after the Start Date/Time (including the time itself). If the end time is set before the start time (even if the end date is after the start date), the last scheduled report will not run.

7. Edit the values in the remaining panels as required (see [Scheduling Reports](#)).
8. Click **Schedule** in the lower right corner of the Reschedule page.
The History page shows the updated status for the report.
9. (Optional) On the **History** page, click the value in the **Status** field to see the scheduler parameters.

Reporter Standard Reports

FlexNet Operations Reporter includes a number of predefined, standard reports. This chapter describes each standard report, the prompts you can use to modify its output, and the attributes included in the report.

- [Before You Begin](#)
- [Standard Reports](#)



Tip • Reporter also allows users to create and share custom reports. For more advanced instructions see the *Business Objects* document, “Building Reports Using the Web Intelligence HTML Report Panel”, or click the help link in Reporter.

Before You Begin

Standard reports are available to producers who have access to Reporter. The following sections identify the permissions required to view reports and explain how to launch Reporter.

Producer Permissions for Reporter

Producers who are assigned to roles that have the **View Reports** permission can start Reporter. For more information about managing a user’s roles and permissions, see [Managing Accounts and Users](#).

Starting Reporter

Producers with the View Reports permission can start Reporter from the Producer Portal.



Task **To start Reporter**

In the Producer Portal, click **System > Reports**. The Producer Portal opens Reporter in a new window.

Standard reports are available in Reporter in the Folders drawer in the ALM Standard Reports folder (in the Public Folders directory). See the next section for details about each standard report. Double-click a report to configure its prompts and run it.

Standard Reports

This chapter describes the standard reports included for all producers and available to producer users with the required permissions to use Reporter.

For each report, you will find

- The name of the standard report and a description of its content and purpose
- A list of report filter prompts with prompt text and valid values
- A table of report output attributes and descriptions of those attributes
- A report output sample

To learn about a standard report's purpose, prompts, and attributes, see the section for that report.

Table 25-1 ▪ Standard Reports

Section	Description
ACT-Accounts Created in Last X Days	Shows all accounts created within the time range you specify.
ENT-Entitlement Lines Created in Last X Days	Shows all entitlement lines created within the time range you specify.
ENT-Entitlement Lines Expiring in X Days	Shows all entitlement lines expiring in the time range you specify.
ENT-Maintenance Expiring in Next X Days	Shows all maintenance lines expiring in the time range you specify.
FUL-Fulfillments Created in Last X Days	Shows all fulfillments created within the time range you specify.
FUL-Fulfillments with Returns/Rehosts/Reinstallations	Shows all fulfillments that were subject to return, rehost, and reinstall operations along with counts related to those operations. This report has prompts for you to specify the time range and, optionally, the account name on which to report.
PRD-Product Created in Last X Days	Shows all products created for the product name and version you identify and in the time range you specify.



Tip ▪ Reporter also allows users to create and share custom reports. For more advanced instructions see the *Business Objects* document, *Building Reports Using the Web Intelligence HTML Report Panel*, or click the *help* link in Reporter.

ACT-Accounts Created in Last X Days

The Accounts Created in Last X Days report shows recently created accounts with information about their account type, creation date, description, address, and number of users.

Report Prompts

This report has only one prompt to filter reports by their create date.

Prompt	Description
Account created between today - ? days and yesterday	Enter the number of days to set the date range for the report. For example, if you set the prompt to 365, the report returns a list of accounts created in the last year (between yesterday and the 365 days prior). Default: 100 days.

Report Attributes

The table, below, lists the attributes included in the Accounts Created in Last X Days report.

Attribute	Description
Account ID	A unique identifier of an organization's account as defined in FlexNet Operations. (For example, Stark International Enterprises.)
Account Name	A display name for an organization's account as defined in FlexNet Operations. (For example, Stark.) The Account Name is what FlexNet Operations displays on most of the Producer Portal and End-User Portal pages.
Account Type	The account type distinguishes between regular customer accounts (CUSTOMER), self-registered accounts (SELF_REGISTERED), channel partner accounts (CHANNEL_PARTNER), and producer accounts (PUBLISHER). Accounts without a standard account type are shown as UNKNOWN.
Account Create Date	The date the account was first created.
Account Description	The description associated the account.
Account Address Line 1	The first line of the optional street address of the account.
Account Address Line 2	The second line of the optional street address of the account.
Account City	The city for the address associated with the account.
Account Country	The country code for the account.

Attribute	Description
Account Region	The region where the account is situated. For instance, EMEA or APAC. Region is an optional field in the account-creation process and can contain any region designation the user enters.
Parent Account ID	The account ID of the parent account, if any.
Parent Account Name	The account name of the parent account, if any.
User Count	Number of users on the account.

Report Sample

The image, below, shows a sample of the Accounts Created in Last X Days report.

ACT - Accounts Created in Last X Days

Account ID	Account Name	Account Type	Account Create Date	Account Description	Account Address Line 1	Account Address Line 2	Account City	Account Country	Account Region	Parent Account ID	Parent Account Name	User Count
AACMidwest	AACMidwest	SELF_REGISTE	01/09/2018						UNKNOWN			1
AACWest	AACWest	SELF_REGISTE	01/10/2018						UNKNOWN			1
ABCAccount	ABCAccount	CUSTOMER	12/07/2017	TestAccount				US	UNKNOWN			1
ABTTestAccount	ABTTestAccount	CUSTOMER	12/07/2017	TestAccount				US	UNKNOWN			0
ABU SALIMA EL LIBI	ABU SALIMA EL LIBI	CUSTOMER	01/25/2018					US	UNKNOWN			1
AC4	AC4	PUBLISHER	01/19/2018						UNKNOWN	MYORG	My Organiza	0
ACC1-FEB031	ACC1-FEB031	CUSTOMER	02/03/2018					US	UNKNOWN			1
ACC1-FEB032	ACC1-FEB032	CUSTOMER	02/03/2018					US	UNKNOWN			1
ACC1-FEB033	ACC1-FEB033	CUSTOMER	02/03/2018					US	UNKNOWN			1
Acc1_V_18Jan	Acc1_V_18Jan	CUSTOMER	01/18/2018					US	UNKNOWN			2
Acc2_V_18Jan	Acc2_V_18Jan	CUSTOMER	01/18/2018					US	UNKNOWN			2
ACC_ESD_DEC4	ACC_ESD_DEC4	CUSTOMER	12/04/2017					US	UNKNOWN			0
Acc_ID	Acc_Name	CUSTOMER	01/08/2018					US	UNKNOWN			0
AccIDPublisher_V_5Jan	AccPublisher_V_5Jan	PUBLISHER	01/19/2018						UNKNOWN	MYORG	My Organiza	0

Figure 25-1: ACT-Accounts Created in Last X Days Report

ENT-Entitlement Lines Created in Last X Days

The Entitlement Lines Created in Last X Days report shows recently created entitlement lines with information about their owner, entitlement ID, activation ID, product name and version, as well as the entitlement lines' creation, expiration, and maintenance end dates.

Report Prompts

This report includes only one prompt with which you can set the number of passed days to look for created entitlement lines.

Prompt	Description
Line Item created between today - ? days and yesterday	Enter the number of days to set the date range for line items in the report. For example, if you set the prompt to 365, the report returns a list of line items created in the last year (between yesterday and the 365 days prior). Default: 100 days.

Report Attributes

The table, below, lists the attributes included in the Entitlement Lines Created in Last X Days report.

Attribute	Description
End Customer Account ID	The account ID for the end user (customer) account that owns the entitlement.
End Customer Account Name	A display name for the end user (customer) account that owns the entitlement.
Entitlement ID	The unique identifier of the entitlement as defined by FlexNet Operations.
Line Item Activation ID	The unique identifier of the entitlement line item as defined in FlexNet Operations.
Ordered Product Name	The name of the product or suite as defined in FlexNet Operations.
Ordered Product Version	The version of the product or suite as defined in FlexNet Operations.
Extended Seat Count	A count of the activated licenses. This count includes the number of copies of a given product purchased on its own as well as those copies included in a suite.
Line Item Created Date String	The date the entitlement line was created.
Line Item Expiration Date String	The expiration date of the entitlement line. If the entitlement line does not expire, Line Item Expiration Date String is PERMANENT .
Line Item Maintenance End Date	The expiration date of the maintenance line. This attribute may be blank if the maintenance line has no end date (permanent) or if the line item has not maintenance.

Report Sample

The image, below, shows a sample of the Entitlement Lines Created in Last X Days report.

ENT - Entitlement Lines Created in Last X Days

End Customer Account ID	End Customer Account Name	Entitlement ID	Line Item Activation ID	Ordered Product Name	Ordered Product Version	Extended Seat Count	Line Item Created Date String	Line Item Expiration Date String	Line Item Maintenance End Date
aaarshi.chatterjee@yahoo.com	trialOrg	ENT-56c5-ad6B-2Cfd-061	Act-ENT-56c5-ad6B-2Cfd-061-1	PJAN10AA	1.0	1	01/10/2018	04/20/2018	
Aberdeen	Aberdeen Golf	A-47dc-c40A-4E73-061	ACT-952d-c4A6-1573-061	UAT-Test-Prod	1.0	100	12/09/2017	PERMANENT	
ABU SALIMA EL LIBI	ABU SALIMA EL LIBI	ABUSALIMAELLIBI-37f9-92AF-58f2-161	ACT-f22a-929F-D1f2-161	AS-ESDProduct-12131	1.0	1	01/25/2018	12/31/2019	
ACC1-FEB031	ACC1-FEB031	E-FEB031	E-FEB031-LNM1	EDEC161	1.0	100	02/03/2018	02/28/2019	
ACC1-FEB032	ACC1-FEB032	E-ACC2-FEB032	E-ACC2-FEB032-LNM1	EC2	1.0	100	02/03/2018	02/28/2019	
ACC1-FEB033	ACC1-FEB033	E-ACC3-FEB033	E-ACC3-FEB033-LNM1	ECFEB021	1.0	100	02/03/2018	02/28/2019	
ACC_ESD_DEC4	ACC_ESD_DEC4	ENT_ESD_DEC4	ACT_LS_DEC4	product_dec41	1.0	100	12/04/2017	01/05/2019	
Acc_ID	Acc_Name	AID-26b4-5a16-404d-061	ACT-65d4-5a12-AE4d-061	P1_PRODUCT	1.0	1,000	01/08/2018	01/31/2019	
ACC_LS1_DEC14_BEYOND	ACC_LS1_DEC14_BEYOND	ENT_LS_DEC14_BEYOND_LOOKAHEAD	ACT_LS_DEC14_BEYOND_LOOK_AHEAD	Prod_ls_dec6	1.0	100	12/14/2017	11/29/2018	
ACC_LS1_DEC14_PERMANENT	ACC_LS1_DEC14_PERMANENT	ENT_LS1_DEC14_PERM	ACT_LS_DEC14_PERM	Prod_ls_dec6	1.0	100	12/14/2017	PERMANENT	
ACC_LS_DEC5_1	ACC_LS_DEC5_1	ENT_LS_DEC5_1_AUTOPROVISION	ACT_LS_DEC5_AUTOPROV	prod_ls_autoprovision_de	1.0	100	12/05/2017	12/25/2017	
ACC_LS_DEC5_MUL	ACC_LS_DEC5_MUL	ENT_DEC5_MUL	ACT_LS_MUL1_DEC5	prod_ls_fc	1.0	100	12/05/2017	12/25/2017	

Figure 25-2: ENT-Entitlement Lines Created in Last X Days Report

ENT-Entitlement Lines Expiring in X Days

The Entitlement Lines Expiring in X Days report shows expiring entitlement lines with information about their owner, entitlement ID, activation ID, product name and version, as well as the entitlement lines' expiration and maintenance end dates.

Report Prompts

This report includes only one prompt with which you can set the number of days in the future to look for expiring entitlement lines.

Prompt	Description
Line Item Expiration Date between today and days in the future	<p>Enter the number of days to set the date range for line items in the report.</p> <p>For example, if you set the prompt to 365, the report returns a list of line items that expire in the next year (between today and the next 365 days).</p> <p>Default: 1 day.</p>

Report Attributes

The table, below, lists the attributes included in the Entitlement Lines Expiring in X Days report.

Attribute	Description
End Customer Account ID	The account ID for the end-user (customer) account that owns the entitlement.
End Customer Account Name	A display name for the end-user (customer) account that owns the entitlement.
Entitlement ID	The unique identifier of the entitlement as defined by FlexNet Operations.
Line Item Activation ID	The unique identifier of the entitlement line item as defined in FlexNet Operations.

Attribute	Description
Ordered Product Name	The name of the product or suite as defined in FlexNet Operations.
Ordered Product Version	The version of the product or suite as defined in FlexNet Operations.
Extended Seat Count	A count of the activated licenses. This count includes the number of copies of a given product purchased on its own as well as those copies included in a suite.
Line Item Expiration Date String	The expiration date of the entitlement line.
Line Item Maintenance End Date String	The expiration date of the maintenance line.

Report Sample

The image, below, shows a sample of the Entitlement Lines Expiring in X Days report.

ENT - Entitlement Lines Expiring in X Days									
End Customer Account ID	End Customer Account Name	Entitlement Id	Line Item Activation Id	Ordered Product Name	Ordered Product Version	Extended Seat Count	Line Item Expiration Date String	Line Item Maintenance End Date	
24org	24org	CVSTEST-PERM-E1	CVSTEST-PERM-E1-UNLBRW	CVS-Borrow	1.0	10	02/28/2018		
ACC_LS_FEB3_CON_IN_HEALTHY	ACC_LS_FEB3_CON_IN_HEALTHY	ENT_LS_FEB3_CON_IN_HEALTHY	ACT_LS_FEB3_CON_IN_HEALTHY	PROD1_FEB3	1.0	100	02/28/2018		
ACC_LS_FEB3_CON_IN_WARNING	ACC_LS_FEB3_CON_IN_WARNING	ENT_LS_FEB3_CON_IN_WARNING	ACT_LS_FEB3_CON_IN_WARNING	PROD1_FEB3	1.0	100	02/28/2018		
ACC_LS_FEB3_REN_IN_HEALTHY	ACC_LS_FEB3_REN_IN_HEALTHY	ENT_LS_FEB3_REN_IN_HEALTHY	ACT_LS_FEB3_REN_IN_HEALTHY	PROD1_FEB3	1.0	100	02/28/2018		
ACC_LS_FEB3_REN_IN_RISK	ACC_LS_FEB3_REN_IN_RISK	ENT_LS_FEB3_REN_IN_RISK	ACT_LS_FEB3_REN_IN_RISK	PROD1_FEB3	1.0	100	02/28/2018		
ACC_LS_FEB3_STEP1	ACC_LS_FEB3_STEP1	ENT_LS_FEB3_STEP1	ACT_LS_FEB3_STEP1	PROD1_FEB3	1.0	100	02/28/2018		
ACC_LS_FEB3_STEP12	ACC_LS_FEB3_STEP12	ENT_LS_FEB3_STEP12	ACT_LS_STEP12_1	P_LS_1	1.0	100	02/28/2018		
ACC_LS_FEB3_STEP12	ACC_LS_FEB3_STEP12	ENT_LS_FEB3_STEP12	ACT_LS_STEP12_1	P_LS_2	1.0	100	02/28/2018		
ACC_LS_FEB3_STEP12	ACC_LS_FEB3_STEP12	ENT_LS_FEB3_STEP12	ACT_LS_STEP12_1	P_LS_3	1.0	100	02/28/2018		
ACC_LS_FEB3_STEP12	ACC_LS_FEB3_STEP12	ENT_LS_FEB3_STEP12	ACT_LS_STEP12_2	P_LS_1	1.0	1,000	02/28/2018		
ACC_LS_FEB3_STEP12	ACC_LS_FEB3_STEP12	ENT_LS_FEB3_STEP12	ACT_LS_STEP12_2	P_LS_3	1.0	1,000	02/28/2018		
ACC_LS_FEB3_STEP12	ACC_LS_FEB3_STEP12	ENT_LS_FEB3_STEP12	ACT_LS_STEP12_2	P_LS_2	1.0	1,000	02/28/2018		
ACC_LS_FEB3_STEP12	ACC_LS_FEB3_STEP12	ENT_LS_FEB3_STEP12	ACT_LS_STEP12_3	P_LS_3	1.0	1,000	02/28/2018		
ACC_LS_FEB3_STEP16	ACC_LS_FEB3_STEP16	ENT_LS_FEB3_STEP16	ACT_LS_CHILD_STEP16	prod_ls_child	1.0	0	02/28/2018		
ACC_LS_FEB3_STEP16	ACC_LS_FEB3_STEP16	ENT_LS_FEB3_STEP16	ACT_LS_PARENT_STEP16	prod_ls_parent	1.0	100	02/28/2018		
ACC_LS_FEB3_STEP16	ACC_LS_FEB3_STEP16	ENT_LS_FEB3_STEP16	nsbFC-5R31-07FD-12a5-161	prod_ls_child	1.0	0	02/28/2018		

Figure 25-3: ENT-Entitlement Lines Expiring in X Days Report

ENT-Maintenance Expiring in Next X Days

The Maintenance Expiring in Next X Days report shows expiring maintenance lines with information about their owner, entitlement ID, activation ID, product name and version, as well as the entitlement lines' expiration and maintenance end dates.

Report Prompts

This report includes only one prompt with which you can set the number of days in the future to look for expiring maintenance lines.

Prompt	Description
Line Item Maintenance End Date between today and days in the future	<p>Enter the number of days to set the date range for line items in the report. For example, if you set the prompt to 365, the report returns a list of maintenance line items that expire in the next year (between today and the next 365 days).</p> <p>Default: 100 days.</p>

Report Attributes

The table, below, lists the attributes included in the Maintenance Expiring in Next X Days report.

Attribute	Description
End Customer Account ID	The account ID for the end user (customer) account that owns the entitlement.
End Customer Account Name	A display name for the end user (customer) account that owns the entitlement.
Entitlement ID	The unique identifier of the entitlement as defined by FlexNet Operations.
Line Item Activation ID	The unique identifier of the entitlement line item as defined in FlexNet Operations.
Ordered Product Name	The name of the product or suite as defined in FlexNet Operations.
Ordered Product Version	The version of the product or suite as defined in FlexNet Operations.
Net Orders Seat Count	The net copies available for the maintenance line. This count includes all new, upgrade, upsell, and renew orders, and excludes all upgraded, upsold, renewed, obsolete, and inactive orders for a maintenance line.
Maintenance Activation ID	The unique identifier of the maintenance line as defined in FlexNet Operations.
Maintenance Start Date	The date on which maintenance begins.
Maintenance End Date	The date on which maintenance ends.
Maintenance Product	The name of the maintenance product.
Maintenance Part Number	The part number to which the maintenance line is linked.

Report Sample

The image, below, shows a sample of the Maintenance Expiring in Next X Days report.

ENT - Maintenance Expiring in Next X Days											
End Customer Account ID	End Customer Account Name	Entitlement Id	Line Item Activation Id	Ordered Product Name	Ordered Product Version	Net Orders Seat Count	Maintenance Activation Id	Maintenance Start Date	Maintenance End Date	Maintenance Product	Maintenance Part Number
24org	24org	S_15MEnt	S_15MEnt_1	S_15MP1	4	15	S_15MEnt_main	03/16/2017	03/28/2018	S_15Mm1	
customer123	customer123	S_3NEnt1	S_3NEnt1_1	S_3NPR1	2.0	100	S_3Nmaint2	11/03/2017	03/08/2018	S_3NMain1	
customer123	customer123	S_3NEnt1	S_3NEnt1_2	S_3NPR1	2.0	100	S_3Nmaint2	11/03/2017	03/08/2018	S_3NMain1	
customer123	customer123	S_3NEnt1	S_3NEnt1_2	S_3NPR1	2.0	100	S_3Nmaint4	11/03/2017	03/08/2018	S_3NMain1	S_3Npart
customer123	customer123	S_3Nent2	S_3Nent2_1	S_3NPR1	2.0	100	S_3Nmaint3	11/03/2017	03/08/2018	S_3NMain1	

Figure 25-4: ENT-Maintenance Expiring in Next X Days Report

FUL-Fulfillments Created in Last X Days

The Fulfillments Created in Last X Days report shows recently created fulfillments with information about their owner, entitlement ID, activation ID, product name and version, as well as the entitlement lines' creation, expiration, and maintenance end dates.

Report Prompts

This report includes only one prompt with which you can set the number of passed days to look for created fulfillments.

Prompt	Description
Fulfillments created between today - ? days and yesterday	Enter the number of days to set the date range for fulfillments in the report. For example, if you set the prompt to 365, the report returns a list of fulfillments created in the last year (between today and the prior 365 days). Default: 1 day.


Report Attributes

The table, below, lists the attributes included in the Fulfillments Created in Last X Days report.

Attribute	Description
Account ID	A unique name of an organization's account as defined in FlexNet Operations. (For example, Stark International Enterprises.)
Account Name	A display name for an organization's account as defined in FlexNet Operations. (For example, Stark.)
Ordered Product Name	The name of the product or suite as defined in FlexNet Operations.
Ordered Product Version	The version of the product or suite as defined in FlexNet Operations.

Attribute	Description
Part Number	The part number to which the fulfillment is linked, if any.
Entitlement ID	The unique identifier of the entitlement as defined by FlexNet Operations.
Line Item Activation ID	The unique identifier of the entitlement line item as defined in FlexNet Operations.
Line Item Current State	The state of the line item: Deployed, Inactive, or Obsolete.
Fulfillment ID	A unique identifier for the fulfillment record.
Fulfillment Status	The state of the fulfillment record: ACTIVE or OBSOLETE.
Activation Type	<p>The method of activation. Activation Type can be SHORTCODE, MANUAL, PROGRAMMATIC, CERTIFICATE, TRUSTED, EMBEDDED, or CUSTOM.</p> <ul style="list-style-type: none"> ● SHORTCODE—Trusted storage fulfillment records generated using short code activation. ● MANUAL—Trusted storage fulfillment records generated using manual (or offline activation) processing of the request and response XML files. ● PROGRAMMATIC—Trusted storage fulfillment records generated using regular online activation from the client. ● CERTIFICATE—Certificate licenses. ● TRUSTED—Legacy trusted storage fulfillment records which do not have specific information about how they were activated. ● EMBEDDED—Licenses generated using FlexNet Embedded for hardware devices. ● CUSTOM—Fulfillment records that belong to any non-FlexNet licensing technology.

Attribute	Description
<p>Lifecycle Status</p>	<p>The lifecycle support action on the fulfillment record, if any. Lifecycle Status can be MASTER, DELETE, RETURN, REHOST, REPAIR, REINSTALL, RENEW, EMERGENCY, STOPGAP, TRANSFER, UPGRADE, UPSSELL, PUBLISHER_ERROR, or NULL (blank).</p> <ul style="list-style-type: none"> ● MASTER—A new fulfillment record. No support lifecycle operations have been performed on this fulfillment. ● RETURN—A fulfillment record that has been returned. ● REHOST—A fulfillment record that has been rehosted. ● REPAIR—A fulfillment record that has been repaired. ● REINSTALL—A fulfillment record that has been reinstalled. ● RENEW—A fulfillment record that has been renewed to another fulfillment record. ● EMERGENCY—A fulfillment record that was created as an emergency license. ● STOPGAP—A fulfillment record that was created as a stop gap license. ● UPGRADE—A fulfillment record that was upgraded to another fulfillment record. ● UPSSELL—A fulfillment record that was upsold to another fulfillment record. ● DELETE—A fulfillment that was deleted. Deleted fulfillments do not appear in the Producer Portal or the End-User Portal. ● PUBLISHER_ERROR—A fulfillment flagged by the producer as an error. ● TRANSFER—A fulfillment record that has been transferred to a different account.
<p>Platform Type</p>	<p>The platform on which the license was activated, if available. Platform Type can be any of the supported platform types reported by the FlexNet client, such as i86n3 (Windows), i86re3 (Linux), Mac, and so forth. If the client did not report a platform type, this report shows UNKNOWN.</p>

Attribute	Description
Fulfillment Source	<p>The activation process used for fulfillment. Fulfillment Source can be ONLINE, APPLICATION, or LEGACY.</p> <ul style="list-style-type: none"> ● ONLINE—For fulfillment records generated using web services. ● APPLICATION—For fulfillment records generated using the FlexNet Operations user interface. ● LEGACY—Used for legacy fulfillment records that do not have information about how the fulfillment records were generated.
Host ID	<p>The host on which the license was activated.</p> <ul style="list-style-type: none"> ● For certificate licenses, Host ID is the usual host identifier (such as INTERNET=64.0.0.1). ● For trusted licenses, Host ID is UMN or Machine Identifier. ● For non-FlexNet technologies, Host ID is the custom host identifier. <p></p> <p>Note - See <i>Special Host ID Types</i> in the <i>FlexNet Operations User Guide</i> for more information about host ID types.</p>
Active Fulfillment Count	The number of active fulfillments for a given ordered product.
Obsolete Fulfillment Count	The number of fulfillments that were changed to obsolete.
Upgrade Fulfillment Count	The number of fulfillments generated from upgrade licenses (purchased as an upgrade from another product version).
Rehost Fulfillment Count	The number of fulfillments of a given ordered product that were rehosted.
Return Fulfillment Count	The number of fulfillments of a given ordered product that were returned.
Repair Fulfillment Count	The number of fulfillments that had to be repaired. (FlexNet Operations supports the repair operation for both trusted and certificate licenses.)
Reinstall Fulfillment Count	The number of fulfillments that were reinstalled. (Reinstalls are relevant only for trusted storage licenses. A trust storage activation request coming from the same machine for the same activation ID is deemed a reinstall.)
Upsell Fulfillment Count	The number of fulfillments generated from upsell licenses (purchased as an upsell from another product).
Stop Gap Fulfillment Count	The number of fulfillments generated as stop gap licenses. (Stop gap fulfillments are supported only for certificate and custom licenses.)

Item State	Fulfillment Id	Fulfillment Status	Activation Type	Lifecycle Status	Platform Type	Fulfillment Source	Host Id	Active Fulfillment Count
YED	GCO-GECB-0193-52E0-7F15-161	ACTIVE	CERTIFICATE	EMERGENCY	UNKNOWN	APPLICATION	COMPOSITE=52	
YED	GCO-GECB-32c3-6277-9E15-161	OBSOLETE	CERTIFICATE	REHOST	UNKNOWN	APPLICATION	COMPOSITE=51	
YED	GCO-GECB-7eb7-42B7-E015-161	ACTIVE	CERTIFICATE	STOPGAP	UNKNOWN	APPLICATION	COMPOSITE=51	
YED	GCO-GECB-8ae5-22A4-3015-161	ACTIVE	CERTIFICATE		UNKNOWN	APPLICATION	COMPOSITE=50	2
YED	GCO-GECB-aa0a-52E0-C715-161	OBSOLETE	CERTIFICATE	RETURN	UNKNOWN	APPLICATION	COMPOSITE=51	3
YED	GCO-GECB-b43c-a48A-9915-161	ACTIVE	CERTIFICATE		UNKNOWN	APPLICATION	COMPOSITE=6	
YED	GCO-GECB-d55e-3246-5E15-161	OBSOLETE	CERTIFICATE	REPAIR	UNKNOWN	APPLICATION	COMPOSITE=51	3
YED	GCO-GECB-e11e-62AC-EE15-161	OBSOLETE	CERTIFICATE	UPGRADE	UNKNOWN	APPLICATION	COMPOSITE=6	
YED	GCO-GECB-ecbe-84F9-FF15-161	OBSOLETE	CERTIFICATE	UPSELL	UNKNOWN	APPLICATION	COMPOSITE=6	2
YED	GCO-GECB-edf1-a43A-4515-161	OBSOLETE	CERTIFICATE	RENEW	UNKNOWN	APPLICATION	COMPOSITE=6	
YED	GCO-GECB-bb1c-a46A-2A15-161	ACTIVE	CERTIFICATE		UNKNOWN	APPLICATION	COMPOSITE=6	
YED	TWORGID-TW-e35f-c750-9A33-161	ACTIVE	CERTIFICATE		UNKNOWN	APPLICATION	HOSTNAME=ASC	
YED	TWORGID-TW-f080-aaC3-91b9-161	ACTIVE	CERTIFICATE		UNKNOWN	APPLICATION	HOSTNAME=ASC	
YED	WILY-Sr-d821-c751-5C3e-f51	ACTIVE	CERTIFICATE		UNKNOWN	APPLICATION	COMPOSITE=54	
YED	WILY-Sr-80c3-b815-343e-f51	ACTIVE	CERTIFICATE		UNKNOWN	APPLICATION	COMPOSITE=9	
YED	WILY-Sr-12b3-58EE-113e-f51	OBSOLETE	CERTIFICATE	REPAIR	UNKNOWN	APPLICATION	COMPOSITE=7	8
YED	WILY-Sr-376b-7843-C53e-f51	ACTIVE	CERTIFICATE		UNKNOWN	APPLICATION	COMPOSITE=8	1
YED	WILY-Sr-4669-58D4-843e-f51	OBSOLETE	CERTIFICATE	REHOST	UNKNOWN	APPLICATION	COMPOSITE=9	
YED	WILY-Sr-6d65-b816-103e-f51	ACTIVE	CERTIFICATE		UNKNOWN	APPLICATION	COMPOSITE=7	

Active Fulfillment Count	Obsolete Fulfillment Count	Upgrade Fulfillment Count	Rehost Fulfillment Count	Return Fulfillment Count	Repair Fulfillment Count	Reinstall Fulfillment Count	Upsell Fulfillment Count	Stop Gap Fulfillment Count	Emergency Fulfillment Count	Transferred Fulfillment Count	Obsoleted Fulfillment Count	Net Fulfillment Count
0	0	0	0	0	0	0	0	0	30	0	0	0
29	29	0	29	0	0	0	0	0	0	0	29	0
0	0	0	0	0	0	0	0	30	0	0	0	0
20	0	0	0	0	0	0	0	0	0	0	0	20
30	1	0	0	1	0	0	0	0	0	0	1	29
14	0	0	0	0	0	0	0	0	0	0	0	14
30	30	0	0	0	30	0	0	0	0	0	30	0
29	5	5	0	0	0	0	0	0	0	0	5	24
24	0	0	0	0	0	0	0	5	0	0	5	19
19	0	0	0	0	0	0	0	0	0	0	5	14
5	0	0	0	0	0	0	0	0	0	0	0	5
2	0	0	0	0	0	0	0	0	0	0	0	2
1	0	0	0	0	0	0	0	0	0	0	0	1
24	0	0	0	0	0	0	0	0	0	0	0	24
3	0	0	0	0	0	0	0	0	0	0	0	3
80	80	0	0	0	80	0	0	0	0	0	80	0
10	0	0	0	0	0	0	0	0	0	0	0	10
80	10	0	10	0	0	0	0	0	0	0	10	70
1	0	0	0	0	0	0	0	0	0	0	0	1

Figure 25-5: FUL-Fulfillments Created in Last X Days Report

FUL-Fulfillments with Returns/Rehosts/Reinstallations

The Fulfillments with Returns/Rehosts/Reinstallations report shows the number of returns, rehosts, and reinstallations for each account's ordered products.

Report Prompts

This report has prompts to limit the fulfillments in the report by their creation date and by their account name.

Prompt	Description
Enter Earliest Fulfillment Create Date	<p>Required.</p> <p>Click the Calendar button to set the date. In the Calendar popup, click Today to set to the current date.</p> <p>Default: 01 January 1970.</p>
Enter Last Fulfillment Create Date	<p>Required.</p> <p>Click the Calendar button to set the date. In the Calendar popup, click Today to set to the current date.</p> <p>Default: 31 December 9999.</p>
Enter Account Name	<p>Optional. The name or partial name for the account.</p> <p>Use % as a wildcard character.</p> <p>This prompt is not case sensitive.</p> <p>If you do not enter a value for the account name, Reporter does not restrict report content by account name.</p>

Report Attributes

The Fulfillments with Returns/Rehosts/Reinstallations report includes eight attributes and shows rehost, return, and reinstall counts by account and product.

Attribute	Description
Account ID	A unique name of an organization's account as defined in FlexNet Operations. (For example, Stark International Enterprises.)
Account Name	A display name for an organization's account as defined in FlexNet Operations. (For example, Stark.)
Ordered Product Name	The name of the product or suite as defined in FlexNet Operations.
Ordered Product Version	The version of the product or suite as defined in FlexNet Operations.
Rehost Fulfillment Count	The number of fulfillments of a given ordered product that were rehosted.
Return Fulfillment Count	The number of fulfillments of a given ordered product that were returned.

Attribute	Description
Reinstall Fulfillment Count	The number of fulfillments that were reinstalled. (Reinstalls are relevant only for trusted storage licenses. A trust storage activation request coming from the same machine for the same activation ID is deemed a reinstall.)
Total Return/Rehost/Reinstall	The sum of fulfillments that were returned, rehosted, or reinstalled for a given ordered product.

Report Sample

FUL - Fulfillments with Returns/Rehosts/Reinstallations							
Account ID	Account Name	Ordered Product Name	Ordered Product Version	Rehost Fulfillment Count	Return Fulfillment Count	Reinstall Fulfillment Count	Total Rehost / Return / Reinstall
UNKNOWN_ORG_	Information Not Available	test23	1.0	0	16,022	0	16,022
AS_Customer_01	AS_Customer_01	FNP_Trusted_ServerActivation	1.0	0	5,002	0	5,002
AS_Customer_01	AS_Customer_01	FNP_Trusted_ServerActivation_Windows	1.0	0	1,001	0	1,001
ACC_LS_FEB3_CC	ACC_LS_FEB3_CON_IN_HEAL	PROD1_FEB3	1.0	0	160	0	160
UNKNOWN_ORG_	Information Not Available	PR1	1.0	0	101	0	101
ACME	Software Corporation	FT3	1.0	0	100	0	100
ACC_LS_FEB3_RE	ACC_LS_FEB3_REN_IN_HEAL	PROD1_FEB3	1.0	0	80	0	80
ACC_LS_FEB3_RE	ACC_LS_FEB3_REN_IN_RISK	PROD1_FEB3	1.0	0	80	0	80
ACC_LS_FEB3_RE	ACC_LS_FEB3_REN_IN_WARN	PROD1_FEB3	1.0	0	50	0	50
ACC_LS_FEB3_ST	ACC_LS_FEB3_STEP7	PROD1_FEB3	1.0	0	50	0	50
Generic_Cust_Org	Generic_Cust_Org	Gen_SOAP_31Jan_Prod1	1.1	35	7	0	42

Figure 25-6: FUL-Fulfillments with Returns/Rehosts/Reinstallations Report

PRD-Product Created in Last X Days

The Product Created in Last X Days report allows you to set a product-creation date range and a product name and version to show matching products with their current status and their actual creation dates.

Report Prompts

This report has prompts to limit the products in the report by their creation date and by their account name.

Prompt	Description
Products Created Between Today - ? Days and Yesterday	Enter the number of days to set the date range for the report. For example, if you set the prompt to 365, the report returns a list of products created in the last year (between yesterday and the 365 days prior). Default: 10 days.

Prompt	Description
Product Name and Version Matches	<p>Required. The name or partial name and version for the product.</p> <p>Use * as a wildcard character.</p> <p>To set a specific product name and version, enter <code><product_name>::<version></code>. For example, <code>PhotoPrint::1.0</code> or <code>Photo*</code>.</p> <p>Default: *</p>

Report Attributes

The Products Created in Last X Days report shows only four attributes in the report output: Product Name, Product Name and Version, Product Status, and Product Create Date.

The report shows the products and versions that meet the criteria expressed in your report prompts along with their current status and creation date.

Attribute	Description
Product Name	The name of the product.
Product Name and Version	The combined product name and version in the format <code>productname::version</code> .
Product Status	<p>The current status of the product. A product's status can be Active, Inactive, or Missing.</p> <p>Products that are deleted have an Inactive value for Product Status.</p> <p>(Missing is a special value used to facilitate reporting on entire product categories and showing download packages that have no parent product.)</p>
Product Create Date	The month, day, and year in which the product was created.

Report Sample

The image, below, shows a sample of the Products Created in Last X Days report.

PRD - Product Created In Last X Days

Product Name	Product Name and Version	Product Status	Product Create Date
3STS_pro1	3STS_pro1::1.0	Active	02/20/2018
DELIVERS_ONE_COUNTED	DELIVERS_ONE_COUNTED::1.0	Active	02/27/2018
FNE_BASE_FOR_UPGRADE	FNE_BASE_FOR_UPGRADE::1.0	Active	02/27/2018
FNE_UPGRADE	FNE_UPGRADE::2.0	Active	02/27/2018
ksaurabh_1p	ksaurabh_1p::1.0	Active	02/26/2018
PRO_3Svr1	PRO_3Svr1::1.0	Active	02/20/2018
PRO_3Svr2	PRO_3Svr2::1.0	Active	02/20/2018
RF_SANITY_wsProd_1519283078457	RF_SANITY_wsProd_1519283078457::1.0	Active	02/21/2018
RF_SANITY_wsProd_1519284377041	RF_SANITY_wsProd_1519284377041::1.0	Active	02/21/2018
RF_SANITY_wsProd_1519695847296	RF_SANITY_wsProd_1519695847296::1.0	Active	02/26/2018
RF_SANITY_wsProd_1519698704888	RF_SANITY_wsProd_1519698704888::1.0	Active	02/26/2018
RF_SANITY_wsProd_1519868639818	RF_SANITY_wsProd_1519868639818::1.0	Active	02/28/2018

Figure 25-7: Products Created in Last X Days Report